
FASTR Documentation

Release 3.1.2

Fastr contributors

Jun 18, 2019

CONTENTS

1 FASTR Documentation	3
1.1 Introduction	3
1.1.1 Philosophy	3
1.1.2 System overview	3
1.2 Quick start guide	5
1.2.1 Installation	5
1.2.2 Configuration	6
1.2.3 Creating a simple network	6
1.2.4 Running a Network	9
1.3 User Manual	9
1.3.1 Tools	10
1.3.2 Network	13
1.3.3 Data Flow	15
1.3.4 DataTypes	20
1.3.5 Execution	21
1.3.6 IOPlugins	22
1.3.7 Secrets	22
1.3.8 Debugging	22
1.3.9 Naming Convention	27
1.3.10 Provenance	28
1.4 Command Line Tools	29
1.4.1 fastr cat	29
1.4.2 fastr dump	29
1.4.3 fastr execute	30
1.4.4 fastr extract_argparse	30
1.4.5 fastr provenance	30
1.4.6 fastr pylint	31
1.4.7 fastr report	31
1.4.8 fastr run	31
1.4.9 fastr sink	32
1.4.10 fastr source	32
1.4.11 fastr test	32
1.4.12 fastr trace	33
1.4.13 fastr upgrade	34
1.4.14 fastr verify	34
1.4.15 fastr webapp	34
1.5 Resource File Formats	35
1.5.1 Config file	35
1.5.2 Tool description	39
1.6 Plugin Reference	39

1.6.1	CollectorPlugin Reference	39
1.6.2	ExecutionPlugin Reference	41
1.6.3	FlowPlugin Reference	44
1.6.4	IOPlugin Reference	45
1.6.5	Interface Reference	50
1.6.6	ReportingPlugin Reference	52
1.6.7	Target Reference	53
1.7	Development and Design Documentation	55
1.7.1	Sample flow in Fastr	56
1.7.2	Network Execution	58
1.7.3	Secrets	60
1.8	Changelog	62
1.8.1	3.1.2 - 2019-06-18	62
1.8.2	3.1.1 - 2019-05-02	62
1.8.3	3.1.0 - 2019-05-02	63
1.8.4	3.0.1 - 2019-03-28	63
1.8.5	3.0.0 - 2019-03-05	63
1.8.6	2.1.2 - 2018-10-24	64
1.8.7	2.1.1 - 2018-06-29	64
1.8.8	2.1.0 - 2018-04-13	65
1.8.9	2.0.1 - 2017-10-19	65
1.8.10	2.0.0 - 2017-09-28	65
1.8.11	1.2.2 - 2017-08-24	66
1.8.12	1.2.1 - 2017-04-04	67
1.8.13	1.2.0 - 2017-03-15	67
1.8.14	1.1.2 - 2016-12-22	68
1.8.15	1.1.1 - 2016-12-22	68
1.8.16	1.1.0 - 2016-12-08	68
2	FASTR User reference	71
2.1	Fastr User Reference	71
3	FASTR Developer Module reference	79
3.1	fastr Package	79
3.1.1	fastr Package	79
3.1.2	exceptions Module	79
3.1.3	version Module	87
3.1.4	Subpackages	88
4	Indices and tables	253
	Python Module Index	255
	Index	257

FASTR is a framework that helps creating workflows of different tools. The workflows created in FASTR are automatically enhanced with flexible data input/output, execution options (local, cluster, etc) and solid provenance.

We chose to create tools by creating wrappers around executables and connecting everything with Python.

Fastr is open-source (licensed under the Apache 2.0 license) and hosted on bitbucket at https://bitbucket.org/bigr_erasmusmc/fastr

For support, go to <https://groups.google.com/d/forum/fastr-users>

To get yourself a copy, see the [*Installation*](#)

The official documentation can be found at fastr.readthedocs.io

The Fastr workflow system is presented in the following article:

Hakim Achterberg, Marcel Koek, and Wiro Niessen. “Fastr: a workflow engine for advanced data flows in medical image analysis.” *Frontiers in ICT* 3 (2016): 15.

Fastr is made possible by contributions from the following people: Hakim Achterberg, Marcel Koek, Adriaan Versteeg, Thomas Phil, Mattias Hansson, Baldur van Lew, Marcel Zwiers, and Coert Metz

FASTR DOCUMENTATION

1.1 Introduction

Fastr is a system for creating workflows for automated processing of large scale data. A processing workflow might also be called a processing pipeline, however we feel that a pipeline suggests a linear flow of data. Fastr is designed to handle complex flows of data, so we prefer to use the term network. We see the workflow as a network of processing tools, through which the data will flow.

The original authors work in a medical image analysis group at Erasmus MC. They often had to run analysis that used multiple programs written in different languages. Every time a experiment was set up, the programs had to be glued together by scripts (often in bash or python).

At some point the authors got fed up by doing these things again and again, and so decided to create a flexible, powerful scripting base to easily create these scripts. The idea evolved to a framework in which the building blocks could be defined in XML and the networks could be constructed in very simple scripts (similar to creating a GUI).

1.1.1 Philosophy

Researchers spend a lot of time processing data. In image analysis, this often includes using multiple tools in succession and feeding the output of one tool to the next. A significant amount of time is spent either executing these tools by hand or writing scripts to automate this process. This process is time consuming and error-prone. Considering all these tasks are very similar, we wanted to write one elaborate framework that makes it easy to create pipelines, reduces the risk of errors, generates extensive logs, and guarantees reproducibility.

The Fastr framework is applicable to multiple levels of usage: from a single researcher who wants to design a processing pipeline and needs to get reproducible results for publishing; to applying a consolidated image processing pipeline to a large population imaging study. On all levels of application the pipeline provenance and managed execution of the pipeline enables you to get reliable results.

1.1.2 System overview

There are a few key requirements for the design of the system:

- Any tool that your computer can run using the command line (without user interaction) should be usable by the system without modifying the tool.
- The creation of a workflow should be simple, conceptual and require no real programming.
- Networks, once created, should be usable by anyone like a simple program. All processing should be done automatically.
- All processing of the network should be logged extensively, allowing for complete reproducibility of the system (guaranteeing data provenance).

Using these requirements we define a few key elements in our system:

- A `fastr.Tool` is a definition of any program that can be used as part of a pipeline (e.g. a segmentation tool)
- A `fastr.Node` is a single operational step in the workflow. This represents the execution of a `fastr.Tool`.
- A `fastr.Link` indicates how the data flows between nodes.
- A `fastr.Network` is an object containing a collection of `fastr.Node` and `fastr.Link` that form a workflow.

With these building blocks, the creation of a pipeline will boil down to just specifying the steps in the pipeline and the flow of the data between them. For example a simple neuro-imaging pipeline could look like:




Fig. 1.1: A simple workflow that registers two images and uses the resulting transform to resample the moving image.

In Fastr this translates to:

- Create a `fastr.Network` for your pipeline
- Create a `fastr.SourceNode` for the fixed image
- Create a `fastr.SourceNode` for the moving image
- Create a `fastr.SourceNode` for the registration parameters
- Create a `fastr.Node` for the registration (in this case `elastix`)
- Create a `fastr.Node` for the resampling of the image (in this case `transformmix`)
- Create a `fastr.SinkNode` to save the transformations
- Create a `fastr.SinkNode` to save the transformed images

- `fastr.Link` the output of the fixed image source node to the fixed image input of the registration node
- `fastr.Link` the output of the moving image source node to the moving image input of the registration node
- `fastr.Link` the output of the registration parameters source node to the registration parameters input of the registration node
- `fastr.Link` the output transform of the registration node to the transform input of the resampling node
- `fastr.Link` the output transform of the registration node to the input of transformation SinkNode
- `fastr.Link` the output image of the resampling node to the input of image SinkNode
- Run the `fastr.Network` for subjects X

This might seem like a lot of work for a registration, but the Fastr framework manages all other things, executes the pipeline and builds a complete paper trail of all executed operations. The execution can be on any of the supported execution environments (local, cluster, etc). The data can be imported from and exported to any of the supported data connections (file, XNAT, etc). It is also important to keep in mind that this is a simple example, but for more complex pipelines, managing the workflow with Fastr will be easier and less error-prone than writing your own scripts.

1.2 Quick start guide

This manual will show users how to install Fastr, configure Fastr, construct and run simple networks, and add tool definitions.

1.2.1 Installation

You can install Fastr either using pip, or from the source code.

Installing via pip

You can simply install fastr using pip:

```
pip install fastr
```

Note: You might want to consider installing `fastr` in a `virtualenv`

Installing from source code

To install from source code, use Mercurial via the command-line:

```
hg clone https://<yourusername>@bitbucket.org/bigr_erasmusmc/fastr # for http
hg clone ssh://hg@bitbucket.org/bigr_erasmusmc/fastr # for ssh
```

If you prefer a GUI you can try [TortoiseHG](#) (Windows, Linux and Mac OS X) or [SourceTree](#) (Windows and Mac OS X). The address of the repository is (given for both http and ssh):

```
https://<yourusername>@bitbucket.org/bigr_erasmusmc/fastr
ssh://hg@bitbucket.org/bigr_erasmusmc/fastr
```

To install to your current Python environment, run:

```
cd fastr/
pip install .
```

This installs the scripts and packages in the default system folders. For windows this is the python site-packages directory for the fastr python library and Scripts directory for the executable scripts. For Ubuntu this is in the /usr/local/lib/python3.x/dist-packages/ and /usr/local/bin/ respectively.

Note: If you want to develop fastr, you might want to use pip install -e . to get an editable install

Note: You might want to consider installing fastr in a [virtualenv](#)

Note:

- On windows python and the Scripts directory are not on the system PATH by default. You can add these by going to System -> Advanced Options -> Environment variables.
 - On mac you need the Xcode Command Line Tools. These can be installed using the command `xcode-select --install`.
-

1.2.2 Configuration

Fastr has defaults for all settings so it can be run out of the box to test the examples. However, when you want to create your own Networks, use your own data, or use your own Tools, it is required to edit your config file.

Fastr will search for a config file named `config.py` in the `$FASTRHOME` directory (which defaults to `~/fastr/` if it is not set). So if `$FASTRHOME` is set the `~/fastr/` will be ignored.


For a sample configuration file and a complete overview of the options in `config.py` see the [Config file](#) section.

1.2.3 Creating a simple network

If Fastr is properly installed and configured, we can start creating networks. Creating a network is very simple:

```
>>> import fastr
>>> network = fastr.create_network(id='example', version='1.0')
```

Now we have an empty network, the next step is to create some nodes and links. Imagine we want to create the following network:



Creating nodes

We will create the nodes and add them to the network. This is done via the network `create_` methods. Let's create two source nodes, one normal node, and one sink:

```
>>> sourcel = network.create_source('Int', id='sourcel')
>>> sink1 = network.create_sink('Int', id='sink1')
>>> addint = network.create_node('fastr/math/AddInt:1.0', tool_version='1.0', id=
←'addint')
```

The functions `Network.create_source`, `Network.create_sink` and `Network.create_node` create the desired node and add it into the Network.

A `SourceNode` and `SinkNode` only require the datatype to be specified. A `Node` requires a `Tool` to be instantiated from. The `id` option is optional for all four, but makes it easier to identify the nodes and read the logs. The tool is defined by a namespace, the `id` and the version of the command. Many packages have multiple version which are available. The `tool_version` argument reflects the version of the Fastr wrapper which describes how the command can be called. For reproducibility also these are checked as they might be updated as well.

There is an easy way to add a constant to an input, by using a shortcut method. If you assign a `list` or `tuple` to an item in the input list, it will automatically create a `ConstantNode` and a `Link` between the `ContantNode` and the given Input:

```
>>> [1, 3, 3, 7] >> addint.inputs['right_hand']
Link link_0 (network: example):
    fastr:///networks/example/1.0/nodelist/const__addint__right_hand/outputs/output ==>
← fastr:///networks/example/1.0/nodelist/addint/inputs/right_hand/0
```

The created constant would have the `id const__addint__right_hand_0` as it automatically names the new constant `const__$nodeid__$inputid$number`.

Note: The use of the `>>`, `<<`, and `=` operators for linking is discussed bellow in section *Creating links*.

In an interactive python session we can simply look at the basic layout of the node using the `repr` function. Just type the name of the variable holding the node and it will print a human readable representation:

```
>>> sourcel
SourceNode sourcel (tool: Source:1.0 v1.0)
    Inputs          |      Outputs
-----
                           |      output     (Int)
>>> addint
Node addint (tool: AddInt:1.0 v1.0)
    Inputs          |      Outputs
-----
left_hand (Int)       |      result     (Int)
right_hand (Int)      |
```

This tool has inputs of type `Int`, so the sources and sinks need to have a matching datatype.

The tools and datatypes available are stored in `fastr.tools` and `fastr.types`. These variables are created when `fastr` is imported for the first time. They contain all the datatype and tools specified by the yaml, json or xml files in the search paths. To get an overview of the tools and datatypes loaded by `fastr`:

```
>>> fastr.tools
ToolManager
```

(continues on next page)

(continued from previous page)

```
...
fastr/math/Add:1.0      1.0 :  .../fastr/resources/tools/fastr/math/1.0/add.yaml
fastr/math/AddInt:1.0   1.0 :  .../fastr/resources/tools/fastr/math/1.0/addint.yaml
...

>>> fastr.types
DataTypeManager
...
Directory          : <URLType: Directory>
...
Float              : <ValueType: Float>
...
Int                : <ValueType: Int>
...
String             : <ValueType: String>
...
```

The `fastr.tools` variable contains all tools that Fastr could find during initialization. Tools can be chosen in two ways:

- `tools[id]` which returns the newest version of the tool
- `tools[id, version]` which returns the specified version of the tool

Creating links

So now we have a network with 4 nodes defined, however there is no relation between the nodes yet. For this we have to create some links.

```
>>> link1 = source1.output >> addint.inputs['left_hand']
>>> link2 = sink1.inputs['input'] << addint.outputs['result']
```

This asks the network to create links and immediately store them inside the network. A link always points from an Output to an Input (note that SubOutput or SubInputs are also valid). A SourceNode has only 1 output which is fixed, so it is easy to find. However, addImage has two inputs and one output, this requires us to specify which output we need. A normal node has a mapping with Inputs and one with Outputs. They can be indexed with the appropriate id's. The function returns the links, but you only need that if you are planning to change the properties of a link.


The operators with `>>` and `<<` clearly indicate the direction of the desired data flow. Also they return the created link, which is easy if you want to change the flow in a link later on. The last short hand uses the assignment, but it cannot return the created link and changing the link later on is more difficult.

Create an image of the Network

For checking your Network it is very useful to have a graphical representation of the network. This can be achieved using the `Network.draw` method.

```
>>> network.draw()
'example.svg'
```

This will create a figure in the path returned by the function that looks like:



Note: for this to work you need to have graphviz installed

1.2.4 Running a Network

Running a network locally is almost as simple as calling the `Network.execute` method:

```

>>> source_data = {'source1': {'s1': 4, 's2': 5, 's3': 6, 's4': 7}}
>>> sink_data = {'sink1': 'vfs://tmp/fastr_result_{sample_id}.txt'}
>>> run = network.execute(source_data, sink_data)
>>> # Lots output will appear on the stdout while running
>>> run.result # Show if the run was successful or if errors were encountered
True
  
```

As you can see the execute method needs data for the sources and sinks. This has to be supplied in two `dict` that have keys matching every source/sink `id` in the network. Not supplying data for every source and sink will result in an error, although it is possible to pass an empty `list` to a source.

Note: The values of the source data have to be simple values or urls and values of the sink data have to be url templates. To see what url schemes are available and how they work see [IOPlugin Reference](#). For the sink url templates see `SinkNode.set_data`

For source nodes you can supply a `list` or a `dict` with values. If you supply a `dict` the keys will be interpreted as sample ids and the values as the corresponding values. If you supply a `list`, keys will be generated in the form of `id_{N}` where N will be index of the value in the list.

Warning: As a `dict` does not have a fixed order, when a `dict` is supplied the samples are ordered by key to get a fixed order! For a `list` the original order is retained.

For the sink data, an url template has to be supplied that governs how the data is stored. The mini-language (the replacement fields) are described in the `SinkNode.set_data` method.

To rerun a stopped/crashed pipeline check the user manual on [Continuing a Network](#)

1.3 User Manual

In this chapter we will discuss the parts of Fastr in more detail. We will give a more complete overview of the system and describe the more advanced features.

1.3.1 Tools

The Tool in Fastr are the building blocks of each workflow. A tool represents a program/script/binary that can be called by Fastr and can be seen as a template. A [Node](#) can be created based on a Tool. A Node will be one processing step in a workflow, and the tool defines what the step does.

On the import of Fastr, all available Tools will be loaded in a default ToolManager that can be accessed via `fastr.tools`. To get an overview of the tools in the system, just print the `repr()` of the ToolManager:

```
>>> import fastr
>>> fastr.tools
ToolManager
...
fastr.math.Add      v0.1 :  .../fastr/resources/tools/fastr/math/0.1/add.xml
fastr.math.AddInt   v0.1 :  .../fastr/resources/tools/fastr/math/0.1/addint.xml
...
```

As you can see it gives the tool id, version and the file from which it was loaded for each tool in the system. To view the layout of a tool, just print the `repr()` of the Tool itself.

```
>>> fastr.tools['AddInt']
Tool AddInt v0.1 (Add two integers)
    Inputs           |       Outputs
-----
left_hand (Int)    | result (Int)
right_hand (Int)   |
```

To add a Tool to the system a file should be added to one of the path in `fastr.config.tools_path`. The structure of a tool file is described in [Tool description](#)

Create your own tool

There are 4 steps in creating a tool:

1. **Create folders.** We will call the tool ThrowDie. Create the folder `throw_die` in the folder `fastr-tools`. In this folder create another folder called `bin`.
2. **Place executable in correct place.** In this example we will use a snippet of executable python code:

```
#!/usr/bin/env python
import sys
import random
import json

if (len(sys.argv) > 1):
    sides = int(sys.argv[1])
else:
    sides = 6
result = [int(random.randint(1, sides ))]

print ('RESULT={}'.format(json.dumps(result)))
```

Save this text in a file called `throw_die.py`

Place the executable python script in the folder `throw_die/bin`

3. **Create and edit xml file for tool.** See [tool definition reference](#) for all the fields that can be defined in a tool.

Put the following text in file called `throw_die.xml`.

```

<tool id="ThrowDie" description="Simulates a throw of a die. Number of sides of the die is provided by user"
      name="throw_die" version="1.0">
  <authors>
    <author name="John Doe" />
  </authors>
  <command version="1.0" >
    <authors>
      <author name="John Doe" url="http://a.b/c" />
    </authors>
    <targets>
      <target arch="*" bin="throw_die.py" interpreter="python" os="*" paths='bin/' />
    </targets>
    <description>
      throw_die.py number_of_sides
      output = simulated die throw
    </description>
  </command>
  <interface>
    <inputs>
      <input cardinality="1" datatype="Int" description="Number of die sides" id="die_sides" name="die sides" nospace="False" order="0" required="True"/>
    </inputs>
    <outputs>
      <output id="output" name="output value" datatype="Int" automatic="True" cardinality="1" method="json" location="^RESULT=(.*)$" />
    </outputs>
  </interface>
</tool>

```

Put throw_die.xml in the folder example_tool. All Attributes in the example above are required. For a complete overview of the xml Attributes that can be used to define a tool, check the [Tool description](#). The most important Attributes in this xml are:

<pre> id : The id is used in in FASTR to create an instance of your tool, this name will appear in the tools when you type fastr.tools. targets : This defines where the executables are located and on which platform they are available. inputs : This defines the inputs that you want to be used in FASTR, how FASTR should use them and what data is allowed to be put in there. </pre>

More xml examples can be found in the fastr-tools folder.

- 4) **Edit configuration file.** Append the line [PATH TO LOCATION OF FASTR-TOOLS]/fastr-tools/throw_die/ to the config.py (located in ~/.fastr/ directory) to the tools_path. See [Config file](#) for more information on configuration.

You should now have a working tool. To test that everything is ok do the following in python:

<pre> >>> import fastr >>> fastr.tools ... </pre>

Now a list of available tools should be produced, including the tool ThrowDie

To test the tool create the script test_throwdie.py:

```

import fastr

# Create network
network = fastr.create_network('ThrowDie')

# Create nodes
source1 = network.create_source('Int', id='source1')
sink1 = network.create_sink('Int', id='sink1')
throwdie = network.create_node('ThrowDie', id='throwdie')

# Create links
link1 = source1.output >> throwdie.inputs['die_sides']
link2 = throwdie.outputs['output'] >> sink1.inputs['input']

# Draw and execute
source_data = {'source1': {'s1': 4, 's2': 5, 's3': 6, 's4': 7}}
sink_data = {'sink1': 'vfs://tmp/fastr_result_{sample_id}.txt'}
network.draw()
network.execute(source_data, sink_data)

```

Call the script from commandline by

```
$ python test_throwdie.py
```

An image of the network will be created in the current directory and result files will be put in the tmp directory. The result files are called `fastr_result_s1.txt`, `fastr_result_s2.txt`, `fastr_result_s3.txt`, and `fastr_result_s4.txt`

Note: If you have code which is operating system depend you will have to edit the xml file. The following gives an example of how the elastix tool does this:

```


<targets>
  <target os="windows" arch="*" bin="elastix.exe">
    <paths>
      <path type="bin" value="vfs://apps/elastix/4.7/install/" />
      <path type="lib" value="vfs://apps/elastix/4.7/install/lib" />
    </paths>
  </target>
  <target os="linux" arch="*" modules="elastix/4.7" bin="elastix">
    <paths>
      <path type="bin" value="vfs://apps/elastix/4.7/install/" />
      <path type="lib" value="vfs://apps/elastix/4.7/install/lib" />
    </paths>
  </target>
  <target os="darwin" arch="*" modules="elastix/4.7" bin="elastix">
    <paths>
      <path type="bin" value="vfs://apps/elastix/4.7/install/" />
      <path type="lib" value="vfs://apps/elastix/4.7/install/lib" />
    </paths>
  </target>
</targets>

```

`vfs` is the virtual file system path, more information can be found at [VirtualFileSystem](#).

1.3.2 Network

A *Network* represented an entire workflow. It hold all *Nodes*, *Links* and other information required to execute the workflow. Networks can be visualized as a number of building blocks (the Nodes) and links between them:



An empty network is easy to create, all you need is to name it:

```
>>> network = fastr.create_network(id="network_name")
```

the *network* is the main interface to fastr, from it you can create all elements to create a workflow. in the following sections the different elements of a *network* will be described in more detail.

Node

Nodes are the point in the *Network* where the processing happens. A *Node* takes the input data and executes jobs as specified by the underlying Tool. A *Nodes* can be created easily:

```
>>> node2 = network.create_node(tool, id='node1', step_id='step1')
```

We tell the Network to create a Node using the *create_node* method. Optionally you can add define a *step_id* for the node which is a logical grouping of Nodes that is mostly used for visualization.

Note: For a Node, the tool can be given both as the Tool class or the id of the tool. This id can be just the id or a tuple with the id and version.

A *Node* contains *Inputs* and *Outputs*. To see the layout of the *Node* one can simply look at the *repr()*.

```
>>> addint = network.create_node('AddInt', id='addint')
>>> addint
Node addint (tool: AddInt v1.0)
  Inputs           |       Outputs
  -----
  left_hand (Int) |   result   (Int)
  right_hand (Int)|
```

The inputs and outputs are located in mappings with the same name:

```
>>> addint.inputs  
<Input map, items: ['left_hand', 'right_hand']>  
  
>>> addint.outputs  
<Output map, items: ['result']>
```

The InputMap and OutputMap are classes that behave like mappings. The InputMap also facilitates the linking shorthand. By assigning an *Output* to an existing key, the InputMap will create a *Link* between the Input and Output.

SourceNode

A SourceNode is a special kind of node that is the start of a workflow. The SourceNodes are given data at run-time that fetched via IOPlugins. On create, only the datatype of the data that the SourceNode supplied needs to be known. Creating a SourceNode is very similar to an ordinary node:

```
>>> source1 = network.create_source('Int', id='source1', step_id='step1', node_group=  
    ↪'subject')
```

The first argument is the type of data the source supplies. The other optional arguments are for naming and grouping of the nodes. A SourceNode only has a single output which has a short-cut access via `source.output`.

Note: For a source or constant node, the datatype can be given both as the *BaseDataType* class or the id of the datatype.

ConstantNode

A ConstantNode is another special node. It is a subclass of the SourceNode and has a similar function. However, instead of setting the data at run-time, the data of a constant is given at creation and saved in the object. Creating a ConstantNode is similar as creating a source, but with supplying data:

```
>>> constant1 = network.create_constant('Int', [42], id='constant1', step_id='step1',  
    ↪node_group='subject')
```

The first argument is the datatype the node supplies, similar to a SourceNode. The second argument is the data that is contained in the ConstantNode. Often, when a ConstantNode is created, it is created specifically for one input and will not be reused. In this case there is a shorthand to create and link a constant to an input:

```
>>> link = addint.inputs['value1'] << [42]  
>>> link = [42] >> addint.inputs['value1']  
>>> addint.inputs['value1'] = [42]
```

are three methods that will create a constant node with the value 42 and create a link between the output and input `addint.value1`.

SinkNode

The SinkNode is the counter-part of the source node. Instead of get data into the workflow, it saves the data resulting from the workflow. For this a rule has to be given at run-time that determines where to store the data. The information about how to create such a rule is described at `SinkNode.set_data`. At creation time, only the datatype has to be specified:

```
>>> sink2 = network.create_sink('Int', id='sink2', step_id='step1', node_group=
    ↪'subject')
```

Link

Links indicate how the data flows between *Nodes*. Links can be created explicitly using one of the following:

```
>>> link = network.create_link(node1.outputs['image'], node2.inputs['image'])
```


or can be created implicitly by a short hand (there are three options):

```
# This style of assignment will create a Link similar to above
>>> link = node1.outputs['image'] >> node2.inputs['image']
>>> link = node2.inputs['image'] << node1.outputs['image']
>>> node2.inputs['image'] = node1.outputs['image']
```

Note that a *Link* is also created automatically when using the short-hand for the ConstantNode <fastr.planning.node.ConstantNode>`.

1.3.3 Data Flow

The data enters the Network via SourceNodes flows via other Node and leaves the Network via SinkNodes. The flow between Nodes goes from an Output via a Link to an Input. In the following image it is simple to track the data from the SourceNodes at the left to the SinkNodes at right side:



Note that the data in Fastr is stored in the Output and the Link and Input just give access to it (possible while transforming the data).

Data flow inside a Node

In a Node all data from the Inputs will be combined and the jobs will be generated. There are strict rules to how this combination is performed. In the default case all inputs will be used pair-wise, and if there is only a single value for an input, it will be considered as a constant.

To illustrate this we will consider the following Tool (note this is a simplified version of the real tool):

```
>>> fastr.tools['Elastix']
Tool Elastix v4.8 (Elastix Registration)
Inputs | Outputs
-----|-----
→-----
```


(continues on next page)

(continued from previous page)


fixed_image	(ITKImageFile) ↳ (ElastixTransformFile)	transform
moving_image	(ITKImageFile)	
parameters	(ElastixParameterFile)	

Also it is important to know that for this tool (by definition) the cardinality of the `transform` Output will match the cardinality of the `parameters` Input.


If we supply a Node based on this Tool with a single sample on each Input there will be one single matching Output sample created:




If the cardinality of the `parameters` sample would be increased to 2, the resulting `transform` sample would also become 2:



Now if the number of samples on `fixed_image` would be increased to 3, the `moving_image` and `parameters` will be considered constant and be repeated, resulting in 3 `transform` samples.



Then if the amount of samples for `moving_image` is also increased to 3, the `moving_image` and `fixed_image` will be used pairwise and the `parameters` will be constant.




Advanced flows in a Node

Sometimes the default pairwise behaviour is not desirable. For example if you want to test all combinations of certain input samples. To achieve this we can change the `input_group` of `Inputs` to set them apart from the rest. By default all Inputs are assigned to the default input group. Now let us change that:

```
>>> node = network.create_node('Elastix', id='elastix')
>>> node.inputs['moving_image'].input_group = 'moving'
```

This will result in `moving_image` to be put in a different input group. Now if we would supply `fixed_image` with 3 samples and `moving_image` with 4 samples, instead of an error we would get the following result:




Warning: TODO: Expand this section with the merging dimensions

Data flows in a Link

As mentioned before the data flows from an Output to an Input through a Link. By default the Link passed the data as is, however there are two special directives that change the shape of the data:

1. Collapsing flow, this collapses certain dimensions from the sample array into the cardinality. As a user you have to specify the dimension or tuple of dimensions you want to collapse.




This is useful in situation where you want to use a tool that aggregates over a number of samples (e.g. take a mean or sum).

To achieve this you can set the `collapse` property of the `Link` as follows:

```
>>> link.collapse = 'dim1'
>>> link.collapse = ('dim1', 'dim2') # In case you want to collapse multiple dimensions
```

2. Expanding flow, this turns the cardinality into a new dimension. The new dimension will be named after the `Output` from which the link originates. It will be in the form of `{nodeid}__{outputid}`




This flow directive is useful if you want to split a large sample in multiple smaller samples. This could be because processing the whole sample is not feasible because of resource constraints. An example would be splitting a 3D image into slices to process separately to avoid high memory use or to achieve parallelism.

To achieve this you can set the `expand` property of the [Link](#) to True:

```
>>> link.expand = True
```

Note: both collapsing and expanding can be used on the same link, it will executes similar to a expand-collapse sequence, but the newly created expand dimension is ignored in the collapse.



```
>>> link.collapse = 'dim1'  
>>> link.expand = True
```

Data flows in an Input

If an Input has multiple Links attached to it, the data will be combined by concatenating the values for each corresponding sample in the cardinality.


Broadcasting (matching data of different dimensions)

Sometimes you might want to combine data that does not have the same number of dimensions. As long as all dimensions of the lower dimensional datasets match a dimension in the higher dimensional dataset, this can be achieved using *broadcasting*. The term *broadcasting* is borrowed from [NumPy](#) and described as:


“The term broadcasting describes how numpy treats arrays with different shapes during arithmetic operations. Subject to certain constraints, the smaller array is “broadcast” across the larger array so that they have compatible shapes.”

—[NumPy manual on broadcasting](#)

In fastr it works similar, but to combined different Inputs in an InputGroup. To illustrate broadcasting it is best to use an example, the following network uses broadcasting in the `transformix` Node:



As you can see this visualization prints the dimensions for each Input and Output (e.g. the `elastix.fixed_image` Input has dimensions [N]). To explain what happens in more detail, we present an image illustrating the details for the samples in `elastix` and `transformix`:



In the figure the `moving_image` (and references to it) are identified with different colors, so they are easy to track across the different steps.

At the top the Inputs for the `elastix` Node are illustrated. Because the input groups a set differently, output samples are generated for all combinations of `fixed_image` and `moving_image` (see [Advanced flows in a Node](#) for details).

In the `transformix` Node, we want to combine a list of samples that is related to the `moving_image` (it has the same dimension name and sizes) with the resulting `transform` samples from the `elastix` Node. As you can see the sizes of the sample collections do not match ($[N]$ vs $[N \times M]$). This is where *broadcasting* comes into play, it allows the system to match these related sample collections. Because all the dimensions in $[N]$ are known in $[N \times M]$, it is possible to match them uniquely. This is done automatically and the result is a new $[N \times M]$ sample collection. To create a matching sample collections, the samples in the `transformix.image` Input are reused as indicated by the colors.

Warning: Note that this might fail when there are data-blocks with non-unique dimension names, as it will be not be clear which of the dimensions with identical names should be matched!

1.3.4 DataTypes

In Fastr all data is contained in object of a specific type. The types in Fastr are represented by classes that subclass `BaseDataType`. There are a few different other classes under `BaseDataType` that are each a base class for a family of types:

- `DataType` – The base class for all types that hold data
 - `ValueType` – The base class for types that contain simple data (e.g. Int, String) that can be represented as a str
 - `EnumType` – The base class for all types that are a choice from a set of options
 - `URLType` – The base class for all types that have their data stored in files (which are referenced by URL)
- `TypeGroup` – The base class for all types that actually represent a group of types




Fig. 1.2: The relation between the different `DataType` classes

The types are defined in xml files and created by the `DataTypeManager`. The `DataTypeManager` acts as a container containing all Fastr types. It is automatically instantiated as `fastr.types`. In `fastr` the created `DataTypes` classes are also automatically place in the `fastr.datatypes` module once created.

Resolving Datatypes

`Outputs` in `fastr` can have a `TypeGroup` or a number of `DataTypes` associated with them. The final `DataType`

used will depend on the linked *Inputs*. The *DataType* resolving works as a two-step procedure.

1. All possible *DataTypes* are determined and considered as *options*.
2. The best possible *DataType* from *options* is selected for non-automatic Outputs

The *options* are defined as the intersection of the set of possible values for the *Output* and each separate *Input* connected to the *Output*. Given the resulting *options* there are three scenarios:

- If there are no valid *DataTypes* (*options* is empty) the result will be None.
- If there is a single valid *DataType*, then this is automatically the result (even if it is not a preferred *DataType*).
- If there are multiple valid *DataTypes*, then the preferred *DataTypes* are used to resolve conflicts.

There are a number of places where the preferred *DataTypes* can be set, these are used in the order as given:

1. The *preferred* keyword argument to `match_types`
2. The preferred types specified in the `fastr.config`

1.3.5 Execution

Executing a Network is very simple:

```
>>> source_data = {'source_id1': ['val1', 'val2'],
                   'source_id2': {'id3': 'val3', 'id4': 'val4'}}
>>> sink_data = {'sink_id1': 'vfs://some_output_location/{sample_id}/file.txt'}
>>> network.execute(source_data, sink_data)
```

The `Network.execute` method takes a `dict` of source data and a `dict` sink data as arguments. The dictionaries should have a key for each SourceNode or SinkNode.

The execution of a Network uses a layered model:

- `Network.execute` will analyze the Network and call all Nodes.
- `Node.execute` will create jobs and fill their payload
- `execute_job` will execute the job on the execute machine and resolve any deferred values (`val:// urls`).
- `Tool.execute` will find the correct target and call the interface and if required resolve `vfs:// urls`
- `Interface.execute` will actually run the required command(s)

The ExecutionPlugin will call the `executionscript.py` for each job, passing the job as a gzipped pickle file. The `executionscript.py` will resolve deferred values and then call `Tool.execute` which analyses the required target and executes the underlying `Interface`. The Interface actually executes the job and collect the results. The result is returned (via the Tool) to the `executionscript.py`. There we save the result, provenance and profiling in a new gzipped pickle file. The execution system will use a callback to load the data back into the Network.

The selection and settings of the ExecutionPlugin are defined in the `fastr config`.

Continuing a Network

Normally a random temporary directory is created for each run. To continue a previously stopped/crashed network, you should call the `Network.execute` method using the same temporary directory(tmp dir). You can set the temporary directory to a fixed value using the following code:

```
>>> tmpdir = '/tmp/example_network_rerun'  
>>> network.execute(source_data, sink_data, tmpdir=tmpdir)
```

Warning: Be aware that at this moment, Fastr will rerun only the jobs where not all output files are present or if the job/tool parameters have been changed. It will not rerun if the input data of the node has changed or the actual tools have been adjusted. In these cases you should remove the output files of these nodes, to force a rerun.

1.3.6 IOPlugins

Sources and sink are used to get data in and out of a *Network* during execution. To make the data retrieval and storage easier, a plugin system was created that selects different plugins based on the URL scheme used. So for example, a url starting with `vfs://` will be handles by the *VirtualFileSystem plugin*. A list of all the *IOPlugins* known by the system and their use can be found at *IOPlugin Reference*.

1.3.7 Secrets

Fastr uses a secrets system for storing and retrieving login credentials. Currently the following keyrings are supported:

- Python keyring and keyrings.alt lib:
 - Mac OS X Keychain - Freedesktop Secret Service (requires secretstorage)
 - KWallet (requires dbus) - Windows Credential Vault - Gnome Keyring - Google Keyring (stores keyring on Google Docs)
 - Windows Crypto API (File-based keyring secured by Windows Crypto API)
 - Windows Registry Keyring (registry-based keyring secured by Windows Crypto API)
 - PyCrypto File Keyring - Plaintext File Keyring (not recommended)
- Netrc (not recommended)

When a password is retrieved trough the fastr SecretService it loops trough all of the available SecretProviders (currently keyring and netrc) until a match is found.

The Python keyring library automatically picks the best available keyring backend. If you wish to choose your own python keyring backend it is possible to do so by make a keyring configuration file according to the keyring library documentation. The python keyring library connects to one keyring. Currently it cannot loop trough all available keyrings until a match is found.

1.3.8 Debugging

This section is about debugging Fastr tools wrappers, Fastr Networks (when building a Network) and Fastr Network Runs.

Debugging a Fastr tool

When wrapping a Tool in Fastr sometimes it will not work as expected or not load properly. Fastr is shipped with a command that helps checking Tools. The *fastr verify* command can try to load a Tool in steps to make it more easy to understand where the loading went wrong.

The *fastr verify* command will use the following steps:

- Try to load the tool with and without compression
- Try to find the correct serializer and make sure the format is correct
- Try to validate the Tool content against the json_schema of a proper Tool

- Try to create a Tool object
- If available, execute the tool test

An example of the use of `fastr verify`:

```
$ fastr verify tool fastr/resources/tools/fastr/math/0.1/add.xml
[INFO]     verify:0020 >> Trying to read file with compression OFF
[INFO]     verify:0036 >> Read data from file successfully
[INFO]     verify:0040 >> Trying to load file using serializer "xml"
[INFO]     verify:0070 >> Validating data against Tool schema
[INFO]     verify:0080 >> Instantiating Tool object
[INFO]     verify:0088 >> Loaded tool <Tool: Add version: 1.0> successfully
[INFO]     verify:0090 >> Testing tool...
```

If your Tool is loading but not functioning as expected you might want to easily test your Tool without building an entire Network around it that can obscure errors. It is possible to run a tool from the Python prompt directly using `tool.execute`:

```
>>> tool.execute(left_hand=40, right_hand=2)
[INFO] localbinarytarget:0090 >> Changing ./bin
[INFO]     tool:0311 >> Target is <Plugin: LocalBinaryTarget>
[INFO]     tool:0318 >> Using payload: {'inputs': {'right_hand': (2,), 'left_hand': (40,)}, 'outputs': {}}
[INFO] localbinarytarget:0135 >> Adding extra PATH: ['/home/hachterberg/dev/fastr-develop/fastr/resources/tools/fastr/math/0.1/bin']
[INFO] fastrinterface:0393 >> Execution payload: {'inputs': {'right_hand': (2,), 'left_hand': (40,)}, 'outputs': {}}
[INFO] fastrinterface:0496 >> Adding (40,) to argument list based on <fastrinterface> InputParameterDescription object at 0x7fc950fa8850>
[INFO] fastrinterface:0496 >> Adding (2,) to argument list based on <fastrinterface> InputParameterDescription object at 0x7fc950fa87d0>
[INFO] localbinarytarget:0287 >> Options: ['/home/hachterberg/dev/fastr-develop/fastr/resources/tools/fastr/math/0.1/bin']
[INFO] localbinarytarget:0201 >> Calling command arguments: ['python', '/home/hachterberg/dev/fastr-develop/fastr/resources/tools/fastr/math/0.1/bin/addint.py', '--in1', '40', '--in2', '2']
[INFO] localbinarytarget:0205 >> Calling command: "'python' '/home/hachterberg/dev/fastr-develop/fastr/resources/tools/fastr/math/0.1/bin/addint.py' '--in1' '40' '--in2' '2'"
[INFO] fastrinterface:0400 >> Collecting results
[INFO] executionpluginmanager:0467 >> Callback processing thread ended!
[INFO] executionpluginmanager:0467 >> Callback processing thread ended!
[INFO] executionpluginmanager:0467 >> Callback processing thread ended!
[INFO] jsoncollector:0076 >> Setting data for result with [42]
<fastr.core.interface.InterfaceResult at 0x7fc9661ccfd0>
```

In this case an `AddInt` was ran from the python shell. As you can see it shows the payload it created based on the call, followed by the options for the directories that contain the binary. Then the command that is called is given both as a list and string (for easy copying to the prompt yourself). Finally the collected results is displayed.

Note: You can give input and outputs as keyword arguments for `execute`. If an input and output have the same name, you can disambiguate them by prefixing them with `in_` or `out_` (e.g. `in_image` and `out_image`)

Debugging an invalid Network

The simplest command to check if your Network is considered valid is to use the `Network.is_valid` method. It will simply check if the Network is valid:

```
>>> network.is_valid()
True
```

It will return a boolean that only indicates the validity of the Network, but it will print any errors it found to the console/log with the ERROR log level, for example when datatypes on a link do not match:


```
>>> invalid_network.is_valid()
[WARNING] datatypemanager:0388 >> No matching DataType available (args (<ValueType:_  
↳Float class [Loaded]>, <ValueType: Int class [Loaded]>))
[WARNING]         link:0546 >> Cannot match datatypes <ValueType: Float class [Loaded]>_  
↳and <ValueType: Int class [Loaded]> or not preferred datatype is set! Abort linking_
↳fastr://networks/add_ints/0.0/nodelist/source/outputs/output to fastr://networks/_  
↳add_ints/0.0/nodelist/add/inputs/left_hand!
[WARNING] datatypemanager:0388 >> No matching DataType available (args (<ValueType:_  
↳Float class [Loaded]>, <ValueType: Int class [Loaded]>))
[ERROR]   network:0571 >> [add] Input left_hand is not valid: SubInput fastr://_
↳networks/add_ints/0.0/nodelist/add/inputs/left_hand/0 is not valid: SubInput source_
↳(link_0) is not valid
[ERROR]   network:0571 >> [add] Input left_hand is not valid: SubInput fastr://_
↳networks/add_ints/0.0/nodelist/add/inputs/left_hand/0 is not valid: [link_0] source_
↳and target have non-matching datatypes: source Float and Int
[ERROR]   network:0571 >> [link_0] source and target have non-matching datatypes:_
↳source Float and Int
False
```

Because the messages might not always be enough to understand errors in the more complex Networks, we would advice you to create a plot of the network using the `network.draw_network` method:

```
>>> network.draw_network(network.id, draw_dimensions=True, expand_macro=True)
'add_ints.svg'
```

The value returned is the path of the output image generated (it will be placed in the current working directory). The `draw_dimensions=True` will make the drawing add indications about the sample dimensions in each Input and Output, whereas `expand_macro=True` causes the draw to expand MacroNodes and draw the content of them. If you have many nested MacroNodes, you can set `expand_macro` to an integer and that is the depth until which the MacroNodes will be drawn in detail.

An example of a simple multi-atlas segmentation Network nicely shows the use of drawing the dimensions, the dimensions vary in certain Nodes due to the use of `input_groups` and a collapsing link (drawn in blue):



Debugging a Network run with errors

If a Network run did finish but there were errors detected, Fastr will report those at the end of the execution. We included an example of a Network that has failing samples in `fastr/examples/failing_network.py` which can be used to test debugging. An example of the output of a Network run with failures:

```
[INFO] networkrun:0604 >> ##### network execution FINISHED #####
[INFO] networkrun:0605 >> #      network execution FINISHED      #
[INFO] networkrun:0606 >> #####
[INFO] networkrun:0618 >> ===== RESULTS =====
[INFO] networkrun:0627 >> sink_1: 2 success / 2 failed
[INFO] networkrun:0627 >> sink_2: 2 success / 2 failed
[INFO] networkrun:0627 >> sink_3: 1 success / 3 failed
[INFO] networkrun:0627 >> sink_4: 1 success / 3 failed
[INFO] networkrun:0627 >> sink_5: 1 success / 3 failed
[INFO] networkrun:0628 >> =====
[WARNIN] networkrun:0651 >> There were failed samples in the run, to start debugging_
→ you can run:

    fastr trace $RUNDIR/_sink_data__.json --sinks

see the debug section in the manual at https://fastr.readthedocs.io/en/default/static/user\_manual.html#debugging for more information.
```

As you can see, there were failed samples in every sink. Also you already get the suggestion to use `fastr trace`. This command helps you inspect the staging directory of the Network run and pinpoint the errors.

The suggested command will print a similar summary as given by the network execution:

```
$ fastr trace $RUNDIR/_sink_data__.json --sinks
sink_1 -- 2 failed -- 2 succeeded
sink_2 -- 2 failed -- 2 succeeded
sink_3 -- 3 failed -- 1 succeeded
sink_4 -- 3 failed -- 1 succeeded
sink_5 -- 3 failed -- 1 succeeded
```

Since this is not given us new information we can add the `-v` flag for more output and limit the output to one sink, in this case `sink_5`:

```
$ fastr trace $RUNDIR/__sink_data__.json --sinks sink_5
sink_5 -- 3 failed -- 1 succeeded
  sample_1_1: Encountered error: [FastrOutputValidationError] Could not find result
  ↵for output out_2 (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.
  ↵py:970)
  sample_1_2: Encountered error: [FastrOutputValidationError] Could not find result
  ↵for output out_1 (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.
  ↵py:970)
  sample_1_3: Encountered error: [FastrOutputValidationError] Could not find result
  ↵for output out_1 (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.
  ↵py:970)
  sample_1_3: Encountered error: [FastrOutputValidationError] Could not find result
  ↵for output out_2 (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.
  ↵py:970)
```

Now we are given one error per sample, but this does not yet give us that much information. To get a very detailed report we have to specify one sink and one sample. This will make the `fastr trace` command print a complete error report for that sample:

```
$ fastr trace $RUNDIR/__sink_data__.json --sinks sink_5 --sample sample_1_1 -v
Tracing errors for sample sample_1_1 from sink sink_5
Located result pickle: /home/hachterberg/FastrTemp/fastr_failing_network_2017-09-
  ↵04T10-44-58_uMWeMV/step_1/sample_1_1/__fastr_result__.pickle.gz

===== JOB failing_network_step_1_sample_1_1 =====
Network: failing_network
Run: failing_network_2017-09-04T10-44-58
Node: step_1
Sample index: (1)
Sample id: sample_1_1
Status: JobState.execution_failed
Timestamp: 2017-09-04 08:45:19.238192
Job file: /home/hachterberg/FastrTemp/fastr_failing_network_2017-09-04T10-44-58_
  ↵uMWeMV/step_1/sample_1_1/__fastr_result__.pickle.gz

Command:
List representation: [u'python', u'/home/hachterberg/dev/fastr-develop/fastr/fastr/
  ↵resources/tools/fastr/util/0.1/bin/fail.py', u'--in_1', u'1', u'--in_2', u'1', u'--
  ↵fail_2']
String representation: 'python' '/home/hachterberg/dev/fastr-develop/fastr/fastr/
  ↵resources/tools/fastr/util/0.1/bin/fail.py' '--in_1' '1' '--in_2' '1' '--fail_2'

Output data:
{'out_1': [<Int: 2>]}

Status history:
2017-09-04 08:45:19.238212: JobState.created
2017-09-04 08:45:21.537417: JobState.running
2017-09-04 08:45:31.578864: JobState.execution_failed

----- ERRORS -----
- FastrOutputValidationError: Could not find result for output out_2 (/home/
  ↵hachterberg/dev/fastr-develop/fastr/fastr/execution/job.py:970)
- FastrValueError: [failing_network_step_1_sample_1_1] Output values are not
  ↵valid! (/home/hachterberg/dev/fastr-develop/fastr/fastr/execution/job.py:970) (continues on next page)
```

(continued from previous page)

```
-----
----- STDOUT -----
Namespace(fail_1=False, fail_2=True, in_1=1, in_2=1)
in 1 : 1
in 2 : 1
fail_1: False
fail_2: True
RESULT_1=[2]

-----
----- STDERR -----
```

As shown above, it finds the result files of the failed job(s) and prints the most important information. The first paragraph shows the information about the Job that was involved. The second paragraph shows the command used both as a list (which is clearer and internally used in Python) and as a string (which you can copy/paste to the shell to test the command). Then there is the output data as determined by Fastr. The next section shows the status history of the Job which can give an indication about wait and run times. Then there are the errors that Fastr encountered during the execution of the Job. In this case it could not find the output for the Tool. Finally the stdout and stderr of the subprocess are printed. In this case we can see that RESULT_2=[...] was not in the stdout, and so the result could not be located.

Note: Sometimes there are no Job results in a directory, this usually means the process got killed before the Job could finished. On cluster environments, this often means that the process was killed due to memory constraints.

Asking for help with debugging

If you would like help with debugging, you can contact us via the [fastr-users google group](#). To enable us to track the errors please include the following:

- The entire log of the fastr run (can be copied from console or from the end of `~/.fastr/logs/info.log`).
- A dump of the network run, which can be created that by using the [`fastr dump`](#) command like:

```
$ fastr dump $RUNDIR fastr_run_dump.zip
```

This will create a zip file including all the job files, logs, etc but not the actual data files.

These should be enough information to trace most errors. In some cases we might need to ask for additional information (e.g. tool files, datatype files) or actions from your side.

1.3.9 Naming Convention

For the naming convention of the tools we tried to stay close to the Python [PEP 8](#) coding style. In short, we defined toolnames as classes so they should be UpperCamelCased. The inputs and outputs of a tool we considered as functions or method arguments, these should be named lower_case_with_underscores.

An overview of the mapping of Fastr to [PEP 8](#):

Fastr construct	Python PEP8 equivalent	Examples
Network.id	module	brain_tissue_segmentation
Tool.id	class	BrainExtractionTool, ThresholdImage
Node.id	variable name	brain_extraction, threshold_mask
Input/Output.id	method	image, number_of_classes, probability_image

Furthermore there are some small guidelines:

- No input or output in the input or output names. This is already specified when setting or getting the data.
- Add the type of the output that is named. i.e. enum, string, flag, image,
 - No File in the input/output name (Passing files around is what Fastr was developed for).
 - No type necessary where type is implied i.e. lower_threshold, number_of_levels, max_threads.
- Where possible/useful use the fullname instead of an abbreviation.

1.3.10 Provenance

For every data derived data object, Fastr records the **Provenance**. The *SinkNode* write provenance records next to every data object it writes out. The records contain information on what operations were performed to obtain the resulting data object.

W3C Prov

The provenance is recorded using the **W3C Prov Data Model (PROV-DM)**. Behind the scenes we are using the python `prov` implementation.

The PROV-DM defines 3 Starting Point Classes and their relating properties. See Fig. 1.3 for a graphic representation of the classes and the relations.

Fig. 1.3: The three Starting Point classes and the properties that relate them. The diagrams in this document depict Entities as yellow ovals, Activities as blue rectangles, and Agents as orange pentagons. The responsibility properties are shown in pink.⁰

*

Implementation

In the workflow document the provenance classes map to fastr concepts in the following way:

Agent Fastr, *Networks*, *Tools*, *Nodes*

Activity *Jobs*

Entities Data

⁰ This picture and caption is taken from <http://www.w3.org/TR/prov-o/> . “Copyright © 2011-2013 World Wide Web Consortium, (MIT, ERCIM, Keio, Beihang). <http://www.w3.org/Consortium/Legal/2015/doc-license>”

Usage

The provenance is stored in ProvDocument objects in pickles. The convenience command line tool `fastr prov` can be used to extract the provenance in the [PROV-N](#) notation and can be serialized to [PROV-JSON](#) and [PROV-XML](#). The provenance document can also be visualized using the `fastr prov` command line tool.

1.4 Command Line Tools

Fastr is shipped with a number of command line tools to perform common tasks and greatly simplify things such as debugging. The list of command line tools that is included in Fastr:

command	description
<code>cat</code>	Print information from a job file
<code>dump</code>	Dump the contents of a network run tempdir into a zip for remote assistance
<code>execute</code>	Execute a fastr job file
<code>extract_argparse</code>	Create a stub for a Tool based on a python script using argparse
<code>provenance</code>	Get PROV information from the result pickle.
<code>pylint</code>	Tiny wrapper in pylint so the output can be saved to a file (for test automation)
<code>report</code>	Print report of a job result (<code>__fastr_result__.pickle.gz</code>) file
<code>run</code>	Run a Network from the commandline
<code>sink</code>	Command line access to the IOPlugin sink
<code>source</code>	Command line access to the IOPlugin source
<code>test</code>	Run the tests of a tool to verify the proper function
<code>trace</code>	Trace samples/sinks from a run
<code>upgrade</code>	Upgrade a fastr 2.x python file to fastr 3.x syntax
<code>verify</code>	Verify fastr resources, at the moment only tool definitions are supported.
<code>webapp</code>	Start the fastr webapp and open in a new browser tab

1.4.1 fastr cat

Extract selected information from the extra job info. The path is the selection of the data to retrieve. Every parts of the path (separated by a /) is seen as the index for the previous object. So for example to get the stdout of a job, you could use ‘`fastr cat __fastr_extra_job_info__.json process/stdout`’.

```
usage: fastr cat [-h] __fastr_extra_job_info__.json path
```

Positional Arguments

<code>__fastr_extra_job_info__.json</code>	result file to cat
<code>path</code>	path of the data to print

1.4.2 fastr dump

Create a dump of a network run directory that contains the most important information for debugging. This includes a serialization of the network, all the job command and result files, the extra job information files and the provenance files. No data files will be included, but note that if jobs get sensitive information passed via the command line this will be included in the job files.

```
usage: fastr dump [-h] RUNDIR DUMP.zip
```

Positional Arguments

RUNDIR	The run directory to dump
DUMP.zip	The file to place the dump in

1.4.3 fastr execute

Execute a job from commandline.

```
usage: fastr execute [-h] [JOBFILE]
```

Positional Arguments

JOBFILE	File of the job to execute (default ./__fastr_command__.pickle.gz)
----------------	--

1.4.4 fastr extract_argparse

Extract basic information from argparse.

```
usage: fastr extract_argparse [-h] SCRIPT.py TOOL.xml
```

Positional Arguments

SCRIPT.py	Python script to inspect
TOOL.xml	created Tool stub

1.4.5 fastr provenance

Export the provenance information from JSON to other formats or plot the provenance data as a graph.

```
usage: fastr provenance [-h] [-so SYNTAX_OUT_FILE] [-sf SYNTAX_FORMAT]
                        [-i INDENT] [-vo VISUALIZE_OUT_FILE]
                        [RESULTFILE]
```

Positional Arguments

RESULTFILE	File of the job to execute (default ./__fastr_prov__.json)
-------------------	--

Named Arguments

- so, --syntax-out-file** Write the syntax to file.
- sf, --syntax-format** Choices are: [json], provn or xml
Default: “json”
- i, --indent** Indent size of the serialized documents.
Default: 2
- vo, --visualize-out-file** Visualize the provenance. The most preferred format is svg. You can specify any format pydot supports. Specify the format by postfixing the filename with an extension.

1.4.6 fastr pylint

Run pylint in such a way that the output is written to a file

```
usage: fastr pylint [-h] --output_file PYLINT.OUT
```

Named Arguments

- output_file** The file to result in

1.4.7 fastr report

Print a report of a job result file.

```
usage: fastr report [-h] [JOBFILE]
```

Positional Arguments

- JOBFILE** File of the job to execute (default ./__fastr_command__.pickle.gz)

1.4.8 fastr run

Execute a job or network from commandline.

```
usage: fastr run [-h] NETWORKFILE
```

Positional Arguments

- NETWORKFILE** File of the network to execute

1.4.9 fastr sink

executes an ioplugin

```
usage: fastr sink [-h] -i INPUT [INPUT ...] -o OUTPUT [OUTPUT ...]
                  [-d DATATYPE [DATATYPE ...]]
```

Named Arguments

-i, --input	The url to process (can also be a list)
-o, --output	The output urls in vfs scheme (can also be a list and should be the same size as -inurl)
-d, --datatype	The datatype of the source/sink data to handle

1.4.10 fastr source

Executes an source command

```
usage: fastr source [-h] -i INPUT [INPUT ...] -o OUTPUT [-d DATATYPE]
                     [-s SAMPLE_ID]
```

Named Arguments

-i, --input	The url to process (can also be a list)
-o, --output	The output url in vfs scheme
-d, --datatype	The datatype of the source/sink data to handle
-s, --sample_id	The sample_id of the source/sink data to handle

1.4.11 fastr test

Run a tests for a fastr resource.

```
usage: fastr test [-h] {tool,tools,network,networks} ...
```

Sub-commands:

tool

Test a single tool

```
fastr test tool [-h] TOOL
```

Positional Arguments

TOOL	Tool to test or directory with tool reference data
-------------	--

tools

Test all tools known to fastr

```
fastr test tools [-h]
```

network

Test a single network

```
fastr test network [-h] NETWORK
```

Positional Arguments

NETWORK The reference data to test the Network

networks

Test all network references inside subdirectories

```
fastr test networks [-h] [--result RESULT.json] REFERENCE
```

Positional Arguments

REFERENCE path of the directory containing subdirectories with reference data

Named Arguments

--result Write the results of the test to a JSON file

1.4.12 fastr trace

Fastr trace helps you inspect the staging directory of the Network run and pinpoint the errors.

```
usage: fastr trace [-h] [--verbose] [--sinks [SINKS [SINKS ...]]]
                   [--samples [SAMPLES [SAMPLES ...]]]
                   [__sink_data__.json]
```

Positional Arguments

__sink_data__.json result file to cat

Default: “/home/docs/checkouts/readthedocs.org/user_builds/fastr/checkouts/3.1.2/fastr/doc/__sink_data__

Named Arguments

--verbose, -v	set verbose output for more details Default: False
--sinks	list results for specified sinks
--samples	list result for all samples

1.4.13 fastr upgrade

Upgrades a python file that creates a Network to the new fastr 3.x syntax. The file will be parsed and the full syntax tree will be transformed to fit the new syntax.

Note: Solves most common problems, but cannot always solve 100% of the issues

```
usage: fastr upgrade [-h] [--type TYPE] NETWORK.py NEW.py
```

Positional Arguments

NETWORK.py	Network creation file (in python) to upgrade
NEW.py	location of the result file

Named Arguments

--type	tool of resource to upgrade, one of: network, tool
---------------	--

1.4.14 fastr verify

Verify fastr resources, at the moment only tool definitions are supported.

```
usage: fastr verify [-h] TYPE path
```

Positional Arguments

TYPE	Possible choices: tool
	Type of resource to verify (e.g. tool)
path	path of the resource to verify

1.4.15 fastr webapp

Starts the fastr web client.

```
usage: fastr webapp [-h] [-d] [-o]
```

Named Arguments

-d, --debug	Debug mode. Default: False
-o, --openpage	Open web page after start. Default: False

1.5 Resource File Formats

This chapter describes the various files fastr uses. The function and format of the files is described allowing the user to configure fastr and add DataTypes and Tools.

1.5.1 Config file

Fastr reads the config files from `$FASTRHOME/config.py` by default. If the `$FASTRHOME` environment variable is not set it will default to `~/.fastr`. As a result it read:

- `$FASTRHOME/config.py` (if environment variable set)
- `~/.fastr/config.py` (otherwise)

Reading a new config file change or override settings, making the last config file read have the highest priority. All settings have a default value, making config files and all settings within optional.

Note: To verify which config files have been read you can see `fastr.config.read_config_files` which contains a list of the read config files (in read order).

Note: If `$FASTRHOME` is set, `$FASTRHOME/tools` is automatically added as a tool directory if it exists and `$FASTRHOME/datatypes` is automatically added as a type directory if it exists.

Splitting up config files

Sometimes it is nice to have config files split in multiple smaller files. Next to the `config.py` you can also created a directory `config.d` and all `.py` files in this directory will be sourced in alphabetical order.

Given the following layout of the `$FASTRHOME` directory:

```
./config.d/a.py
./config.d/b.txt
./config.d/c.py
./config.py
```

The following files will be read in order:

1. `./config.py`
2. `./config.d/a.py`
3. `./config.d/c.py`

Example config file

Here is a minimal config file:

```
# Enable debugging output
debug = False

# Define the path to the tool definitions
tools_path = ['/path/to/tools',
              '/path/to/other/tools'] + tools_path
types_path = ['/path/to/datatypes',
              '/path/to/other/datatypes'] + types_path

# Specify what your preferred output types are.
preferred_types += ["NiftiImageFileCompressed",
                     "NiftiImageFile"]

# Set the tmp mount
mounts['tmp'] = '/path/to/tmpdir'
```

Format

The config file is actually a python source file. The next syntax applies to setting configuration values:

```
# Simple values
float_value = 1.0
int_value = 1
str_value = "Some value"
other_str_value = 'name'.capitalize()

# List-like values
list_value = ['over', 'ride', 'values']
other_list_value.prepend('first')
other_list_value.append('list')

# Dict-like values
dict_value = {'this': 1, 'is': 2, 'fixed': 3}
other_dict_value['added'] = 'this key'
```

Note: Dictionaries and list always have a default, so you can always append or assign elements to them and do not have to create them in a config file. Best practice is to only edit them unless you really want to block out the earlier config files.

Most operations will be assigning values, but for list and dict values a special wrapper object is used that allows manipulations from the default. This limits the operations allowed.

List values in the `config.py` have the following supported operators/methods:

- `+`, `__add__` and `__radd__`
- `+=` or `__iadd__`
- `append`
- `prepend`

- `extend`

Mapping (dict-like) values in the `config.py` have the following supported operators/methods:

- `update`
- `[]` or `__getitem__`, `__setitem__` and `__delitem__`

Configuration fields

This is a table the known config fields on the system:

name	type	description	default
debug	bool	Flag to enable/disable debugging	False
examples-dir	str	Directory containing the fastr examples	\$systemdir/examples
execution_plugin	str	The default execution plugin to use	'ProcessPoolExecution'
execution-script	str	Execution script location	\$systemdir/execution/executionscript.py
filesynchelpurl	str	Redis url e.g. redis://localhost:6379	"
job_cleanup_level	int	The level of cleanup required, options: all, no_cleanup, non_failed	no_cleanup
log_to_file	bool	Indicate if default logging settings should log to files or not	False
logdir	str	Directory where the fastr logs will be placed	\$userdir/logs
logging_config	dict	Python logger config	{}
loglevel	int	The log level to use (as int), INFO is 20, WARNING is 30, etc	20
logtype	str	Type of logging to use	'default'
mounts	dict	A dictionary containing all mount points in the VFS system	{'tmp': '\$TMPDIR', 'example_data': '\$systemdir/examples/data', 'home': '~'}
networks_path	list	Directories to scan for networks	[\$userdir/networks', '\$resourcedir/networks']
plugins_path	list	Directories to scan for plugins	[\$userdir/plugins', '\$resourcedir/plugins']
preferred_types	list	A list indicating the order of the preferred types to use. First item is most preferred.	[]
protected_modules	list	A list of modules in the environment modules that are protected against unloading	[]
reporting_plugins	list	The reporting plugins to use, is a list of all plugins to be activated	['SimpleReport']
resources-dir	str	Directory containing the fastr system resources	\$systemdir/resources
schemadir	str	Directory containing the fastr data schemas	\$systemdir/schemas
source_job_limit	int	The number of source jobs allowed to run concurrently	0
systemdir	str	Fastr installation directory	Directory of the top-level fastr package
tools_path	list	Directories to scan for tools	[\$userdir/tools', '\$resourcedir/tools']
types_path	list	Directories to scan for datatypes	[\$userdir/datatypes', '\$resourcedir/datatypes']
userdir	str	Fastr user configuration directory	\$FASTRHOME or ~/.fastr
warn_develop	bool	Warning users on import if this is not a production version of fastr	True
web_hostname	str	The hostname to expose the web app for	'localhost'
web_port	int	The port to expose the web app on	5000
web_secret_key	str	The secret key to use for the flask web app	'VERYSECRETKEY!'

Note: This tables only includes the fastr default config fields, but not the fields added by plugins. For information look at the appropriate plugin reference. For the built-in fastr plugins they can be found at the [plugin reference](#)

1.5.2 Tool description

Tools are the building blocks in the fastr network. To add new *Tools* to fastr, XML/json files containing a *Tool* definition can be added. These files have the following layout:

Attribute	Description
id	The id of this Tool (used internally in fastr)
name	The name of the Tool, for human readability
version	The version of the Tool wrapper (not the binary)
url	The url of the Tool wrapper
authors []	List of authors of the Tools wrapper
name	Name of the author
email	Email address of the author
url	URL of the website of the author
tags	tag[]
	List of tags describing the Tool
command	Description of the underlying command
version	Version of the tool that is wrapped
url	Website where the tools that is wrapped can be obtained
targets []	Description of the target binaries/script of this Tool
os	OS targeted (windows, linux, macos or * (for any))
arch	Architecture targeted 32, 64 or * (for any)
...	Extra variables based on the target used, see <i>Targets</i>
description	Description of the Tool
license	License of the Tool, either full license or a clear name (e.g. LGPL, GPL v2)
authors []	List of authors of the Tool (not the wrapper!)
name	Name of the authors
email	Email address of the author
url	URL of the website of the author
interface	The interface definition see <i>Interfaces</i>
help	Help text explaining the use of the Tool
cite	Bibtext of the Citation(s) to reference when using this Tool for a publication

1.6 Plugin Reference

In this chapter we describe the different plugins bundled with Fastr (e.g. IOPlugins, ExecutionPlugins). The reference is build automatically from code, so after installing a new plugin the documentation has to be rebuild for it to be included in the docs.

1.6.1 CollectorPlugin Reference

CollectorPlugins are used for finding and collecting the output data of outputs part of a FastrInterface

scheme	CollectorPlugin
JsonCollector	<i>JsonCollector</i>
PathCollector	<i>PathCollector</i>
StdoutCollector	<i>StdoutCollector</i>

JsonCollector

The JsonCollector plugin allows a program to print out the result in a pre-defined JSON format. It is then used as values for fastr.

The working is as follows:

1. The location of the output is taken
2. If the location is `None`, go to step 5
3. The substitutions are performed on the location field (see below)
4. The location is used as a [regular expression](#) and matched to the `stdout` line by line
5. The matched string (or entire `stdout` if location is `None`) is [loaded as a json](#)
6. The data is parsed by `set_result`

The structure of the JSON has to follow the a predefined format. For normal `Nodes` the format is in the form:

```
[value1, value2, value3]
```

where the multiple values represent the cardinality.

For a `FlowNodes` the format is the form:

```
{  
    'sample_id1': [value1, value2, value3],  
    'sample_id2': [value4, value5, value6]  
}
```

This allows the tool to create multiple output samples in a single run.

PathCollector

The PathCollector plugin for the FastrInterface. This plugin uses the location fields to find data on the filesystem. To use this plugin the method of the output has to be set to `path`

The general working is as follows:

1. The location field is taken from the output
2. The substitutions are performed on the location field (see below)
3. The updated location field will be used as a [regular expression](#) filter
4. The filesystem is scanned for all matching files/directory

The special substitutions performed on the location use the Format Specification Mini-Language [Format Specification Mini-Language](#). The predefined fields that can be used are:

- `inputs`, an objet with the input values (use like `{inputs.image[0]}`) The input contains the following attributes that you can access:
 - `.directory` for the directory name (use like `input.image[0].directory`) The directory is the same as the result of `os.path.dirname`
 - `.filename` is the result of `os.path.basename` on the path
 - `.basename` for the basename name (use like `input.image[0].basename`) The basename is the same as the result of `os.path.basename` and the extension stripped. The extension is considered to be everything after the first dot in the filename.

- .extension for the extension name (use like `input.image[0].extension`)
- output, an object with the output values (use like `{outputs.result[0]}`) It contains the same attributes as the input
 - `special.cardinality`, the index of the current cardinality
 - `special.extension`, is the extension for the output DataType

Example use:

```
<output ... method="path" location="{output.directory[0]}/TransformParameters.  
↪{special.cardinality}.{special.extension}" />
```

Given the output directory `./nodeid/sampleid/result`, the second sample in the output and filetype with a `.txt` extension, this would be translated into:

```
<output ... method="path" location="./nodeid/sampleid/result/TransformParameters.1.  
↪.txt" />
```

StdoutCollector

The StdoutCollector can collect data from the stdout stream of a program. It filters the `stdout` line by line matching a predefined regular expression.

The general working is as follows:

1. The location field is taken from the output
2. The substitutions are performed on the location field (see below)
3. The updated location field will be used as a `regular expression` filter
4. The `stdout` is scanned line by line and the `regular expression` filter is applied

The special substitutions performed on the location use the Format Specification Mini-Language [Format Specification Mini-Language](#). The predefined fields that can be used are:

- `inputs`, an object with the input values (use like `{inputs.image[0]}`)
- `outputs`, an object with the output values (use like `{outputs.result[0]}`)
- `special` which has two subfields:
 - `special.cardinality`, the index of the current cardinality
 - `special.extension`, is the extension for the output DataType

Note: because the plugin scans line by line, it is impossible to catch multi-line output into a single value

1.6.2 ExecutionPlugin Reference

This class is the base for all Plugins to execute jobs somewhere. There are many methods already in place for taking care of stuff.

There are fall-backs for certain features, but if a system already implements those it is usually preferred to skip the fall-back and let the external system handle it. There are a few flags to enable disable these features:

- `cls.SUPPORTS_CANCEL` indicates that the plugin can cancel queued jobs

- `cls.SUPPORTS_HOLD_RELEASE` indicates that the plugin can queue jobs in a hold state and can release them again (if not, the base plugin will create a hidden queue for held jobs). The plugin should respect the `Job.status == JobState.hold` when queueing jobs.
- `cls.SUPPORTS_DEPENDENCY` indicate that the plugin can manage job dependencies, if not the base plugin job dependency system will be used and jobs will only be submitted when all dependencies are met.
- `cls.CANCELS_DEPENDENCIES` indicates that if a job is cancelled it will automatically cancel all jobs depending on that job. If not the plugin traverse the dependency graph and kill each job manual.

Note: If a plugin supports dependencies it is assumed that when a job gets cancelled, the depending job also get cancelled automatically!

Most plugins should only need to redefine a few abstract methods:

- `__init__` the constructor
- `cleanup` a clean up function that frees resources, closes connections, etc
- `_queue_job` the method that queues the job for execution

Optionally an extra job finished callback could be added:

- `_job_finished` extra callback for when a job finishes

If `SUPPORTS_CANCEL` is set to True, the plugin should also implement:

- `_cancel_job` cancels a previously queued job

If `SUPPORTS_HOLD_RELEASE` is set to True, the plugin should also implement:

- `_hold_job` holds a job that is currently held
- `_release_job` releases a job that is currently held

If `SUPPORTED_DEPENDENCY` is set to True, the plugin should:

- Make sure to use the `Job.hold_jobs` as a list of its dependencies

Not all of the functions need to actually do anything for a plugin. There are examples of plugins that do not really need a `cleanup`, but for safety you need to implement it. Just using a `pass` for the method could be fine in such a case.

Warning: When overwriting other functions, extreme care must be taken not to break the plugins working, as there is a lot of bookkeeping that can go wrong.

<code>scheme</code>	<code>ExecutionPlugin</code>
<code>BlockingExecution</code>	<code>BlockingExecution</code>
<code>DRMAAExecution</code>	<code>DRMAAExecution</code>
<code>LinearExecution</code>	<code>LinearExecution</code>
<code>ProcessPoolExecution</code>	<code>ProcessPoolExecution</code>
<code>RQExecution</code>	<code>RQExecution</code>
<code>SlurmExecution</code>	<code>SlurmExecution</code>
<code>StrongrExecution</code>	<code>StrongrExecution</code>

BlockingExecution

The blocking execution plugin is a special plugin which is meant for debug purposes. It will not queue jobs but immediately execute them inline, effectively blocking fastr until the Job is finished. It is the simplest execution plugin and can be used as a template for new plugins or for testing purposes.

DRMAAExecution

A DRMAA execution plugin to execute Jobs on a Grid Engine cluster. It uses a configuration option for selecting the queue to submit to. It uses the python `drmaa` package.

Note: To use this plugin, make sure the `drmaa` package is installed and that the execution is started on an SGE submit host with DRMAA libraries installed.

Note: This plugin is at the moment tailored to SGE, but it should be fairly easy to make different subclasses for different DRMAA supporting systems.

Configuration fields

The following configuration fields are added to the fastr config:

name	type	description	default
<code>drmaa_queue</code>	str	The default queue to use for jobs send to the scheduler	'week'
<code>drmaa_max_jobs</code>	int	The maximum jobs that can be send to the scheduler at the same time (0 for no limit)	0
<code>drmaa_engine</code>	str	The engine to use (options: grid_engine, torque	'grid_engine'
<code>drmaa_job_check_interval</code>	int	The interval in which the job checker will start to check for stale jobs	900

LinearExecution

An execution engine that has a background thread that executes the jobs in order. The queue is a simple FIFO queue and there is one worker thread that operates in the background. This plugin is meant as a fallback when other plugins do not function properly. It does not multi-processing so it is safe to use in environments that do not support that.

ProcessPoolExecution

A local execution plugin that uses multiprocessing to create a pool of worker processes. This allows fastr to execute jobs in parallel with true concurrency. The number of workers can be specified in the fastr configuration, but the default amount is the number of cores - 1 with a minimum of 1.

Warning: The ProcessPoolExecution does not check memory requirements of jobs and running many workers might lead to memory starvation and thus an unresponsive system.

Configuration fields

The following configuration fields are added to the fastr config:

name	type	description	default
process_pool_worker_number	int	Number of workers to use in a process pool	3

RQExecution

A execution plugin based on Redis Queue. Fastr will submit jobs to the redis queue and workers will peel the jobs from the queue and process them.

This system requires a running redis database and the database url has to be set in the fastr configuration.

Note: This execution plugin required the `redis` and `rq` packages to be installed before it can be loaded properly.

Configuration fields

The following configuration fields are added to the fastr config:

name	type	description	default
rq_host	str	The url of the redis serving the redis queue	'redis://localhost:6379/0'
rq_queue	str	The redis queue to use	'default'

SlurmExecution

Configuration fields

The following configuration fields are added to the fastr config:

name	type	description	de- fault
slurm_job_check_interval	int	The interval in which the job checker will start to check for stale jobs	30
slurm_partition	str	The slurm partition to use	"

StrongrExecution

A execution plugin based on Redis Queue. Fastr will submit jobs to the redis queue and workers will peel the jobs from the queue and process them.

This system requires a running redis database and the database url has to be set in the fastr configuration.

Note: This execution plugin required the `redis` and `rq` packages to be installed before it can be loaded properly.

1.6.3 FlowPlugin Reference

Plugin that can manage an advanced data flow. The plugins override the execution of node. The execution receives all data of a node in one go, so not split per sample combination, but all data on all inputs in one large payload. The flow plugin can then re-order the data and create resulting samples as it sees fits. This can be used for all kinds of specialized data flows, e.g. cross validation.

To create a new FlowPlugin there is only one method that needs to be implemented: `execute`.

scheme	FlowPlugin
CrossValidation	<i>CrossValidation</i>

CrossValidation

Advanced flow plugin that generated a cross-validation data flow. The node need an input with data and an input number of folds. Based on that the outputs test and train will be supplied with a number of data sets.

1.6.4 IOPlugin Reference

IOPlugins are used for data import and export for the sources and sinks. The main use of the *IOPlugins* is during execution (see *Execution*). The *IOPlugins* can be accessed via `fastr.ioplugins`, but generally there should be no need for direct interaction with these objects. The use of is mainly via the URL used to specify source and sink data.

scheme	IOPlugin
CommaSeperatedValueFile	<i>CommaSeperatedValueFile</i>
FileSystem	<i>FileSystem</i>
HTTPPlugin	<i>HTTPPlugin</i>
Null	<i>Null</i>
Reference	<i>Reference</i>
S3Filesystem	<i>S3Filesystem</i>
VirtualFileSystem	<i>VirtualFileSystem</i>
VirtualFileSystemRegularExpression	<i>VirtualFileSystemRegularExpression</i>
VirtualFileSystemValueList	<i>VirtualFileSystemValueList</i>
XNATStorage	<i>XNATStorage</i>

CommaSeperatedValueFile

The CommaSeperatedValueFile an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs.

The `csv://` URL is a `vfs://` URL with a number of query variables available. The URL mount and path should point to a valid CSV file. The query variable then specify what column(s) of the file should be used.

The following variable can be set in the query:

variable	usage
value	the column containing the value of interest, can be int for index or string for key
id	the column containing the sample id (optional)
header	indicates if the first row is considered the header, can be <code>true</code> or <code>false</code> (optional)
delimiter	the delimiter used in the csv file (optional)
quote	the quote character used in the csv file (optional)
reformat	a reformatting string so that <code>value = reformat.format(value)</code> (used before relative_path)
relative_path	indicates the entries are relative paths (for files), can be <code>true</code> or <code>false</code> (optional)

The header is by default `false` if the neither the `value` and `id` are set as a string. If either of these are a string, the header is required to define the column names and it automatically is assumed `true`.

The delimiter and quota characters of the file should be detected automatically using the `Sniffer`, but can be forced by setting them in the URL.

Example of valid csv URLs:

```
# Use the first column in the file (no header row assumed)
csv://mount/some/dir/file.csv?value=0

# Use the images column in the file (first row is assumed header row)
csv://mount/some/dir/file.csv?value=images

# Use the segmentations column in the file (first row is assumed header row)
# and use the id column as the sample id
csv://mount/some/dir/file.csv?value=segmentations&id=id

# Use the first column as the id and the second column as the value
# and skip the first row (considered the header)
csv://mount/some/dir/file.csv?value=1&id=0&header=true

# Use the first column and force the delimiter to be a comma
csv://mount/some/dir/file.csv?value=0&delimiter=,
```

FileSystem

The FileSystem plugin is create to handle `file://` type or URLs. This is generally not a good practice, as this is not portable over between machines. However, for test purposes it might be useful.

The URL scheme is rather simple: `file://host/path` (see [wikipedia](#) for details)

We do not make use of the host part and at the moment only support localhost (just leave the host empty) leading to `file:///` URLs.

Warning: This plugin ignores the hostname in the URL and does only accept driver letters on Windows in the form `c:/`

HTTPPlugin

Warning: This Plugin is still under development and has not been tested at all. example url: <https://server.io/> path/to/resource

Null

The Null plugin is create to handle `null://` type or URLs. These URLs are indicating the sink should not do anything. The data is not written to anywhere. Besides the scheme, the rest of the URL is ignored.

Reference

The Reference plugin is create to handle `ref://` type or URLs. These URLs are to make the sink just write a simple reference file to the data. The reference file contains the `DataType` and the `value` so the result can be reconstructed. It for files just leaves the data on disk by reference. This plugin is not useful for production, but is used for testing purposes.

S3Filesystem

Warning: As this IOPlugin is under development, it has not been thoroughly tested.

example url: s3://bucket.server/path/to/resource

VirtualFileSystem

The virtual file system class. This is an IOPlugin, but also heavily used internally in fastr for working with directories. The VirtualFileSystem uses the `vfs://` url scheme.

A typical virtual filesystem url is formatted as `vfs://mountpoint/relative/dir/from/mount.ext`

Where the `mountpoint` is defined in the [Config file](#). A list of the currently known mountpoints can be found in the `fastr.config` object

```
>>> fastr.config.mounts
{'example_data': '/home/username/fastr-feature-documentation/fastr/fastr/examples/data
',
 'home': '/home/username/',
 'tmp': '/home/username/FastrTemp'}
```

This shows that a url with the mount `home` such as `vfs://home/tempdir/testfile.txt` would be translated into `/home/username/tempdir/testfile.txt`.

There are a few default mount points defined by Fastr (that can be changed via the config file).

mountpoint	default location
home	the users home directory (<code>expanduser('~/')</code>)
tmp	the fastr temporary dir, defaults to <code>tempfile.gettempdir()</code>
example_data	the fastr example data directory, defaults <code>\$FASTRDIR/example/data</code>

VirtualFileSystemRegularExpression

The `VirtualFileSystemValueList` an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs.

A `vfsregex://` URL is a `vfs` URL that can contain regular expressions on every level of the path. The regular expressions follow the [re module](#) definitions.

An example of a valid URLs would be:

```
vfsregex://tmp/network_dir/.*/*/__fastr_result__.pickle.gz
vfsregex://tmp/network_dir/nodeX/(?P<id>.*)/__fastr_result__.pickle.gz
```

The first URL would result in all the `__fastr_result__.pickle.gz` in the working directory of a Network. The second URL would only result in the file for a specific node (`nodeX`), but by adding the named group `id` using `(?P<id>.*)` the sample id of the data is automatically set to that group (see [Regular Expression Syntax](#) under the special characters for more info on named groups in regular expression).

Concretely if we would have a directory `vfs://mount/somedir` containing:

```
image_1/Image.nii
image_2/image.nii
```

(continues on next page)

(continued from previous page)

```
image_3/anotherimage.nii  
image_5/inconsistentnamingftw.nii
```

we could match these files using `vfsregex://mount/somedir/(?P<id>image_\d+)/.*\.nii` which would result in the following source data after expanding the URL:

```
{'image_1': 'vfs://mount/somedir/image_1/Image.nii',  
'image_2': 'vfs://mount/somedir/image_2/image.nii',  
'image_3': 'vfs://mount/somedir/image_3/anotherimage.nii',  
'image_5': 'vfs://mount/somedir/image_5/inconsistentnamingftw.nii'}
```

Showing the power of this regular expression filtering. Also it shows how the ID group from the URL can be used to have sensible sample ids.

Warning: due to the nature of regexp on multiple levels, this method can be slow when having many matches on the lower level of the path (because the tree of potential matches grows) or when directories that are parts of the path are very large.

VirtualFileSystemValueList

The VirtualFileSystemValueList is an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs. A `vfslist://` URL basically is a url that points to a file using vfs. This file then contains a number lines each containing another URL.

If the contents of a file `vfs://mount/some/path/contents` would be:

```
vfs://mount/some/path/file1.txt  
vfs://mount/some/path/file2.txt  
vfs://mount/some/path/file3.txt  
vfs://mount/some/path/file4.txt
```

Then using the URL `vfslist://mount/some/path/contents` as source data would result in the four files being pulled.

Note: The URLs in a vfslist file do not have to use the `vfs` scheme, but can use any scheme known to the Fastr system.

XNATStorage

Warning: As this IOPlugin is under development, it has not been thoroughly tested.

The XNATStorage plugin is an IOPlugin that can download data from and upload data to an XNAT server. It uses its own `xnat://` URL scheme. This is a scheme specific for this plugin and though it looks somewhat like the XNAT rest interface, a different type of URL.

Data resources can be accessed directly by a data url:

```
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/experiments/
  ↪experiment001/scans/T1/resources/DICOM
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/experiments/
  ↪*_BRAIN/scans/T1/resources/DICOM
```

In the second URL you can see a wildcard being used. This is possible at long as it resolves to exactly one item.

The `id` query element will change the field from the default experiment to subject and the `label` query element sets the use of the label as the fastr id (instead of the XNAT id) to True (the default is False)

To disable https transport and use http instead the query string can be modified to add `insecure=true`. This will make the plugin send requests over http:

```
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/experiments/
  ↪*_BRAIN/scans/T1/resources/DICOM?insecure=true
```

For sinks it is import to know where to save the data. Sometimes you want to save data in a new assessor/resource and it needs to be created. To allow the Fastr sink to create an object in XNAT, you have to supply the type as a query parameter:

```
xnat://xnat.bmia.nl/data/archive/projects/sandbox/subjects/S01/experiments/_BRAIN/
  ↪assessors/test_assessor/resources/IMAGE/files/image.nii.gz?resource_
  ↪type=xnat:resourceCatalog&assessor_type=xnat:qcAssessmentData
```

Valid options are: `subject_type`, `experiment_type`, `assessor_type`, `scan_type`, and `resource_type`.

If you want to do a search where multiple resources are returned, it is possible to use a search url:

```
xnat://xnat.example.com/search?projects=sandbox&subjects=subject[0-9][0-9][0-9]&
  ↪experiments=*_BRAIN&scans=T1&resources=DICOM
```

This will return all DICOMs for the T1 scans for experiments that end with _BRAIN that belong to a subjectXXX where XXX is a 3 digit number. By default the ID for the samples will be the experiment XNAT ID (e.g. XNAT_E00123). The wildcards that can be the used are the same UNIX shell-style wildcards as provided by the module `fnmatch`.

It is possible to change the id to a different fields id or label. Valid fields are project, subject, experiment, scan, and resource:

```
xnat://xnat.example.com/search?projects=sandbox&subjects=subject[0-9][0-9][0-9]&
  ↪experiments=*_BRAIN&scans=T1&resources=DICOM&id=subject&label=true
```

The following variables can be set in the search query:

variable	default	usage
projects	*	The project(s) to select, can contain wildcards (see <code>fnmatch</code>)
subjects	*	The subject(s) to select, can contain wildcards (see <code>fnmatch</code>)
experiments	*	The experiment(s) to select, can contain wildcards (see <code>fnmatch</code>)
scans	*	The scan(s) to select, can contain wildcards (see <code>fnmatch</code>)
resources	*	The resource(s) to select, can contain wildcards (see <code>fnmatch</code>)
id	experiment	What field to use a the id, can be: project, subject, experiment, scan, or resource
label	false	Indicate the XNAT label should be used as fastr id, options true or false
insecure	false	Change the url scheme to be used to http instead of https
verify	true	(Dis)able the verification of SSL certificates
regex	false	Change search to use regex <code>re.match()</code> instead of fnmatch for matching
overwrite	false	Tell XNAT to overwrite existing files if a file with the name is already present

For storing credentials the `.netrc` file can be used. This is a common way to store credentials on UNIX systems. It is required that the file is only accessible by the owner only or a `NetrcParseError` will be raised. A `netrc` file is really easy to create, as its entries look like:

```
machine xnat.example.com
  login username
  password secret123
```

See the [netrc module](#) or the [GNU inet utils website](#) for more information about the `.netrc` file.

Note: On windows the location of the `netrc` file is assumed to be `os.path.expanduser('~/_.netrc')`. The leading underscore is because windows does not like filename starting with a dot.

Note: For scan the label will be the scan type (this is initially the same as the series description, but can be updated manually or the XNAT scan type cleanup).

Warning: labels in XNAT are not guaranteed to be unique, so be careful when using them as the sample ID.

For background on XNAT, see the [XNAT API DIRECTORY](#) for the REST API of XNAT.

1.6.5 Interface Reference

Abstract base class of all Interfaces. Defines the minimal requirements for all Interface implementations.

scheme	Interface
FastrInterface	<i>FastrInterface</i>
FlowInterface	<i>FlowInterface</i>
NipypeInterface	<i>NipypeInterface</i>

FastrInterface

The default Interface for fastr. For the command-line Tools as used by fastr. It build a commandline call based on the input/output specification.

The fields that can be set in the interface:

Attribute	Description
<code>id</code>	The id of this Tool (used internally in fastr)
<code>inputs[]</code>	List of Inputs that can be accepted by the Tool
	<code>id</code>
	<code>name</code>
	<code>datatype</code>

Continued on next page

Table 1.1 – continued from previous page

Attribute		Description
	enum[]	List of possible values for an Enum-Type (created on the fly by fastr) ¹
	prefix	Commandline prefix of the Input (e.g. -in, -i)
	cardinality	Cardinality of the Input
	repeat_prefix	Flag indicating if for every value of the Input the prefix is repeated
	required	Flag indicating if the input is required
	nospace	Flag indicating if there is no space between prefix and value (e.g. -in=val)
	format	For DataTypes that have multiple representations, indicate which one to use
	default	Default value for the Input
	description	Long description for an input
outputs[]		List of Outputs that are generated by the Tool (and accessible to fastr)
	id	ID of the Output
	name	Longer name of the Output (more human readable)
	datatype	The ID of the DataType of the Output ¹
	enum[]	List of possible values for an Enum-Type (created on the fly by fastr) ¹
	prefix	Commandline prefix of the Output (e.g. -out, -o)
	cardinality	Cardinality of the Output
	repeat_prefix	Flag indicating if for every value of the Output the prefix is repeated
	required	Flag indicating if the input is required
	nospace	Flag indicating if there is no space between prefix and value (e.g. -out=val)
	format	For DataTypes that have multiple representations, indicate which one to use
	description	Long description for an input
	action	Special action (defined per DataType) that needs to be performed before creating output value (e.g. ‘ensure’ will make sure an output directory exists)
	automatic	Indicate that output doesn’t require commandline argument, but is created automatically by a Tool ²
	method	The collector plugin to use for the gathering automatic output, see the Collector plugins

Continued on next page

Table 1.1 – continued from previous page

Attribute	Description
	location Definition where to an automatically, usage depends on the method ²

FlowInterface

The Interface use for AdvancedFlowNodes to create the advanced data flows that are not implemented in the fastr. This allows nodes to implement new data flows using the plugin system.

The definition of FlowInterfaces are very similar to the default FastrInterfaces.

Note: A flow interface should be using a specific FlowPlugin

NipypeInterface

Experimental interfaces to using nipype interfaces directly in fastr tools, only using a simple reference.

To create a tool using a nipype interface just create an interface with the correct type and set the `nipype` argument to the correct class. For example in an xml tool this would become:

```
<interface class="NipypeInterface">
  <nipype_class>nipype.interfaces.elastix.Registration</nipype_class>
</interface>
```

Note: To use these interfaces nipype should be installed on the system.

Warning: This interface plugin is basically functional, but highly experimental!

1.6.6 ReportingPlugin Reference

Base class for all reporting plugins. The plugin has a number of methods that can be implemented that will be called on certain events. On these events the plugin can inspect the presented data and take reporting actions.

<code>scheme</code>	<code>ReportingPlugin</code>
<code>ElasticsearchReporter</code>	<code>ElasticsearchReporter</code>
<code>PimReporter</code>	<code>PimReporter</code>
<code>SimpleReport</code>	<code>SimpleReport</code>

ElasticsearchReporter

NOT DOCUMENTED!

¹ `datatype` and `enum` are conflicting entries, if both specified `datatype` has precedence

² More details on defining automatica output are given in [TODO]

Configuration fields

The following configuration fields are added to the fastr config:

name	type	description	default
elasticsearch_host	str	The elasticsearch host to report to	''
elasticsearch_index	str	The elasticsearch index to store data in	'fastr'
elasticsearch_debug	bool	Setup elasticsearch debug mode to send stdout stderr on job success	False

PimReporter

NOT DOCUMENTED!

Configuration fields

The following configuration fields are added to the fastr config:

name	type	description	default
pim_host	str	The PIM host to report to	''
pim_username	str	Username to send to PIM	Username of the currently logged in user
pim_update_interval	float	The interval in which to send jobs to PIM	2.5
pim_batch_size	int	Maximum number of jobs that can be send to PIM in a single interval	100
pim_debug	bool	Setup PIM debug mode to send stdout stderr on job success	False
pim_finished_timeout	int	Maximum number of seconds after the network finished in which PIM tries to synchronize all remaining jobs	10

SimpleReport

NOT DOCUMENTED!

1.6.7 Target Reference

The abstract base class for all targets. Execution with a target should follow the following pattern:

```
>>> with Target() as target:
...     target.run_command(['sleep', '10'])
```

The Target context operator will set the correct paths/initialization. Within the context command can be ran and when leaving the context the target reverts the state before.

scheme	Target
DockerTarget	<i>DockerTarget</i>
LocalBinaryTarget	<i>LocalBinaryTarget</i>
MacroTarget	<i>MacroTarget</i>
SingularityTarget	<i>SingularityTarget</i>

DockerTarget

A tool target that is located in a Docker images. Can be run using docker-py. A docker target only need two variables: the binary to call within the docker container, and the docker container to use.

```
{
  "arch": "*",
  "os": "*",
  "binary": "bin/test.py",
  "docker_image": "fastr/test"
}
```

```
<target os="*" arch="*" binary="bin/test.py" docker_image="fastr/test">
```

LocalBinaryTarget

A tool target that is a local binary on the system. Can be found using environmentmodules or a path on the executing machine. A local binary target has a number of fields that can be supplied:

- **binary** (required): the name of the binary/script to call, can also be called `bin` for backwards compatibility.
- **modules**: list of modules to load, this can be environmentmodules or lmod modules. If modules are given, the paths, environment_variables and initscripts are ignored.
- **paths**: a list of paths to add following the structure `{"value": "/path/to/dir", "type": "bin"}`. The types can be `bin` if the it should be added to \$PATH or `lib` if it should be added to the library path (e.g. \$LD_LIBRARY_PATH for linux).
- **environment_variables**: a dictionary of environment variables to set.
- **initscript**: a list of script to run before running the main tool
- **interpreter**: the interpreter to use to call the binary e.g. `python`

The LocalBinaryTarget will first check if there are modules given and the module subsystem is loaded. If that is the case it will simply unload all current modules and load the given modules. If not it will try to set up the environment itself by using the following steps:

1. Prepend the bin paths to \$PATH
2. Prepend the lib paths to the correct environment variable
3. Setting the other environment variables given (\$PATH and the system library path are ignored and cannot be set that way)
4. Call the initscripts one by one

The definition of the target in JSON is very straightforward:

```
{
  "binary": "bin/test.py",
  "interpreter": "python",
  "paths": [
    {
      "type": "bin",
      "value": "vfs://apps/test/bin"
    },
    {
      "type": "lib",
      "value": "vfs://apps/test/lib"
    }
  ]
}
```

(continues on next page)

(continued from previous page)

```

    "type": "lib",
    "value": "./lib"
  },
],
"environment_variables": {
  "othervar": 42,
  "short_var": 1,
  "testvar": "value1"
},
"initscripts": [
  "bin/init.sh"
],
"modules": ["elastix/4.8"]
}
}

```

In XML the definition would be in the form of:

```

<target os="linux" arch="*" modules="elastix/4.8" bin="bin/test.py" interpreter=
  ↵ "python">
  <paths>
    <path type="bin" value="vfs://apps/test/bin" />
    <path type="lib" value="./lib" />
  </paths>
  <environment_variables short_var="1">
    <testvar>value1</testvar>
    <othervar>42</othervar>
  </environment_variables>
  <initscripts>
    <initscript>bin/init.sh</initscript>
  </initscripts>
</target>

```

MacroTarget

A target for MacroNodes. This target cannot be executed as the MacroNode handles execution differently. But this contains the information for the MacroNode to find the internal Network.

SingularityTarget

A tool target that is run using a singularity container, see the [singularity website](#)

- **binary** (required): the name of the binary/script to call, can also be called `bin` for backwards compatibility.
- **container (required)**: the singularity container to run, this can be in url form for `singularity pull` or as a path to a local container
- **interpreter**: the interpreter to use to call the binary e.g. `python`


1.7 Development and Design Documentation

In this chapter we will discuss the design of Fastr in more detail. We give pointers for development and add the design documents as we currently envision Fastr. This is both for people who are interested in the Fastr develop and for


current developers to have an archive of the design decision agreed upon.

1.7.1 Sample flow in Fastr

The current Sample flow is the following:



The idea is that we make a common interface for all classes that are related to the flow of Samples. For this we propose the following mixin classes that provide the interface and allow for better code sharing. The basic structure of the classes is given in the following diagram:



The abstract and mixin methods are as follows:

ABC	Inherits from	Abstract Methods	Mixin methods
HasDimensions		dimensions	size dimnames
HasSamples	HasDimensions	__getitem__	__contains__ __iter__ iteritems items indexes ids
ContainsSamples	HasSamples	samples	__getitem__ __setitem__ dimensions
ForwardsSamples	HasSamples	source index_to_target index_to_source combine_samples combine_dimensions	__getitem__ dimensions

Note: Though the flow is currently working like this, the mixins are not yet created.


1.7.2 Network Execution

The network execution should contain a number of steps:

- Network
 - Creates a NetworkRun based on the current layout
- NetworkRun
 - Transform the Network (possibly joining Nodes of certain interface into a combined NodeRun etc)
 - Start generation of the Job Direct Acyclic Graph (DAG)
- SchedulingPlugin
 - Prioritize Jobs based on some predefined rules
 - Combine certain Jobs to improve efficiency (e.g. minimize i/o on a grid)
- ExecutionPlugin

- Run a (list of) Jobs. If there is more than one jobs, run them sequentially on same execution host using a local temp for intermediate files.
- On finished callback: Updated DAG with newly ready jobs, or remove cancelled jobs

This could be visualized as the following loop:



The callback of the `ExecutionPlugin` to the `NetworkRun` would trigger the execution of the relevant `NodeRuns` and the addition of more `Jobs` to the `JobDAG`.

Note: The Job DAG should be thread-safe as it could be both read and extended at the same time.

Note: If a list of jobs is send to the `ExecutionPlugin` to be run as on Job on an external execution platform, the resources should be combined as follows: `memory=max`, `cores=max`, `runtime=sum`

Note: If there are execution hosts that have multiple cores the `ExecutionPlugin` should manage this (for example by using pilot jobs). The `SchedulingPlugin` creates units that should be run sequentially on the resources noted and will not attempt parallelization

A `NetworkRun` would contain similar information as the `Network` but not have functionality for editing/changing it. It would contain the functionality to execute the `Network` and track the status and samples. This would allow `Network.execute` to create multiple concurrent runs that operate independent of each other. Also editing a `Network` after the run started would have no effect on that run.

Note: This is a plan, not yet implemented

Note: For this to work, it would be important for a Jobs to have forward and backward dependency links.

SchedulingPlugins

The idea of the plugin is that it would give a priority on Jobs created by a `Network`. This could be done based on different strategies:

- Based on (sorted) sample id's, so that one sample is always prioritized over others. The idea is that samples are processed as much as possible in order, finishing the first sample first. Only processing other samples if there is left-over capacity.
- Based on distance to a (particular) Sink. This is to generate specific results as quick as possible. It would not focus on specific samples, but give priority to whatever sample is closest to being finished.
- Based on the distance to from a Source. Based on the sign of the weight it would either keep all samples on the same stage as much as possible, only progressing to a new `NodeRun` when all samples are done with the previous `NodeRun`, or it would push samples with accelerated rates.

Additionally it will group Jobs to be executed on a single host. This could reduce i/o and limit the number of jobs an external scheduler has to track.

Note: The interface for such a plugin has not yet been established.

1.7.3 Secrets

“Something that is kept or meant to be kept unknown or unseen by others.”

Using secrets

Fastr IOPlugins that need authentication data should use the Fastr SecretService for retrieving such data. The SecretService can be used as follows.

```
from fastr.utils.secrets import SecretService
from fastr.utils.secrets.exceptions import CouldNotRetrieveCredentials

secret_service = SecretService()

try:
    password = secret_service.find_password_for_user('testserver.lan:9000', 'john-doe')
except CouldNotRetrieveCredentials:
    # the password was not found
    pass
```

Implementing a SecretProvider

A SecretProvider is implemented as follows:

1. Create a file in fastr/utils/secrets/providers/<yourprovidername>.py
2. Use the template below to write your SecretProvider
3. Add the secret provider to fastr/utils/secrets/providers/__init__.py
4. Add the secret provider to fastr/utils/secrets/secretservice.py: import it and add it to the array in function _init_providers

```
from fastr.utils.secrets.secretprovider import SecretProvider
from fastr.utils.secrets.exceptions import CouldNotRetrieveCredentials, \
    CouldNotSetCredentials, CouldNotDeleteCredentials, NotImplemented

try:
    # this is where libraries can be imported
    # we don't want fastr to crash if a specific
    # library is unavailable
    # import my-library
except (ImportError, ValueError) as e:
    pass

class KeyringProvider(SecretProvider):
    def __init__(self):
        # if libraries are imported in the code above
        # we need to check if import was successful
        # if it was not, raise a RuntimeError
        # so that FASTR ignores this SecretProvider
        # if 'my-library' not in globals():
        #     raise RuntimeError("my-library module required")
        pass

    def get_password_for_user(self, machine, username):
        # This function should return the password as a string
        # or raise a CouldNotRetrieveCredentials error if the password
        # is not found.
        # In the event that this function is unsupported a
        # NotImplemented exception should be thrown
```

(continues on next page)

(continued from previous page)

```
raise NotImplemented()

def set_password_for_user(self, machine, username, password):
    # This function should set the password for a specified
    # machine + user. If anything goes wrong while setting
    # the password a CouldNotSetCredentials error should be raised.
    # In the event that this function is unsupported a
    # NotImplemented exception should be thrown
    raise NotImplemented()

def del_password_for_user(self, machine, username):
    # This function should delete the password for a specified
    # machine + user. If anything goes wrong while setting
    # the password a CouldNotDeleteCredentials error should be raised.
    # In the event that this function is unsupported a
    # NotImplemented exception should be thrown
    raise NotImplemented()
```

1.8 Changelog

All notable changes to this project will be documented in this file.

The format is based on [Keep a Changelog](#) and this project adheres to [Semantic Versioning](#)

1.8.1 3.1.2 - 2019-06-18

Improved

- Avoid execution plugins calling cleanup multiple times
- Tools can now set an input to environment variables using the environ attribute. The parameter will NOT be put command-line anymore and instead be dispatched via an environment variable given by the environ argument value

Fixed

- Bug in XNATStorage plugin where files with a path within the resource could not be correctly located
- Add timeout when waiting to send to PIM
- Fix problem with non-requested outputs being able to invalidate a job execution

1.8.2 3.1.1 - 2019-05-02

Fixed

- Packaging problem in release (old file left in build folder)

1.8.3 3.1.0 - 2019-05-02

Added

- Added support for tools in YAML
- `fastr upgrade` can also upgrade tools from XML to YAML
- `fastr report` command to print an overview report of a job result

Fixed

- Re-added support for named sub-inputs

Improved

- Fixes in `fastr upgrade` to handle more exotic whitespace and arguments
- Small documentation fixes (especially in configuration section)
- Better windows support (tested by users)

Changed

- In `ResourceLimits` the default time of jobs is now `None` (no limit) instead of 1 hour.
- By default do not log to files (we noticed `fastr` logs are not very often read by users and they could cause some issues with log rotation, by default logging to files is turned off, switching it back on can be done by setting `log_to_file = True` in the `fastr.config`)

1.8.4 3.0.1 - 2019-03-28

Fixed

- Improved implementation of `fastr upgrade` to handle newlines in the `create_node` function properly. Also can handle old-fashioned use of `fastr.toollist[...]` in `create_node`.

1.8.5 3.0.0 - 2019-03-05

Changed

- Now ported to Python 3.6+ (Python 2 is no longer supported!)
- New public API which is not fully compatible with `fastr 2.x`, the changes are small. The new API will be guaranteed in next minor version upgrades and is considered to be stable.
- Clear way of defining resource limits for Nodes in a Network using the `ResourceLimit` class.
- The datatype and cardinality of inputs of a tool are now checked before the tool is to be executed as an extra safety.
- Dimensions are drawn by default in `network.draw`
- The api now accepts types other than `Output`, `list`, `tuple` when creating a link. When a single value is given it is assumedly a constant from the network definition.

- Drawing a network will not create temporary .dot files anymore
- Sinkdata can be a string, in that case it will be the same string for all sink nodes so a {node} substitution should be used in the template
- Make the xnat ioplugin use xnat+http:// and xnat+https:// url schemes in favour of xnat:// with ?insecure=... (old behaviour will also work for now)
- Complete rewrite of PIM plugin (PIMReporter) making use of the new Reporter plugin infrastructure. It also caches all communication with PIM to be resilient against connection interruptions.

Added

- fastr upgrade command to automatically upgrade a network creation file from fastr 2.x to fastr 3.x API.
- http(s) IOPlugin for downloading files via http(s)
- network.draw now has a flag to hide the unconnected inputs and output of a node. The unconnected inputs/outputs are hidden by default.
- Reporting plugins, Fastr now exposes a number of message hooks which can be listened to by Reporter plugins.

Fixed

- Fixed some bugs with drmaa communication (more safeties added)
- Fixed a bug in the MacroNode update function which could cause networks with MacroNodes to be invalid
- The margins and font size of the network.draw graph rendering are set a bit wider and smaller (resp.) to avoid excessive text overflow.
- Fixed bug in provenance which did not properly chain the provenance of subsequent jobs.

1.8.6 2.1.2 - 2018-10-24

Added

- Allow overriding the timestamp of the network execution

Changed

- Updated PIM publisher to support the new PIM API v2
- Updated XNAT IOPlugin to not crash when creating a resource failed because another process already did that (race condition)
- Make default resource limits for DRMAA configurable
- Add stack trace to FastrExceptions

1.8.7 2.1.1 - 2018-06-29

Fixed

- Fixed some issues with the type estimation of outputs of Jobs and update validation functions of NIFTI files

1.8.8 2.1.0 - 2018-04-13

Added

- SLURM execution plugin based on sbatch, scancel, scontrol and squeue. The plugin supports job dependencies and cancellation.
- Support for running tools in Docker containers using a DockerTarget
- Support for running tools in Singularity containers using a SingularityTarget
- Support for datatypes with multiple extensions (e.g. .tif and .tiff) by setting the extension to a tuple of options. The first extension is leading for deciding filenames in a sink.

Changed

- Source jobs now also validate the output (and do not only rely on the stderr of the tool)
- Added preferred_types attribute to TypeGroups that gives the order of preference of members, alternatively the order of _members is used (this should be given as tuple or list to be meaningful)
- In the config.py you can now access the USER_DIR and SYSTEM_DIR variables for use in setting other variables. These are only read and changing them will only change subsequent config reads but not the main config values.
- checksum for nii.gz now takes the md5 checksum of the decompressed data
- Serialization of MacroNodes now should function properly

Fixed

- BUG in XNAT plugin that made it impossible to download data from scans without an empty type string
- BUG where the order of OrderedDict in a source was not preserved
- BUG where newer Werkzeug version requires the web port to be an integer

1.8.9 2.0.1 - 2017-10-19

- Fix a bug in the validation of FilePrefix datatypes

1.8.10 2.0.0 - 2017-09-28

Added

- The default python logger can now be configured from the fastr config file under key logging_config
- Support for MacroNodes, a Network can be used as a Node inside of another Network. There is should be no limitation on the internal Network used, but currently the MacroNode ignores input_groups on its inputs.
- A sync helper was added to assist in slow file synchronisation over NFS
- Source and Sink can now handle S3 URL's
- FastrInterface can now forward errors from a subprocess if they are dumped to stdout or stderr in a json identified by __FASTR_ERRORS__ = [].

- A `specials.workdir` field in the location field of automatic outputs that gives the current working directory (e.g. job directory)
- Added support for Torque (using pbs-drmaa library) to DRMAAExecution
- Added option to set a limit for number of jobs submitted at same time be the DRMAAExecution
- Use of the `~/.fastr/config.d` directory for adding additional config files. Any `.py` file in there will be parsed in alphabetical order.
- XNATStorage IOPlugin now has a retry scheme for uploads, if an uploaded file could not be found on the server, it is retried up to 3 times.
- Added `fastr dump` command to create a zip containing all important debugging information.

Changed

- FilePrefix type does not have an extension anymore (avoids ugly dot in middle of filename)
- Allow expanding of link where samples have a non-uniform cardinality. This will not result in a sparse array.
- The default for `required` for the automatic outputs is now `False`
- Removed `testtool` commandline subcommand in favour of the `test` subcommand which can test both Tools and Networks
- Moved nodegroup specification into the Node for speedup

Fixed

- Stop Jobs from failing when a non-required, non-requested output is invalid
- Bug in boolean value parsing in the Boolean datatype
- Bug in target that caused paths not to be expanded properly in some cases
- Made sure failed sources also create a sample so the failure becomes visible and traceable.
- Bug in XNAT IOPlugin that made download from XNAT seem to fail (while getting the correct data).

Removed

- `fastr.current_network` has been removed as it was deemed to “magical” and could change things out of the sight of the user.

1.8.11 1.2.2 - 2017-08-24

Fixed

- Fixed a bug breaking the XNAT IOPlugin due to an `xnatpy` version update.

1.8.12 1.2.1 - 2017-04-04

Added

- A FastrInterface can now specify a `negate` flag on an automatic output that also has a prefix, which will negate the flag. This is useful for flag the suppress the creation of an output (e.g. `no_mask`). An example is given in the Tool `fastr.util.AutoPrefixNegateTest`.

Changed

- The provenance and extra information of a Job now is not serialized in the Job, but exported to separate files next to the job file `__fastr_prov__.json` and `__fastr_extra_job_info__.json` which makes the information more accessible and reduces the memory footprint of the main process hugely as it will not read this information back anymore.
- Most execution plugin will not overwrite the executionscript `stdout` and `stderr` but rather append it. This is only relevant when continuing a run in the an existing temporary directory, but avoids loss of information.

Fixed

- Bug that stopped the `Link.append` function from returning the newly created link
- Bugs that caused some cardinality computations of the output to fail during execution
- Bug in the `job.tmpurl` that caused double slashes somewhere. Some tools chocked on this when it was used for parameters.

1.8.13 1.2.0 - 2017-03-15

Added

- Failed sample annotation: when a job fails, the result is annotated and forwarded until a SinkNode, where we can determine the status and possibly point of failure of the Sample.
- Commandline tool `fastr trace` that can inspect a workflow run and help trace errors and print debug information
- Supported for Lmod modules environment next to the old environmentmodules
- `BaseDataType` descendants are now (un)picklable (including `EnumTypes`)
- Option to use `{extension}` field in `sink_data`, which differs from `{ext}` in that it doesn't include a leading dot.
- Support for Docker targets. A Docker target will execute a command inside of a specified docker container, allowing Tools to use Docker for distribution
- Using the right and left shift operator (`<<` and `>>`) for creating links to `Inputs` using `input << output` or `output >> input`.
- In the FastrInterfaces, automatic outputs can have a prefix for a flag that should be set for the output to be actually generated.
- Fastr is now able to limit the amount of SourceJobs that are allowed to run concurrently.
- Ability to report progress to PIM (use the `pim_host` field in the config)

Changed

- Version can now also accept a format based on a date (e.g. 2017-02-17_bananas) which will be parsed the same way as 2017.02.17_bananas
- Work on the ExecutionPlugin and the corresponding API. Has better fall-backs and a mechanism to advertise plugin capabilities.
- The collector plugins have the `input` and `input_parts` fields merged, and the `output` and `output_parts` fields merged.

Fixed

- In some cases the log directory was not created properly, causing an handled exception
- A bug making the handling of Booleans incorrect for the FastrInterface, when a Boolean was given a flag would also appear when it was False
- Serialization of the namespace of a Network was not correct
- Check version of Fastr that creates and executes a Job against each other
- `load_gpickle` helper can handle data with Enums that use to cause an `AttributeError`
- Output validation of Jobs did not work correctly for automatic outputs

1.8.14 1.1.2 - 2016-12-22

Fixed

- The example network in `resources/networks/add_ints.json` was using an old serialization format making it non-functions. Replaced by a new network file.

1.8.15 1.1.1 - 2016-12-22

Fixed

- Network runs called from an interpreter (and not file) caused a crash because the network tried to report the file used. Better handling of these situations.

1.8.16 1.1.0 - 2016-12-08

Added

- Namespaces for resources (tools and networks)
- Network manager located at `fastr.networklist`
- RQExecution plugin. This plugin uses `python-rq` to manage a job queue.
- LinearExecution plugin. This plugin uses a background thread for execution.
- BlockingExecution plugin. This plugin executes jobs in a blocking fashion.
- Automatic generation of documentation for all plugins, the configuration fields and all commandline tools.

Changed

- Provenance is updated with a network dump and used tool definitions.
- New configuration system that uses python files
- New plugin system that integrates with the new configuration system and enables automatic importing of plugins
- The fastr command line tools now use an entrypoint which is located in `fastr.utils.cmd`. This code also dispatches the sub commands.

Removed

- `fastr.config` file. This is replaced by the `config.py` file. Go to the docs!

Fixed

- Adds explicit tool namespace and version to the provenance document.

FASTR USER REFERENCE

2.1 Fastr User Reference

fastr.tools

A ToolManager containing all versions of all Tools loaded into the FASTR environment. The ToolManager can be indexed using the Tool id string or a tool id string and a version. For example if you have two versions (4.5 and 4.8) of a tool called *Elastix*:

```
>>> fastr.tools['elastix.Elastix']
Tool Elastix v4.8 (Elastix Registration)
    Inputs | |
    ↵Outputs | |
-----| |
    ↵fixed_image (ITKImageFile) | directory_
    ↵(Directory) | |
    ↵moving_image (ITKImageFile) | transform_
    ↵(ElastixTransformFile) | |
    ↵parameters (ElastixParameterFile) | log_file_
    ↵(ElastixLogFile) | |
    ↵fixed_mask (ITKImageFile) | |
    ↵moving_mask (ITKImageFile) | |
    ↵initial_transform (ElastixTransformFile) | |
    ↵priority (Elastix_4.8_interface_priority_Enum_) | |
    ↵threads (Int) | |

>>> fastr.tools['elastix.Elastix', '4.5']
Tool Elastix v4.5 (Elastix Registration)
    Inputs | |
    ↵Outputs | |
-----| |
    ↵fixed_image (ITKImageFile) | directory_
    ↵(Directory) | |
    ↵moving_image (ITKImageFile) | transform_
    ↵(ElastixTransformFile) | |
    ↵parameters (ElastixParameterFile) | log_file_
    ↵(ElastixLogFile) | |
    ↵fixed_mask (ITKImageFile) | |
    ↵moving_mask (ITKImageFile) | |
    ↵initial_transform (ElastixTransformFile) | |
    ↵priority (Elastix_4.5_interface_priority_Enum_) | |
    ↵threads (Int) | |
```

fastr.types

A dictionary containing all types loaded into the FASTR environment. The keys are the typenames and the values are the classes.

fastr.networks

A dictionary containing all networks loaded in fastr

api.create_network(version=None)

Create a new Network object

Parameters

- **id** (`str`) – id of the network
- **version** (`Union[Version, str, None]`) – version of the network

Return type `Network`**Returns****api.create_network_copy()**

Create a network based on another Network state. The network state can be a Network or the state gotten from a Network with `__getstate__`.

Parameters `network_state` (`Union[Network, Network, dict]`) – Network (state) to create a copy of**Return type** `Network`**Returns** The rebuilt network**class fastr.api.Network(id, version=None)**

Representation of a Network for the creating and adapting Networks

create_constant(datatype, data, id=None, step_id=None, resources=None, node_group=None)

Create a ConstantNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (`Union[BaseDataType, str]`) – The DataType of the constant node
- **data** (`Dict[str, Union[List[Union[str, Tuple[str, ...]]], Dict[str, Union[str, Tuple[str, ...]]]]]`) – The data to hold in the constant node
- **id** (`Optional[str]`) – The id of the constant node to be created
- **step_id** (`Optional[str]`) – The step to add the created constant node to
- **resources** (`Optional[ResourceLimit]`) – The resources required to run this node
- **node_group** (`Optional[str]`) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Return type `Node`**Returns** the newly created constant node**create_link(source, target, id=None, collapse=None, expand=False)**

Create a link between two Nodes and add it to the current Network.

Parameters

- **source** (`Union[Input, BaseInput]`) – the output that is the source of the link
- **target** (`Union[Output, BaseOutput]`) – the input that is the target of the link
- **id** (`Optional[str]`) – the id of the link

- **collapse** (`Optional[Tuple[Union[int, str], ...]]`) – The dimensions to collapse in this link.
- **expand** (`bool`) – Flag to expand cardinality into a new dimension

Return type `Link`

Returns the created link

create_macro (`network, id=None`)

Create macro node (a node which actually contains a network used as node inside another network).

Parameters

- **network** (`Union[Network, Network, dict, Tool, str]`) – The network to use, this can be a network (state), a macro tool, or the path to a python file that contains a function `create_network` which returns the desired network.
- **id** (`Optional[str]`) – The id of the node to be created

Return type `Node`

Returns the newly created node

create_node (`tool, tool_version, id=None, step_id=None, resources=None, node_group=None`)

Create a Node in this Network. The Node will be automatically added to the Network.

Parameters

- **tool** (`Union[Tool, str]`) – The Tool to base the Node on in the form: name / space / toolname:version
- **tool_version** (`str`) – The version of the tool wrapper to use
- **id** (`Optional[str]`) – The id of the node to be created
- **step_id** (`Optional[str]`) – The step to add the created node to
- **resources** (`Optional[ResourceLimit]`) – The resources required to run this node
- **node_group** (`Optional[str]`) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Return type `Node`

Returns the newly created node

create_sink (`datatype, id=None, step_id=None, resources=None, node_group=None`)

Create a SinkNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (`Union[BaseDataType, str]`) – The DataType of the sink node
- **id** (`Optional[str]`) – The id of the sink node to be created
- **step_id** (`Optional[str]`) – The step to add the created sink node to
- **resources** (`Optional[ResourceLimit]`) – The resources required to run this node
- **node_group** (`str`) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Return type `Node`

Returns the newly created sink node

create_source(datatype, id=None, step_id=None, resources=None, node_group=None)

Create a SourceNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (BaseDataType) – The DataType of the source source_node
- **id** (*str*) – The id of the source source_node to be created
- **step_id** (*str*) – The step to add the created source source_node to
- **resources** (*Optional[ResourceLimit]*) – The resources required to run this node
- **node_group** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Returns the newly created source source_node

Return type SourceNode

draw(file_path=None, draw_dimensions=True, hide_unconnected=True, expand_macros=1, font_size=14)

Draw a graphical representation of the Network

Parameters

- **file_path** (*str*) – The path of the file to create, the extension will control the image type
- **draw_dimensions** (*bool*) – Flag to control if the dimension sizes should be drawn in the figure, default is true
- **expand_macros** (*bool*) – Flag to control if and how macro nodes should be expanded, by default 1 level is expanded

Return type *Optional[str]*

Returns path of the image created or None if failed

execute(source_data, sink_data, tmpdir=None, timestamp=None, blocking=True, execution_plugin=None)

Execute the network with the given source and sink data.

Parameters

- **source_data** (*Dict[str, Union[List[Union[str, Tuple[str, ...]]], Dict[str, Union[str, Tuple[str, ...]]]]]*) – Source data to use as an input
- **sink_data** (*Union[str, Dict[str, str]]*) – Sink rules to use for determining the outputs
- **tmpdir** (*Optional[str]*) – The scratch directory to use for this network run, if an existing directory is given, fastr will try to resume a network run (see *Continuing a Network*)
- **timestamp** (*Union[datetime, str, None]*) – The timestamp of the network run (useful for retrying or continuing previous runs)
- **blocking** (*bool*) – Flag to indicate if the execution should be blocking or launched in a background thread
- **execution_plugin** (*Optional[str]*) – The execution plugin to use for this run

Return type *NetworkRun*

Returns The network run object for the started execution

property id

The unique id describing this resource

Return type `str`

classmethod load(*filename*)

Load Network froma file

Parameters `filename (str)` –

Returns loaded network

Return type `Network`

save(*filename*, *indent*=2)

Save the Network to a JSON file

Parameters

- `filename (str)` – Path of the file to save to
- `indent (int)` – Indentation to use (None for no indentation)

property version

Version of the Network (so users can keep track of their version)

Return type `Version`

class fastr.api.Link(*parent*)

Representation of a link for editing the Network

property collapse

The dimensions which the link will collapse into the cardinality

Return type `Tuple[Union[int, str], ...]`

property expand

Flag that indicates if the Link will expand the cardinality into a new dimension.

Return type `bool`

property id

The unique id describing this resource

Return type `str`

class fastr.api.Node(*parent*)

Representation of Node for editing the Network

property id

The unique id describing this resource

Return type `str`

property input

In case there is only a single Inputs in a Node, this can be used as a short hand. In that case it is basically the same as `list(node.inputs.values())[0]`.

Return type `Input`

property inputs

Mapping object containing all Inputs of a Node

Return type `InputMap`

property output

In case there is only a single Outputs in a Node, this can be used as a short hand. In that case it is basically the same as `list(node.outputs.values())[0]`.

Return type `Output`

property outputs

Mapping object containing all Outputs of a Node

Return type `SubObjectMap[Output]`

class fastr.api.Input (parent)

Representation of an Input of a Node

__lshift__ (other)

This operator allows the easy creation of Links to this Input using the `<<` operator. Creating links can be done by:

```
# Generic form
>> link = input << output
>> link = input << ['some', 'data'] # Create a constant node

# Examples
>> link1 = addint.inputs['left_hand'] << source1.input
>> link2 = addint.inputs['right_hand'] << [1, 2, 3]

# Multiple links
>> links = addints.inputs['left_hand'] << (source1.output, source2.output,
   ↴source3.output)
```

The last example would return a tuple with three links.

Parameters other (`Union[Output, BaseOutput, list, dict, tuple]`) – the target to create the link from, this can be an Output, a tuple of Outputs, or a data structure that can be used as the data for a ConstantNode

Return type `Union[Link, Tuple[Link, ...]]`

Returns Newly created link(s)

__rrshift__ (other)

This operator allows to use the `>>` operator as alternative to using the `<<` operator. See the `__lshift__ operator` for details.

Parameters other (`Union[Output, BaseOutput, list, dict, tuple]`) – the target to create the link from

Return type `Union[Link, Tuple[Link, ...]]`

Returns Newly created link(s)

append (value)

Create a link from give resource to a new SubInput.

Parameters value (`Union[Output, BaseOutput, list, dict, tuple]`) – The source for the link to be created

Return type `Link`

Returns The newly created link

property id

The unique id describing this resource

Return type `str`

property `input_group`

The input group of this Input. This property can be read and changed. Changing the input group of an Input will influence the data flow in a Node (see [Advanced flows in a Node](#) for details).

Return type `str`

class `fastr.api.Output` (`parent`)

Representation of an Output of a Node

__getitem__ (`item`)

Get a SubOutput of this Output. The SubOutput selects some data from the parent Output based on an index or slice of the cardinality.

Parameters `key` – the key of the requested item, can be an index or slice

Return type `Output`

Returns the requested SubOutput with a view of the data in this Output

property `id`

The unique id describing this resource

Return type `str`

FASTR DEVELOPER MODULE REFERENCE

3.1 fastr Package

3.1.1 fastr Package

Initialize self. See help(type(self)) for accurate signature.

`fastr.__init__.dir__()` → list
default dir() implementation

`fastr.__init__.format__()`
default object formatter

`fastr.__init__.init_subclass__()`
This method is called when a class is subclassed.

The default implementation does nothing. It may be overridden to extend subclasses.

`fastr.__init__.new__()`
Create and return a new object. See help(type) for accurate signature.

`fastr.__init__.reduce__()`
helper for pickle

`fastr.__init__.reduce_ex__()`
helper for pickle

`fastr.__init__.sizeof__()` → int
size of object in memory, in bytes

`fastr.__init__.subclasshook__()`
Abstract classes can override this to customize issubclass().

This is invoked early on by abc.ABCMeta.__subclasscheck__(). It should return True, False or NotImplemented. If it returns NotImplemented, the normal algorithm is used. Otherwise, it overrides the normal algorithm (and the outcome is cached).

3.1.2 exceptions Module

This module contains all Fastr-related Exceptions

`exception fastr.exceptions.FastrAttributeError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError, AttributeError`

AttributeError in the fastr system

```
__module__ = 'fastr.exceptions'
exception fastr.exceptions.FastrCannotChangeAttributeError(*args, **kwargs)
    Bases: fastr.exceptions.FastrError
```

Attempting to change an attribute of an object that can be set only once.

```
__module__ = 'fastr.exceptions'
exception fastr.exceptions.FastrCardinalityError(*args, **kwargs)
    Bases: fastr.exceptions.FastrError
```

The description of the cardinality is not valid.

```
__module__ = 'fastr.exceptions'
exception fastr.exceptions.FastrCollectorError(*args, **kwargs)
    Bases: fastr.exceptions.FastrError
```

Cannot collect the results from a Job because of an error

```
__module__ = 'fastr.exceptions'
exception fastr.exceptions.FastrDataTypeFileNotFoundException(*args, **kwargs)
    Bases: fastr.exceptions.FastrError
```

Could not read the datatype file.

```
__module__ = 'fastr.exceptions'
exception fastr.exceptions.FastrDataTypeMismatchError(*args, **kwargs)
    Bases: fastr.exceptions.FastrError
```

When using a DataType as the key for the DataTypeManager, the DataTypeManager found another DataType with the same name already in the DataTypeManager. This means fastr has two version of the same DataType in the system, which should never happen!

```
__module__ = 'fastr.exceptions'
exception fastr.exceptions.FastrDataTypeNotFoundError(*args, **kwargs)
    Bases: fastr.exceptions.FastrError
```

The DataType requested is not found by the fastr system. Typically this means that no matching DataType is found in the DataTypeManager.

```
__module__ = 'fastr.exceptions'
exception fastr.exceptions.FastrDataTypeNotInstantiableError(*args, **kwargs)
    Bases: fastr.exceptions.FastrError
```

The base classes for DataTypes cannot be instantiated and should always be sub-classed.

```
__module__ = 'fastr.exceptions'
exception fastr.exceptions.FastrDataTypeValueError(*args, **kwargs)
    Bases: fastr.exceptions.FastrError
```

This value in fastr did not pass the validation specified for its DataType, typically means that the data is missing or corrupt.

```
__module__ = 'fastr.exceptions'
exception fastr.exceptions.FastrError(*args, **kwargs)
    Bases: Exception
```

This is the base class for all fastr related exceptions. Catching this class of exceptions should ensure a proper execution of fastr.

```
__init__(*args, **kwargs)
    Constructor for all exceptions. Saves the caller object fullid (if found) and the file, function and line
    number where the object was created.

__module__ = 'fastr.exceptions'

__repr__()
    String representation of the error

    Returns error representation

    Return type str

__str__()
    String value of the error

    Returns error string

    Return type str

__weakref__
    list of weak references to the object (if defined)

excerpt()
    Return a excerpt of the Error as a tuple.

exception fastr.exceptions.FastrErrorInSubprocess(*args, **kwargs)
Bases: fastr.exceptions.FastrExecutionError

Encountered an error in the subprocess started by the execution script

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrExecutableNotFoundError(executable=None, *args, **kwargs)
Bases: fastr.exceptions.FastrExecutionError

The executable could not be found!

__init__(executable=None, *args, **kwargs)
    Constructor for all exceptions. Saves the caller object fullid (if found) and the file, function and line
    number where the object was created.

__module__ = 'fastr.exceptions'

__str__()
    String representation of the error

exception fastr.exceptions.FastrExecutionError(*args, **kwargs)
Bases: fastr.exceptions.FastrError

Base class for all fastr execution related errors

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrFileNotFoundException(filepath, message=None)
Bases: fastr.exceptions.FastrError

Could not find an expected file

__init__(filepath, message=None)
    Constructor for all exceptions. Saves the caller object fullid (if found) and the file, function and line
    number where the object was created.

__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrIOError(*args, **kwargs)
```

Bases: *fastr.exceptions.FastrError, OSError*

IOError in the fastr system

```
__module__ = 'fastr.exceptions'
```

```
__weakref__
```

list of weak references to the object (if defined)

```
exception fastr.exceptions.FastrImportError(*args, **kwargs)
```

Bases: *fastr.exceptions.FastrError, ImportError*

ImportError in the fastr system

```
__module__ = 'fastr.exceptions'
```

```
__weakref__
```

list of weak references to the object (if defined)

```
exception fastr.exceptions.FastrIndexError(*args, **kwargs)
```

Bases: *fastr.exceptions.FastrError, IndexError*

IndexError in the fastr system

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrIndexNonexistent(*args, **kwargs)
```

Bases: *fastr.exceptions.FastrIndexError*

This is an IndexError for samples requested from a sparse data array. The sample is not there but is probably not there because of sparseness rather than being a missing sample (e.g. out of bounds).

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrKeyError(*args, **kwargs)
```

Bases: *fastr.exceptions.FastrError, KeyError*

KeyError in the fastr system

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrLockNotAcquired(directory, message=None)
```

Bases: *fastr.exceptions.FastrError*

Could not lock a directory

```
__init__(directory, message=None)
```

Constructor for all exceptions. Saves the caller object fullid (if found) and the file, function and line number where the object was created.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrLookupError(*args, **kwargs)
```

Bases: *fastr.exceptions.FastrError*

Could not find specified object in the fastr environment.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrMountUnknownError(*args, **kwargs)
```

Bases: *fastr.exceptions.FastrKeyError*

Trying to access an undefined mount

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrNetworkMismatchError (*args, **kwargs)
Bases: fastr.exceptions.FastrError
```

Two interacting objects belong to different fastr network.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrNetworkUnknownError (*args, **kwargs)
Bases: fastr.exceptions.FastrKeyError
```

Reference to a Tool that is not recognised by the fastr system. This typically means the specific id/version combination of the requested tool has not been loaded by the ToolManager.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrNoValidTargetException (*args, **kwargs)
Bases: fastr.exceptions.FastrKeyError
```

Cannot find a valid target for the tool

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrNodeAlreadyPreparedError (*args, **kwargs)
Bases: fastr.exceptions.FastrStateError
```

A attempt is made at preparing a NodeRun for the second time. This is not allowed as it would wipe the current execution data and cause data-loss.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrNodeNotPreparedError (*args, **kwargs)
Bases: fastr.exceptions.FastrStateError
```

When trying to access execution data of a NodeRun, the NodeRun must be prepare. The NodeRun has not been prepared by the execution, so the data is not available!

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrNodeNotValidError (*args, **kwargs)
Bases: fastr.exceptions.FastrStateError
```

A NodeRun is not in a valid state where it should be, typically an invalid NodeRun is passed to the executor causing trouble.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrNotExecutableError (*args, **kwargs)
Bases: fastr.exceptions.FastrExecutionError
```

The command invoked by subprocess is not executable on the system

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrNotImplementedError (*args, **kwargs)
Bases: fastr.exceptions.FastrError, NotImplementedError
```

This function/method has not been implemented on purpose (e.g. should be overwritten in a sub-class)

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrOSError (*args, **kwargs)
Bases: fastr.exceptions.FastrError, OSError
```

OSError in the fastr system

```
__module__ = 'fastr.exceptions'
```

__weakref__

list of weak references to the object (if defined)

exception `fastr.exceptions.FastrObjectUnknownError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrKeyError`

Reference to a Tool that is not recognised by the fastr system. This typically means the specific id/version combination of the requested tool has not been loaded by the ToolManager.

__module__ = 'fastr.exceptions'

exception `fastr.exceptions.FastrOptionalModuleNotAvailableError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrNotImplementedError`

A optional modules for Fastr is needed for this function, but is not available on the current python installation.

__module__ = 'fastr.exceptions'

exception `fastr.exceptions.FastrOutputValidationError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrExecutionError`

An output of a Job does not pass validation

__module__ = 'fastr.exceptions'

exception `fastr.exceptions.FastrParentMismatchError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrError`

Two interactive objects have different parent where they should be the same

__module__ = 'fastr.exceptions'

exception `fastr.exceptions.FastrPluginCapabilityNotImplemented(*args, **kwargs)`

Bases: `fastr.exceptions.FastrNotImplementedError`

A plugin did not implement a capability that it advertised.

__module__ = 'fastr.exceptions'

exception `fastr.exceptions.FastrPluginNotAvailable(*args, **kwargs)`

Bases: `fastr.exceptions.FastrKeyError`

Indicates that a requested Plugin was not found on the system.

__module__ = 'fastr.exceptions'

exception `fastr.exceptions.FastrPluginNotLoaded(*args, **kwargs)`

Bases: `fastr.exceptions.FastrStateError`

The plugin was not successfully loaded. This means the plugin class cannot be instantiated.

__module__ = 'fastr.exceptions'

exception `fastr.exceptions.FastrResultFileNotFound(filepath, message=None)`

Bases: `fastr.exceptions.FastrFileNotFoundException`, `fastr.exceptions.FastrExecutionError`

Could not find the result file of job that finished. This means the executionscript process was killed during interruption. Generally this means a scheduler killed it because of resource shortage.

__module__ = 'fastr.exceptions'

exception `fastr.exceptions.FastrScriptNotFoundError(interpreter=None, script=None, paths=None, *args, **kwargs)`

Bases: `fastr.exceptions.FastrExecutionError`

Script could not be found

`__init__(interpreter=None, script=None, paths=None, *args, **kwargs)`

Constructor for all exceptions. Saves the caller object fullid (if found) and the file, function and line number where the object was created.

`__module__ = 'fastr.exceptions'`

`__str__()`

String value of the error

Returns error string

Return type str

`exception fastr.exceptions.FastrSerializationError(message, serializer, original_exception=None)`

Bases: `fastr.exceptions.FastrError`

The serialization encountered a serious problem

`__init__(message, serializer, original_exception=None)`

Constructor for all exceptions. Saves the caller object fullid (if found) and the file, function and line number where the object was created.

`__module__ = 'fastr.exceptions'`

`__repr__()`

Simple string representation of the exception

`__str__()`

Advanced string representation of the exception including the data about where in the schema things went wrong.

`exception fastr.exceptions.FastrSerializationIgnoreDefaultError(message, serializer, original_exception=None)`

Bases: `fastr.exceptions.FastrSerializationError`

The value and default are both None, so the value should not be serialized.

`__module__ = 'fastr.exceptions'`

`exception fastr.exceptions.FastrSerializationInvalidDataError(message, serializer, original_exception=None)`

Bases: `fastr.exceptions.FastrSerializationError`

Encountered data to serialize that is invalid given the serialization schema.

`__module__ = 'fastr.exceptions'`

`exception fastr.exceptions.FastrSerializationMethodError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrKeyError`

The desired serialization method does not exist.

`__module__ = 'fastr.exceptions'`

`exception fastr.exceptions.FastrSinkDataUnavailableError(*args, **kwargs)`

Bases: `fastr.exceptions.FastrKeyError`

Could not find the Sink data for the desire sink.

`__module__ = 'fastr.exceptions'`

```
exception fastr.exceptions.FastrSizeInvalidError(*args, **kwargs)
Bases: fastr.exceptions.FastrError
```

The given size cannot be valid.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrSizeMismatchError(*args, **kwargs)
Bases: fastr.exceptions.FastrError
```

The size of two object in fastr is not matching where it should.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrSizeUnknownError(*args, **kwargs)
Bases: fastr.exceptions.FastrError
```

The size of object is not (yet) known and only a theoretical estimate is available at the moment.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrSourceDataUnavailableError(*args, **kwargs)
Bases: fastr.exceptions.FastrKeyError
```

Could not find the Source data for the desire source.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrStateError(*args, **kwargs)
Bases: fastr.exceptions.FastrError
```

An object is in an invalid/unexpected state.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrSubprocessNotFinished(*args, **kwargs)
Bases: fastr.exceptions.FastrExecutionError
```

Encountered an error before the subprocess call by the execution script was properly finished.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrToolNotFoundError(*args, **kwargs)
Bases: fastr.exceptions.FastrError
```

The tool used is not available on the current platform (OS and architecture combination) and cannot be used.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrToolTargetNotFound(*args, **kwargs)
Bases: fastr.exceptions.FastrError
```

Could not determine the location of the tools target binary/script. The tool cannot be used.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrToolUnknownError(*args, **kwargs)
Bases: fastr.exceptions.FastrKeyError
```

Reference to a Tool that is not recognised by the fastr system. This typically means the specific id/version combination of the requested tool has not been loaded by the ToolManager.

```
__module__ = 'fastr.exceptions'
```

```
exception fastr.exceptions.FastrToolVersionError(*args, **kwargs)
Bases: fastr.exceptions.FastrError

Version mismatch, usually the installed tool version and version requested by the network mismatch.

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrTypeError(*args, **kwargs)
Bases: fastr.exceptions.FastrError, TypeError

TypeError in the fastr system

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrUnknownURLSchemeError(*args, **kwargs)
Bases: fastr.exceptions.FastrKeyError

Fastr encountered a data URL with a scheme that was not recognised by the IOPlugin manager.

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrValueError(*args, **kwargs)
Bases: fastr.exceptions.FastrError, ValueError

ValueError in the fastr system

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrVersionInvalidError(*args, **kwargs)
Bases: fastr.exceptions.FastrValueError

The string representation of the version is malformed.

__module__ = 'fastr.exceptions'

exception fastr.exceptions.FastrVersionMismatchError(*args, **kwargs)
Bases: fastr.exceptions.FastrValueError

There is a mismatch between different parts of the Fastr environment and integrity is compromised.

__module__ = 'fastr.exceptions'

fastr.exceptions.get_message(exception)
Extract the message from an exception is a safe manner

Parameters exception (BaseException) – exception to extract from
Returns message string
Return type str
```

3.1.3 version Module

This module keeps track of the version of the currently used Fastr framework. It can check its version from mercurial or a saved file

```
fastr.version.clear_version()
Remove the cached version info

fastr.version.get_base_version()
Get the version from the top-level version file

Return type Optional[str]
Returns the version
```

Rtype str

```
fastr.version.get_hg_info()
```

Read information about the current mercurial branch and revision

Return type Tuple[Optional[str], Optional[str]]

Returns tuple containing head revision and branch

```
fastr.version.get_saved_version()
```

Get cached version from file

Return type Tuple[Optional[str], Optional[str], Optional[str]]

Returns tuple with version, head revision and branch

```
fastr.version.save_version(current_version, current_hg_head, current_hg_branch)
```

Cache the version information (useful for when installing)

Parameters

- **current_version** (str) – version
- **current_hg_head** (str) – mercurial head revision
- **current_hg_branch** (str) – mercurial branch

Returns

3.1.4 Subpackages

api Package

api Package

This module provides the API for fastr that users should use. This API will be considered stable between major versions. If users only interact via this API (and refrain from operating on `parent` attributes), their code should be compatible within major version of fastr.

```
fastr.api.create_network(id, version=None)
```

Create a new Network object

Parameters

- **id** (str) – id of the network
- **version** (Union[Version, str, None]) – version of the network

Return type `Network`

Returns

```
fastr.api.create_network_copy(network_state)
```

Create a network based on another Network state. The network state can be a Network or the state gotten from a Network with `__getstate__`.

Parameters `network_state` (Union[`Network`, `Network`, dict]) – Network (state) to create a copy of

Return type `Network`

Returns The rebuilt network

```
class fastr.api.ResourceLimit (cores=1, memory='2G', time=None)
```

Bases: `object`

`__eq__(other)`

Check if two resource limits are equal

Parameters `other` – resource limit to test against

Return type `bool`

`__getstate__()`

Return type `dict`

`__hash__ = None`

`__init__(cores=1, memory='2G', time=None)`

An object describing resource requirements/limits for a node

Parameters

- `cores` (`Optional[int]`) – number of cores
- `memory` (`Union[str, int, None]`) – memory specification, can be int with number of megabytes or a string with numbers ending on M, G, T, P for megabytes, gigabytes, terabytes or petabytes. Note that the number has to be an integer, e.g. 1500M would work, whereas 1.5G would be invalid
- `time` (`Union[str, int, None]`) – run time specification, this can be an int with the number of seconds or a string in the HH:MM:SS, MM:SS, or SS format. Where HH, MM, and SS are integers representing the number of hours, minutes and seconds.

`__module__ = 'fastr.core.resourcelimit'`

`__ne__(other)`

Check if two resource limits are not equal

Parameters `other` – resource limit to test against

Return type `bool`

`__setstate__(state)`

`__slots__ = ('_cores', '_memory', '_time')`

`copy()`

Return a copy of current resource limit object

Return type `ResourceLimit`

property `cores`

The required number of gpus

Return type `int`

property `memory`

The required memory in megabytes

Return type `int`

property `time`

The required time in seconds

Return type `int`

core Package

core Package

This module contains all of the core components of fastr. It has the classes to create networks and work with them.

cardinality Module

```
class fastr.core.cardinality.AnyCardinalitySpec(parent)
Bases: fastr.core.cardinality.CardinalitySpec
```

```
__eq__(other)
```

Test for equality

```
__hash__ = None
```

```
__module__ = 'fastr.core.cardinality'
```

```
__str__()
```

String version of the cardinality spec, should be parseable by create_cardinality

Return type str

```
validate(payload, cardinality)
```

Validate cardinality given a payload and cardinality

Parameters

- payload (dict) – Payload of the corresponding job
- cardinality (int) – Cardinality to validate

Return type bool

Returns Validity of the cardinality given the spec and payload

```
class fastr.core.cardinality.AsCardinalitySpec(parent, target)
Bases: fastr.core.cardinality.CardinalitySpec
```

```
__eq__(other)
```

Test for equality

```
__hash__ = None
```

```
__init__(parent, target)
```

Initialize self. See help(type(self)) for accurate signature.

```
__module__ = 'fastr.core.cardinality'
```

```
__str__()
```

String version of the cardinality spec, should be parseable by create_cardinality

Return type str

```
calculate_execution_cardinality(key=None)
```

Calculate the cardinality given the node and spec, during execution this should be available and not give unknowns once the data is present and the key is given.

Parameters key – Key for which the cardinality is calculated

Return type Optional[int]

Returns calculated cardinality

calculate_job_cardinality(*payload*)

Calculate the actually cardinality when a job needs to know how many arguments to create for a non-automatic output.

Return type `Optional[int]`

calculate_planning_cardinality()

Calculate the cardinality given the node and spec, for cardinalities that only have validation and not a pre-calculable value, this return None.

Parameters `node` – Node for which the cardinality is calculated

Return type `Optional[int]`

Returns calculated cardinality

property node**property predefined**

Indicate whether the cardinality is predefined or can only be calculated after execution

class fastr.core.cardinality.CardinalitySpec(*parent*)

Bases: `object`

`__dict__ = mappingproxy({ '__module__': 'fastr.core.cardinality', '__init__': <function`

abstract __eq__(*other*)

Test for equality

`__hash__ = None`

__init__(*parent*)

Initialize self. See help(type(self)) for accurate signature.

`__module__ = 'fastr.core.cardinality'`

__ne__(*other*)

Return self!=value.

__repr__()

Console representation of the cardinality spec

Return type `str`

abstract __str__()

String version of the cardinality spec, should be parseable by `create_cardinality`

Return type `str`

__weakref__

list of weak references to the object (if defined)

calculate_execution_cardinality(*key=None*)

Calculate the cardinality given the node and spec, during execution this should be available and not give unknowns once the data is present and the key is given.

Parameters `key` – Key for which the cardinality is calculated

Return type `Optional[int]`

Returns calculated cardinality

calculate_job_cardinality(*payload*)

Calculate the actually cardinality when a job needs to know how many arguments to create for a non-automatic output.

Return type `Optional[int]`

calculate_planning_cardinality()

Calculate the cardinality given the node and spec, for cardinalities that only have validation and not a pre-calculable value, this return None.

Parameters `node` – Node for which the cardinality is calculated

Return type `Optional[int]`

Returns calculated cardinality

property predefined

Indicate whether the cardinality is predefined or can only be calculated after execution

validate(payload, cardinality, planning=True)

Validate cardinality given a payload and cardinality

Parameters

- `payload` (`Optional[dict]`) – Payload of the corresponding job
- `cardinality` (`int`) – Cardinality to validate

Return type `bool`

Returns Validity of the cardinality given the spec and payload

class `fastr.core.cardinality.ChoiceCardinalitySpec(parent, options)`
Bases: `fastr.core.cardinality.CardinalitySpec`

__eq__(other)

Test for equality

__hash__ = None

__init__(parent, options)

Initialize self. See help(type(self)) for accurate signature.

__module__ = 'fastr.core.cardinality'

__str__()

String version of the cardinality spec, should be parseable by `create_cardinality`

Return type `str`

class `fastr.core.cardinality.IntCardinalitySpec(parent, value)`
Bases: `fastr.core.cardinality.CardinalitySpec`

__eq__(other)

Test for equality

__hash__ = None

__init__(parent, value)

Initialize self. See help(type(self)) for accurate signature.

__module__ = 'fastr.core.cardinality'

__str__()

String version of the cardinality spec, should be parseable by `create_cardinality`

Return type `str`

calculate_execution_cardinality(node)

Calculate the cardinality given the node and spec, during execution this should be available and not give unknowns once the data is present and the key is given.

Parameters `key` – Key for which the cardinality is calculated

Return type `int`

Returns calculated cardinality

calculate_job_cardinality (`payload`)

Calculate the actually cardinality when a job needs to know how many arguments to create for a non-automatic output.

Return type `Optional[int]`

calculate_planning_cardinality ()

Calculate the cardinality given the node and spec, for cardinalities that only have validation and not a pre-calculable value, this return None.

Parameters `node` – Node for which the cardinality is calculated

Return type `int`

Returns calculated cardinality

property predefined

Indicate whether the cardinality is predefined or can only be calculated after execution

class `fastr.core.cardinality.MaxCardinalitySpec` (`parent, value`)

Bases: `fastr.core.cardinality.CardinalitySpec`

__eq__ (`other`)

Test for equality

__hash__ = `None`

__init__ (`parent, value`)

Initialize self. See help(type(self)) for accurate signature.

__module__ = `'fastr.core.cardinality'`

__str__ ()

String version of the cardinality spec, should be parseable by `create_cardinality`

Return type `str`

class `fastr.core.cardinality.MinCardinalitySpec` (`parent, value`)

Bases: `fastr.core.cardinality.CardinalitySpec`

__eq__ (`other`)

Test for equality

__hash__ = `None`

__init__ (`parent, value`)

Initialize self. See help(type(self)) for accurate signature.

__module__ = `'fastr.core.cardinality'`

__str__ ()

String version of the cardinality spec, should be parseable by `create_cardinality`

Return type `str`

class `fastr.core.cardinality.RangeCardinalitySpec` (`parent, min, max`)

Bases: `fastr.core.cardinality.CardinalitySpec`

__eq__ (`other`)

Test for equality

```
__hash__ = None
__init__(parent, min, max)
    Initialize self. See help(type(self)) for accurate signature.
__module__ = 'fastr.core.cardinality'
__str__()
    String version of the cardinality spec, should be parseable by create_cardinality

    Return type str

class fastr.core.cardinality.ValueCardinalitySpec(parent, target)
Bases: fastr.core.cardinality.CardinalitySpec

__eq__(other)
    Test for equality

__hash__ = None
__init__(parent, target)
    Initialize self. See help(type(self)) for accurate signature.
__module__ = 'fastr.core.cardinality'
__str__()
    String version of the cardinality spec, should be parseable by create_cardinality

    Return type str

calculate_execution_cardinality(key=None)
    Calculate the cardinality given the node and spec, during execution this should be available and not give
    unknowns once the data is present and the key is given.

        Parameters key – Key for which the cardinality is calculated

        Return type Optional[int]

        Returns calculated cardinality

calculate_job_cardinality(payload)
    Calculate the actually cardinality when a job needs to know how many arguments to create for a non-
    automatic output.

        Return type Optional[int]

property node

fastr.core.cardinality.create_cardinality(desc, parent)
    Create simplified description of the cardinality. This changes the string representation to a tuple that is easier to
    check at a later time.

        Parameters desc (str) – the string version of the cardinality

        Parent the parent input or output to which this cardinality spec belongs

        Return type CardinalitySpec

        Returns the simplified cardinality description

        Raises FastrCardinalityError – if the Input/Output has an incorrect cardinality description.
```

The translation works with the following table:

cardinality string	cardinality spec	description
"*", any	“(‘any’,)“	Any cardinality is allowed
"N"	('int', N)	A cardinality of N is required
"N-M"	('range', N, M)	A cardinality between N and M is required
"*-M"	('max', M)	A cardinality of maximal M is required
"N-*"	('min', N)	A cardinality of minimal N is required
"[M, N, ..., O, P]"	('choice', [M, N, ..., O, P])	The cardinality should one of the given options
"as:input_id"	('as', 'input_id')	The cardinality should match the cardinality of the given Input
"val:input_id"	('val', 'input_id')	The cardinality should match the value of the given Input

Note: The maximum, minimum and range are inclusive

dimension Module

class fastr.core.dimension.**Dimension**(name, size)

Bases: `object`

A class representing a dimension. It contains the name and size of the dimension.

__eq__(other)

Dimension is the same if the name and size are the same

__hash__ = `None`

__init__(name, size)

The constructor for the dimension.

Parameters

- **name** (`str`) – Name of the dimension
- **size** (`int` or `sympy.Symbol`) – Size fo the dimension

__module__ = 'fastr.core.dimension'

__ne__(other)

The not equal test is simply the inverse of the equal test

__repr__()

String representation of a Dimension

__slots__ = ('_name', '_size')

copy()

Get a copy object of a Dimension

property name

property size

update_size(value)

class fastr.core.dimension.**ForwardsDimensions**

Bases: `fastr.core.dimension.HasDimensions`

Class of objects that have dimensions not because they contain data with dimensions but forward them (optionally with changes via `combine_dimensions`)

```
__abstractmethods__ = frozenset({'combine_dimensions', 'source'})  
__module__ = 'fastr.core.dimension'
```

abstract combine_dimensions(dimensions)

Method to combine/manipulate the dimensions

Parameters `dimensions` – the input dimensions from the source

Returns dimensions manipulated for this object

Return type tuple of dimensions

property dimensions

The dimensions of the object based on the forwarding

abstract property source

The source object from which the dimensions are forwarded

Returns the object from which the dimensions are forwarded

Return type `HasDimensions`

```
class fastr.core.dimension.HasDimensions
```

Bases: `object`

A Mixin class for any object that has a notion of dimensions and size. It uses the `dimension` property to expose the dimension name and size.

```
__abstractmethods__ = frozenset({'dimensions'})
```

```
__dict__ = mappingproxy({ '__module__': 'fastr.core.dimension', '__doc__': '\n A Mixin
```

```
__module__ = 'fastr.core.dimension'
```

```
__weakref__
```

list of weak references to the object (if defined)

abstract property dimensions

The dimensions has to be implemented by any subclass. It has to provide a tuple of Dimensions.

Returns dimensions

Return type tuple

property dimnames

A tuple containing the dimension names of this object. All items of the tuple are of type str.

property ndims

The number of dimensions in this object

property size

A tuple containing the size of this object. All items of the tuple are of type int or sympy.Symbol.

interface Module

A module that describes the interface of a Tool. It specifies how a set of input values will be translated to commands to be executed. This creates a generic interface to different ways of executing underlying software.

```

class fastr.core.interface.InputSpec
Bases: fastr.core.interface.InputSpec

Class containing the information about an Input Specification, this is essentially a data class (but

__dict__ = mappingproxy({ '__module__': 'fastr.core.interface', '__doc__': '\n Class \n\n Create new instance of InputSpec(id, cardinality, datatype, required=False, description='', default=None, hid- den=False) \n\n Create new instance of InputSpec(id, cardinality, datatype, required, description, default, hidden) \n\n asdict() \n\n fastr.core.interface.InputSpecBase \n\n alias of fastr.core.interface.InputSpec \n\n class fastr.core.interface.Interface \n\n Bases: fastr.abc.baseplugin.Plugin, fastr.abc.serializable.Serializable \n\n Abstract base class of all Interfaces. Defines the minimal requirements for all Interface implementations. \n\n __abstractmethods__ = frozenset({'__getstate__', '__setstate__', 'execute', 'expanding'}) \n\n abstract __getstate__() \n\n Retrieve the state of the Interface \n\n Returns the state of the object \n\n Rtype dict \n\n __module__ = 'fastr.core.interface' \n\n abstract __setstate__(state) \n\n Set the state of the Interface \n\n abstract execute(target, payload) \n\n Execute the interface given the a target and payload. The payload should have the form:

```

```
{
    'input': {
        'input_id_a': (value, value),
        'input_id_b': (value, value)
    },
    'output': {
        'output_id_a': (value, value),
        'output_id_b': (value, value)
    }
}
```

Parameters

- **target** – the target to call
- **payload** – the payload to use

Returns the result of the execution

Return type (tuple of) *InterfaceResult*

abstract property expanding

Indicates whether or not this Interface will result in multiple samples per run. If the flow is unaffected, this will be zero, if it is nonzero it means that number of dimension will be added to the sample array.

abstract property inputs

OrderedDict of Inputs connected to the Interface. The format should be {input_id: InputSpec}.

abstract property outputs

OrderedDict of Output connected to the Interface. The format should be {output_id: OutputSpec}.

classmethod test()

Test the plugin, interfaces do not need to be tested on import

class fastr.core.interface.InterfaceResult(result_data, target_result, payload, sample_index=None, sample_id=None, errors=None)

Bases: object

The class in which Interfaces should wrap their results to be picked up by fastr

__dict__ = mappingproxy({ '__module__': 'fastr.core.interface', '__doc__': '\n The cl

__init__(result_data, target_result, payload, sample_index=None, sample_id=None, errors=None)

Initialize self. See help(type(self)) for accurate signature.

__module__ = 'fastr.core.interface'

__weakref__

list of weak references to the object (if defined)

class fastr.core.interface.OutputSpec

Bases: fastr.core.interface.OutputSpec

Class containing the information about an Output Specification, this is essentially a data class (but

__dict__ = mappingproxy({ '__module__': 'fastr.core.interface', '__doc__': '\n Class o

__module__ = 'fastr.core.interface'

static __new__(cls, id_, cardinality, datatype, automatic=True, required=False, description='', hidden=False)

Create new instance of OutputSpec(id, cardinality, datatype, automatic, required, description, hidden)

asdict()

fastr.core.interface.OutputSpecBase

alias of fastr.core.interface.OutputSpec

ioplugin Module

This module contains the manager class for IOPlugins and the base class for all IOPlugins

class fastr.core.ioplugin.IOPlugin

Bases: fastr.abc.baseplugin.Plugin

IOPlugins are used for data import and export for the sources and sinks. The main use of the *IOPlugins* is during execution (see *Execution*). The *IOPlugins* can be accessed via fastr.ioplugins, but generally there should be no need for direct interaction with these objects. The use of is mainly via the URL used to specify source and sink data.

__abstractmethods__ = frozenset({'scheme'})

__init__()

Initialization for the IOPlugin

Returns newly created IOPlugin

__module__ = 'fastr.core.ioplugin'

cleanup()

(abstract) Clean up the IOPlugin. This is to do things like closing files or connections. Will be called when the plugin is no longer required.

expand_url(url)

(abstract) Expand an URL. This allows a source to collect multiple samples from a single url. The URL will have a wildcard or point to something with info and multiple urls will be returned.

Parameters `url (str)` – url to expand

Returns the resulting url(s), a tuple if multiple, otherwise a str

Return type str or tuple of str

fetch_url(inurl, outfile)

(abstract) Fetch a file from an external data source.

Parameters

- `inurl` – url to the item in the data store
- `outpath` – path where to store the fetch data locally

fetch_value(inurl)

(abstract) Fetch a value from an external data source.

Parameters `inurl` – the url of the value to retrieve

Returns the fetched value

static isurl(string)

Test if given string is an url.

Parameters `string (str)` – string to test

Returns True if the string is an url, False otherwise

Return type bool

path_to_url(path, mountpoint=None)

(abstract) Construct an url from a given mount point and a relative path to the mount point.

Parameters

- `path (str)` – the path to determine the url for
- `mountpoint (str or None)` – the mount point to use, will be automatically detected if None is given

Returns url matching the path

Return type str

static print_result(result)

Print the result of the IOPlugin to stdout to be picked up by the tool

Parameters `result` – value to print as a result

Returns None

pull_source_data(inurl, outdir, sample_id, datatype=None)

Transfer the source data from inurl to be available in outdir.

Parameters

- `inurl (str)` – the input url to fetch data from
- `outdir (str)` – the directory to write the data to

- **datatype** (`DataType`) – the datatype of the data, used for determining the total contents of the transfer

Returns None

push_sink_data (*inpath*, *outurl*, *datatype*=*None*)

(abstract) Write out the sink data from the *inpath* to the *outurl*.

Parameters

- **inpath** (`str`) – the path of the data to be pushed
- **outurl** (`str`) – the url to write the data to
- **datatype** (`DataType`) – the datatype of the data, used for determining the total contents of the transfer

Returns None

put_url (*inpath*, *outurl*)

(abstract) Put the files to the external data store.

Parameters

- **inpath** – path to the local data
- **outurl** – url to where to store the data in the external data store.

put_value (*value*, *outurl*)

(abstract) Put the files to the external data store.

Parameters

- **value** – the value to store
- **outurl** – url to where to store the data in the external data store.

abstract property scheme

(abstract) This abstract property is to be overwritten by a subclass to indicate the url scheme associated with the IOPlugin.

setup (**args*, ***kwargs*)

(abstract) Setup before data transfer. This can be any function that needs to be used to prepare the plugin for data transfer.

url_to_path (*url*)

(abstract) Get the path to a file from a url.

Parameters **url** (`str`) – the url to retrieve the path for

Returns the corresponding path

Return type `str`

provenance Module

class `fastr.core.provenance.Provenance` (*host*=*None*)

Bases: `object`

The Provenance object keeps track of everything that happens to a data object.

__dict__ = `mappingproxy({ '__module__': 'fastr.core.provenance', '__doc__': '\n The P...`

__init__ (*host*=*None*)

Initialize self. See help(type(self)) for accurate signature.

```
__module__ = 'fastr.core.provenance'

__weakref__
    list of weak references to the object (if defined)

activity(identifier, start_time=None, end_time=None, other_attributes=None)
agent(identifier, other_attributes=None)

collect_input_argument_provenance(input_argument)

collect_provenance(job, advanced_flow=False)
    Collect the provenance for this job

static data_uri(value, job)

entity(identifier, other_attributes=None)

static get_parent_provenance(value)
    Find the provenance of the parent job
```

Parameters `value` (`str`) – url for the value for which to find the job

Returns the provenance of the job that created the value

Raises

- `FastrKeyError` – if the deferred is not available (yet)
- `FastrValueError` – if the value is not a valid deferred url

```
init_provenance(job)
    Create initial provenance document

serialize(filename, format)
```

resourcelimit Module

Module for the management of resource limits of compute resources

```
class fastr.core.resourcelimit.ResourceLimit(cores=1, memory='2G', time=None)
    Bases: object
```

```
__eq__(other)
    Check if two resource limits are equal
```

Parameters `other` – resource limit to test against

Return type `bool`

```
__getstate__()
    Return type dict
```

```
__hash__ = None
```

```
__init__(cores=1, memory='2G', time=None)
    An object describing resource requirements/limits for a node
```

Parameters

- `cores` (`Optional[int]`) – number of cores

- **memory** (`Union[str, int, None]`) – memory specification, can be int with number of megabytes or a string with numbers ending on M, G, T, P for megabytes, gigabytes, terrabytes or petabytes. Note that the number has to be an integer, e.g. 1500M would work, whereas 1.5G would be invalid
- **time** (`Union[str, int, None]`) – run time specification, this can be an int with the number of seconds or a string in the HH:MM:SS, MM:SS, or SS format. Where HH, MM, and SS are integers representing the number of hours, minutes and seconds.

```
__module__ = 'fastr.core.resourcelimit'

__ne__(other)
    Check if two resource limits are not equal

    Parameters other – resource limit to test against

    Return type bool

__setstate__(state)

__slots__ = ('_cores', '_memory', '_time')

copy()
    Return a copy of current resource limit object

    Return type ResourceLimit

property cores
    The required number of gpus

    Return type int

property memory
    The required memory in megabytes

    Return type int

property time
    The required time in seconds

    Return type int
```

samples Module

This package holds the classes for working with samples.

```
class fastr.core.samples.ContainsSamples
    Bases: fastr.core.samples.HasSamples

    __abstractmethods__ = frozenset({'samples'})

    __getitem__(item)

    __module__ = 'fastr.core.samples'

    __setitem__(key, value)

property dimensions
    The dimensions has to be implemented by any subclass. It has to provide a tuple of Dimensions.

    Returns dimensions

    Return type tuple

abstract property samples
```

class fastr.core.samples.**HasSamples**
 Bases: *fastr.core.dimension.HasDimensions*

Base class for all classes that supply samples. This base class allows to only define `__getitem__` and `size` and get all other basic functions mixed in so that the object behaves similar to a Mapping.

```
__abstractmethods__ = frozenset({'__getitem__', 'dimensions'})  
  
__contains__(item)  
  
abstract __getitem__(item)  
  
__iter__()  
  
__module__ = 'fastr.core.samples'  
  
ids()  
  
indexes()  
  
items()  
  
iteritems()
```

class fastr.core.samples.**SampleBaseId**

Bases: *tuple*

This class represents a sample id. A sample id is a multi-dimensional id that has a simple, consistent string representation.

```
__add__(other)  
    Add another SampleId, this allows to add parts to the SampleId in a convenient way.  
  
__dict__ = mappingproxy({'__module__': 'fastr.core.samples', '__doc__': '\n This cla  
__module__ = 'fastr.core.samples'  
  
static __new__(cls, *args)  
    Create a new SampleId
```

Parameters args (iterator/iterable of element type or element type)
 – the strings to make sample id for

```
__radd__(other)  
    Add another SampleId, this allows to add parts to the SampleId in a convenient way. This is the right-hand  
version of the operator.
```

```
__repr__()  
    Get a string representation for the SampleBaseId
```

Returns the string representation

Return type *str*

```
__str__()  
    Get a string version for the SampleId, joins the SampleId with __ to create a single string version.
```

Returns the string version

Return type *str*

class fastr.core.samples.**SampleCollection** (*dimnames, parent*)

Bases: *collections.abc.MutableMapping, fastr.core.dimension.HasDimensions*

The SampleCollections is a class that contains the data including a form of ordering. Each sample is reachable both by its SampleId and a SampleIndex. The object is sparse, so not all SampleId have to be defined allowing for non-rectangular data shapes.

Note: This object is meant to replace both the SampleIdList and the ValueStorage.

`__abstractmethods__ = frozenset({})`

`__contains__(item)`

Check if an item is in the SampleCollection. The item can be a SampleId or SampleIndex. If the item is a slicing SampleIndex, then check if it would return any data (True) or no data (False)

Parameters `item` (`SampleId`, `SampleIndex`) – the item to check for

Returns flag indicating item is in the collections

Return type `bool`

`__delitem__(key)`

Remove an item from the SampleCollection

Parameters `key` (`SampleId`, `SampleIndex`, *tuple of both, or SampleItem*) – the key of the item to remove

`__dict__ = mappingproxy({ '__module__': 'fastr.core.samples', '__doc__': '\n The Samp`

`__getitem__(item)`

Retrieve (a) SampleItem(s) from the SampleCollection using the SampleId or SampleIndex. If the item is a tuple, it should be valid tuple for constructing either a SampleId or SampleIndex.

Parameters `item` (`SampleId`, `SampleIndex`, *or tuple*) – the identifier of the item to retrieve

Returns the requested item

Return type `SampleItem`

Raises

- `FastrTypeError` – if the item parameter is of incorrect type
- `KeyError` – if the item is not found

`__init__(dimnames, parent)`

Create a new SampleCollection

`__iter__()`

Iterate over the indices

`__len__()`

Get the number of samples in the SampleCollections.

`__module__ = 'fastr.core.samples'`

`__repr__()`

Return repr(self).

`__setitem__(key, value)`

Set an item to the SampleCollection. The key can be a SampleId, SampleIndex or a tuple containing a SampleId and SampleIndex. The value can be a SampleItem (with the SampleId and SampleIndex matching), a tuple with values (assuming no depending jobs), or a with a list of values and a set of depending jobs.

Parameters

- `key` (`SampleId`, `SampleIndex`, *tuple of both, or SampleItem*) – the key of the item to store

- **value** (`SampleItem`, tuple of values, or tuple of tuple of values and set of depending jobs) – the value of the `SampleItem` to store

Raises

- `FastrTypeError` – if the key or value types are incorrect
- `FastrValueError` – if the id or values are incorrectly formed

__weakref__

list of weak references to the object (if defined)

property dimensions

The dimensions has to be implemented by any subclass. It has to provide a tuple of Dimensions.

Returns dimensions

Return type tuple

property fullid

The full defining ID for the `SampleIdList`

property ndims

The number of dimensions in this `SampleCollection`

property parent

The parent object holding the `SampleCollection`

class fastr.core.samples.SampleId

Bases: `fastr.core.samples.SampleBaseId`

`SampleId` is an identifier for data using human readable strings

__module__ = 'fastr.core.samples'

class fastr.core.samples.SampleIndex

Bases: `fastr.core.samples.SampleBaseId`

`SampleId` is an identifier for data using the location in the N-d data structure.

__module__ = 'fastr.core.samples'

__repr__()

Get a string representation for the `SampleIndex`

Returns the string representation

Return type str

__str__()

Get a string version for the `SampleId`, joins the `SampleId` with **__** to create a single string version.

Returns the string version

Return type str

expand(size)

Function expanding a slice `SampleIndex` into a list of non-slice `SampleIndex` objects

Parameters size – the size of the collection to slice

property isslice

Flag indicating that the `SampleIndex` is a slice (as opposed to a simple single index).

class fastr.core.samples.SampleItem

Bases: `fastr.core.samples.SampleItemBase`

```
__module__ = 'fastr.core.samples'  
static __new__(cls, index, id_, data, jobs=None, failed_annotations=None)  
    Create a SampleItem. Data should be an OrderedDict of tuples.
```

Parameters

- **index** (*tuple, slice*) – the sample index
- **id** (*SampleId*) – the sample id
- **data** (*SampleValue, Mapping*) – the data values
- **jobs** (*set*) – set of jobs on which this SampleItems data depends.
- **failed_annotations** (*set*) – set of tuples. The tuple is contructed like follows: (job_id, reason).

```
class fastr.core.samples.SampleItemBase  
Bases: tuple
```

This class represents a sample item, a combination of a SampleIndex, SampleID, value and required jobs. The SampleItem based on a named tuple and has some extra methods to combine SampleItems easily.

__add__ (other)

The addition operator combines two SampleItems into a single SampleItems. It merges the data and jobs and takes the index and id of the left-hand item.

Parameters **other** (*SampleItem*) – The other item to add to this one

Returns the combined SampleItem

Return type *SampleItem*

```
__dict__ = mappingproxy({ '__module__': 'fastr.core.samples', '__doc__': '\n This clas  
__getnewargs__()  
    Get new args gives the arguments to use to re-create this object, This is used for serialization.  
__module__ = 'fastr.core.samples'  
static __new__(cls, index, id_, data, jobs=None, failed_annotations=None)  
    Create a SampleItem. Data should be an OrderedDict of tuples.
```

Parameters

- **index** (*tuple, slice*) – the sample index
- **id** (*SampleId*) – the sample id
- **data** (*SampleValue, Mapping*) – the data values
- **jobs** (*set*) – set, tuple or list of jobs on which this SampleItems data depends.
- **failed_annotations** (*set*) – set of tuples. The tuple is contructed like follows: (job_id, reason).

__repr__ ()

Get a string representation for the SampleItem

Returns the string representation

Return type *str*

property cardinality

The cardinality of this Sample

static combine(*args)

Combine a number of SampleItems into a new one.

Parameters `args` (*iterable of SampleItems*) – the SampleItems to combine

Returns the combined SampleItem

Return type `SampleItem`

It is possible to both give multiple arguments, where each argument is a SampleItem, or a single argument which is an iterable yielding SampleItems.

```
# variables a, b, c, d are SampleItems to combine
# These are all valid ways of combining the SampleItems
comb1 = SampleItem.combine(a, b, c, d) # Using multiple arguments
l = [a, b, c, d]
comb2 = SampleItem.combine(l) # Using a list of arguments
comb3 = SampleItem.combine(l.__iter__()) # Using an iterator
```

property data

The data SampleValue of the SampleItem

Returns The value of this SampleItem

Return type `SampleValue`

property dimensionality

The dimensionality of this Sample

property failed_annotations**property id**

The sample id of the SampleItem

Returns The id of this SampleItem

Return type `SampleId`

property index

The index of the SampleItem

Returns The index of this SampleItem

Return type `SampleIndex`

property jobs

The set of the jobs on which this SampleItem depends

Returns The jobs that generated the data for this SampleItem

Return type `set`

class fastr.core.samples.SamplePayload

Bases: `fastr.core.samples.SampleItemBase`

__add__(other)

The addition operator combines two SampleItems into a single SampleItems. It merges the data and jobs and takes the index and id of the left-hand item.

Parameters `other` (`SampleItem`) – The other item to add to this one

Returns the combined SamplePayload

Return type `SamplePayload`

__module__ = 'fastr.core.samples'

```
static __new__(cls, index, id_, data, jobs=None, failed_annotations=None)
Create a SampleItem. Data should be an OrderedDict of tuples.
```

Parameters

- **index** (*tuple, slice*) – the sample index
- **id** (*SampleId*) – the sample id
- **data** (*SampleValue, Mapping*) – the data values
- **jobs** (*set*) – set of jobs on which this SampleItems data depends.
- **failed_annotations** (*set*) – set of tuples. The tuple is contructed like follows: (job_id, reason).

```
class fastr.core.samples.SampleValue(*args, **kwargs)
```

Bases: *collections.abc.MutableMapping*

A collection containing the content of a sample

```
__abstractmethods__ = frozenset({})
```

```
__add__(other)
```

```
__delitem__(key)
```

```
__dict__ = mappingproxy({'__module__': 'fastr.core.samples', '__doc__': '\n A collecti...'})
```

```
__getitem__(item)
```

```
__getstate__()
```

```
__init__(*args, **kwargs)
```

Initialize self. See help(type(self)) for accurate signature.

```
__iter__()
```

```
__len__()
```

```
__module__ = 'fastr.core.samples'
```

```
__radd__(other)
```

```
__repr__()
```

Return repr(self).

```
__setitem__(key, value)
```

```
__setstate__(state)
```

```
__weakref__
```

list of weak references to the object (if defined)

```
cast(datatype)
```

```
property is_mapping
```

```
property is_sequence
```

```
iterelements()
```

```
mapping_part()
```

```
sequence_part()
```

target Module

The module containing the classes describing the targets.

```
class fastr.core.target.ProcessUsageCollection
```

Bases: `collections.abc.Sequence`

```
_abstractmethods_ = frozenset({})
```

```
_dict_ = mappingproxy({'_module_': 'fastr.core.target', 'usage_type': <class 'fa
```

```
_getitem_(item)
```

```
_init_()
```

Initialize self. See help(type(self)) for accurate signature.

```
_len_()
```

```
_module_ = 'fastr.core.target'
```

```
_weakref_
```

list of weak references to the object (if defined)

```
aggregate(number_of_points)
```

```
append(value)
```

```
usage_type
```

alias of `SystemUsageInfo`

```
class fastr.core.target.SubprocessBasedTarget
```

Bases: `fastr.core.target.Target`

Abstract based class for targets which call the target via a subprocess. Supplies a `call_subprocess` which executes the command and profiles the resulting subprocess.

```
_abstractmethods_ = frozenset({'run_command'})
```

```
_module_ = 'fastr.core.target'
```

```
call_subprocess(command)
```

Call a subprocess with logging/timing/profiling

Parameters `command`(*list*) – the command to execute

Returns execution info

Return type `dict`

```
monitor_process(process, resources)
```

Monitor a process and profile the cpu, memory and io use. Register the resource use every `_MONITOR_INTERVAL` seconds.

Parameters

- `process` (`subprocess.Popen`) – process to monitor

- `resources` (`ProcessUsageCollection`) – list to append measurements to

```
class fastr.core.target.SystemUsageInfo(timestamp, cpu_percent, vmem, rmem, read_bytes, write_bytes)
```

Bases: `tuple`

```
_getnewargs_()
```

Return self as a plain tuple. Used by copy and pickle.

```
_module_ = 'fastr.core.target'
```

```
static __new__(_cls, timestamp, cpu_percent, vmem, rmem, read_bytes, write_bytes)
    Create new instance of SystemUsageInfo(timestamp, cpu_percent, vmem, rmem, read_bytes, write_bytes)

__repr__()
    Return a nicely formatted representation string

__slots__ = ()

property cpu_percent
    Alias for field number 1

property read_bytes
    Alias for field number 4

property rmem
    Alias for field number 3

property timestamp
    Alias for field number 0

property vmem
    Alias for field number 2

property write_bytes
    Alias for field number 5
```

class fastr.core.target.Target

Bases: `fastr.abc.baseplugin.Plugin`

The abstract base class for all targets. Execution with a target should follow the following pattern:

```
>>> with Target() as target:
...     target.run_command(['sleep', '10'])
```

The Target context operator will set the correct paths/initialization. Within the context command can be ran and when leaving the context the target reverts the state before.

```
__abstractmethods__ = frozenset({'run_command'})

__enter__()
    Set the environment in such a way that the target will be on the path.

__exit__(exc_type, exc_value, traceback)
    Cleanup the environment where needed

__module__ = 'fastr.core.target'

abstract run_command(command)
    Run a command with the target
```

Return type `TargetResult`

classmethod test()

Test the plugin, interfaces do not need to be tested on import

```
class fastr.core.target.TargetResult(return_code, stdout, stderr, command, resource_usage,
                                         time_elapsed)
```

Bases: `object`

```
__dict__ = mappingproxy({ '__module__': 'fastr.core.target', '__init__': <function Ta
__init__(return_code, stdout, stderr, command, resource_usage, time_elapsed)
    Class to formalize the resulting data of a Target
```

Parameters

- **return_code** (`int`) – the return code of the process
- **stdout** (`Union[str, bytes]`) – the stdout generated by the process
- **stderr** (`Union[str, bytes]`) – the stderr generated by the process
- **command** (`List[Union[str, bytes]]`) – the command executed
- **resource_usage** (`List[SystemUsageInfo]`) – the resource use during execution
- **time_elapsed** (`int`) – time used (in seconds)

__module__ = `'fastr.core.target'`

__weakref__
list of weak references to the object (if defined)

as_dict()
A dictionary of the data in the object (meant for serialization)

Return type `Dict[str, Union[int, str, List[~T]]]`

tool Module

A module to maintain a tool.

Exported classes:

- Tool – A class encapsulating a tool.
- ParameterDescription – The base class containing the shared description of a parameter (both input and output).
- InputParameterDescription – A class containing the description of an input parameter.
- Output ParameterDescription – A class containing the description of an output parameter.

class `fastr.core.tool.Tool(doc=None)`
Bases: `fastr.abc.serializable.Serializable`

The class encapsulating a tool.

```
DEFAULT_TARGET_CLASS = { 'MacroNode' : 'MacroTarget' }
TOOL_REFERENCE_FILE_NAME = '__fastr_tool_ref__.json'
TOOL_RESULT_FILE_NAME = '__fastr_tool_result.pickle.gz'
__dataschemafile__ = 'Tool.schema.json'
```

__eq__(other)

Compare two Tool instances with each other.

Parameters `other` (`Tool`) – the other instances to compare to

Returns True if equal, False otherwise

__getstate__()

Retrieve the state of the Tool

Returns the state of the object

Rtype dict

__hash__ = None

__init__(doc=None)

Create a new Tool :param doc: path of toolfile or a dict containing the tool data :type doc: str or dict

```
__module__ = 'fastr.core.tool'

__repr__()  
    Get a string representation for the Tool. This will show the inputs and output defined in a table-like structure.  
  
        Returns the string representation  
  
        Return type str

__setstate__(state)  
    Set the state of the Tool by the given state.  
  
        Parameters state (dict) – The state to populate the object with

__str__()  
    Get a string version for the Tool  
  
        Returns the string version  
  
        Return type str

authors = None  
List of authors of the tool. These people wrapped the executable but are not responsible for executable itself.

cite = None  
This holds the citation you should use when publishing something based on this Tool

command = None  
Command is a dictionary contain information about the command which is called by this Tool: command['interpreter'] holds the (possible) interpreter to use command['targets'] holds a per os/arch dictionary of files that should be executed command['url'] is the webpage of the command to be called command['version'] is the version of the command used command['description'] can help a description of the command command['authors'] lists the original authors of the command

property command_version  
  
static compare_output_data(current_output_data, reference_output_data, validation_result,  
                           output)  
  
create_reference(input_data, output_directory, mount_name='__ref_tmp__', copy_input=True)

description = None  
Description of the tool and it's functionality

execute(payload=None, **kwargs)  
Execute a Tool given the payload for a single run  
  
        Parameters payload – the data to execute the Tool with  
  
        Returns The result of the execution  
  
        Return type InterFaceResult

property fullid  
The full id of this tool

property hash

help = None  
Man page for the Tool. Here usage and examples can be described in detail

property id

property inputs
```

name = None
 Name of the tool, this should be a descriptive, human readable name.

namespace = None
 The namespace this tools lives in, this will be set by the ToolManager on load

node_class = None
 Class for of the Node to use

property ns_id
 The namespace and id of the Tool

property outputs

property path
 The path of the directory in which the tool definition file was located.

references = None
 A list of documents and in depth reading about the methods used in this tool

requirements = None
 Requirements for this Tool

Warning: Not yet implemented

tags = None
 List of tags for this tool

property target
 The OS and arch matched target definition.

test (reference=None)
 Run the tests for this tool

test_spec
 alias of TestSpecification

classmethod test_tool (reference_data_dir, tool=None, input_data=None)
 Execute the tool with the input data specified and test the results against the reference data. This effectively tests the tool execution.

Parameters

- **reference_data_dir** (*str*) – The path or vfs url of reference data to compare with
- **source_data** (*dict*) – The source data to use

url = None
 URL to website where this tool can be downloaded from

version = None
 Version of the tool, not of the underlying software

version Module

Module containing the class that represent versions

class fastr.core.version.Version
 Bases: *tuple*

Class representing a software version definition. Allows for sorting and extraction of parts.

```
__dict__ = mappingproxy({'__module__': 'fastr.core.version', '__doc__': '\n Class re...  
__module__ = 'fastr.core.version'  
static __new__(cls, *version)  
    Class containing a version  
  
    Can be constructed by:
```

```
Version( 'major.$minor.$extra[0].$extra[1]$seperator$status$build$suffix' )  
Version( major, minor, extra, status, build, suffix, seperator )  
Version( (major, minor, extra, status, build, suffix, seperator) )  
Version( [major, minor, extra, status, build, suffix, seperator] )
```

Parameters

- **major** (*int*) – interger giving major version
- **minor** (*int*) – is an integer (required)
- **extra** (*list of int*) – is a list of integers
- **status** (*str*) – can be “a”, “alpha”, “b”, “beta”, “rc”, or “r”
- **build** (*int*) – is an integer
- **suffix** (*str*) – can contain any combination of alpha-numeric character and “._-“
- **seperator** (*str*) – is any of “.”, “-“, or “_”, which is located between \$extra and \$build

Note: The method based on strings is the recommended method. For strings the major and minor version are required, where for tuple and list constructors all seven elements are optional.

Examples:

```
>>> a = Version('0.1')  
>>> print(tuple(a))  
(0, 1, None, None, None, '', None)  
>>> b = Version('2.5.3-rc2')  
>>> print(tuple(b))  
(2, 5, [3], 'rc', 2, '', '-')  
>>> c = Version('1.2.3.4.5.6.7-beta8_with_suffix')  
>>> print(tuple(c))  
(1, 2, [3, 4, 5, 6, 7], 'beta', 8, '_with_suffix', '-')
```

```
__repr__()  
    Return a in-editor representation of the version  
__str__()  
    Return a string representation of the version  
property build  
    the build number, this is following the status (e.g. for 3.2-beta4, this would be 4)  
date_version_matcher = re.compile('(\d+)-(\d+)-(\d+)(_|-|\.)?(\.* )')  
property extra  
    extra version extension as a list  
property extra_string  
    extra version extension as a string
```

```

property major
    major version

property minor
    minor version

property status
    the status of the version (a, alpha, b, beta, rc or r)

property suffix
    the remainder of the version which was not formatted in a known way

version_matcher = re.compile('(\d+)\.\d+((?:\.\d+)+)?(_|-\.?)?(a(?\=\d)|b(?\=

```

vfs Module

This module contains the virtual file system code. This is internally used object as used as base class for the IOPlugin.

```

class fastr.core.vfs.VirtualFileSystem
Bases: object

```

The virtual file system class. This is an IOPlugin, but also heavily used internally in fastr for working with directories. The VirtualFileSystem uses the `vfs://` url scheme.

A typical virtual filesystem url is formatted as `vfs://mountpoint/relative/dir/from/mount.ext`

Where the `mountpoint` is defined in the [Config file](#). A list of the currently known mountpoints can be found in the `fastr.config` object

```

>>> fastr.config.mounts
{'example_data': '/home/username/fastr-feature-documentation/fastr/fastr/examples/
˓→data',
 'home': '/home/username/',
 'tmp': '/home/username/FastrTemp'}

```

This shows that a url with the mount `home` such as `vfs://home/tempdir/testfile.txt` would be translated into `/home/username/tempdir/testfile.txt`.

There are a few default mount points defined by Fastr (that can be changed via the config file).

mountpoint	default location
home	the users home directory (<code>expanduser('~/')</code>)
tmp	the fastr temporary dir, defaults to <code>tempfile.gettempdir()</code>
example_data	the fastr example data directory, defaults \$FASTRDIR/example/data

```

__dict__ = mappingproxy({ '__module__': 'fastr.core.vfs', '__doc__': "\n The virtual "
__init__()
    Instantiate the VFS plugin

    Returns the VirtualFileSysten plugin

    __module__ = 'fastr.core.vfs'
    __weakref__
        list of weak references to the object (if defined)
    abstract = False

```

static copy_file_dir (inpath, outpath)

Helper function, copies a file or directory not caring what the inpath actually is

Parameters

- **inpath** – path of the things to be copied
- **outpath** – path of the destination

Returns the result of shutil.copy2 or shutil.copytree (depending on inpath pointing to a file or directory)

expand_url (url)

Try to expand the url. For vfs with will return the original url.

Parameters **url** – url to expand

Returns the expanded url (same as url)

fetch_url (inurl, outpath)

Fetch the files from the vfs.

Parameters

- **inurl** – url to the item in the data store, starts with vfs://
- **outpath** – path where to store the fetch data locally

fetch_value (inurl)

Fetch a value from an external vfs file.

Parameters **inurl** – url of the value to read

Returns the fetched value

path_to_url (path, mountpoint=None, scheme=None)

Construct an url from a given mount point and a relative path to the mount point.

Parameters **path** (*str*) – the path to find the url for

Mountpoint *str* mountpoint the url should be under

Returns url of the

put_url (inpath, outurl)

Put the files to the external data store.

Parameters

- **inpath** – path of the local data
- **outurl** – url to where to store the data, starts with vfs://

put_value (value, outurl)

Put the value in the external data store.

Parameters

- **value** – value to store
- **outurl** – url to where to store the data, starts with vfs://

property scheme**setup ()**

The plugin setup, does nothing but needs to be implemented

url_to_path(url, scheme=None)

Get the path to a file from a vfs url

Parameters `url (str)` – url to get the path for

Returns the matching path

Return type `str`

Raises

- `FastrMountUnknownError` – if the mount in url is unknown
- `FastrUnknownURLSchemeError` – if the url scheme is not correct

Example (the mountpoint tmp points to /tmp):

```
>>> fastr.vfs.url_to_path('vfs://tmp/file.ext')
'/tmp/file.ext'
```

Subpackages

test Package

test Package

test_datatypemanager Module

test_dimension Module

test_samples Module

test_tool Module

test_version Module

test_vfs Module

data Package

data Package

Package containing data related modules

url Module

Module providing tools to parse and create valid urls and paths.

usage example:

When in fastr.config under the mounts section the data mount is set to /media/data, you will get the following. ..
code-block:: python

```
>>> from fastr.data.url import get_path_from_url
>>> get_path_from_url('vfs://data/temp/blaat1.png')
'/media/data/temp/blaat1.png'
```

`fastr.data.url.basename(url)`

Get basename of url

Parameters `url` (`str`) – the url

Returns the basename of the path in the url

`fastr.data.url.create vfs_url(mountpoint, path)`

Construct an url from a given mount point and a relative path to the mount point.

Parameters

- `mountpoint` (`str`) – the name of the mountpoint
- `path` (`str`) – relative path from the mountpoint

Returns the created vfs url

`fastr.data.url.dirname(url)`

Get the dirname of the url

Parameters `url` (`str`) – the url

Returns the dirname of the path in the url

`fastr.data.url.dirurl(url)`

Get the a new url only having the dirname as the path

Parameters `url` (`str`) – the url

Returns the modified url with only dirname as path

`fastr.data.url.full_split(urlpath)`

Split the path in the url in a list of parts

Parameters `urlpath` – the url path

Returns a list of parts

`fastr.data.url.get_path_from_url(url)`

Get the path to a file from a url. Currently supports the `file://` and `vfs://` scheme's

Examples:

```
>>> url.get_path_from_url('vfs://neurodata/user/project/file.ext')
'Y:\neuro3\user\project\file.ext'

>>> 'file:///d:/data/project/file.ext'
'd:\data\project\file.ext'
```

Warning: `file://` will not function cross platform and is mainly for testing

`fastr.data.url.get_url_scheme(url)`

Get the schem of the url

Parameters `url` (`str`) – url to extract scheme from

Returns the url scheme

Return type str

fastr.data.url.**isurl**(string)

Check if string is a valid url

Parameters string(*str*) – potential url

Returns flag indicating if string is a valid url

fastr.data.url.**join**(url, *p)

Join the path in the url with p

Parameters

- **url** (*str*) – the base url to join with
- **p** – additional parts of the path

Returns the url with the parts added to the path

fastr.data.url.**normurl**(url)

Normalized the path of the url

Parameters url(*str*) – the url

Returns the normalized url

fastr.data.url.**register_url_scheme**(scheme)

Register a custom scheme to behave http like. This is needed to parse all things properly.

fastr.data.url.**split**(url)

Split a url in a url with the dirname and the basename part of the path of the url

Parameters url(*str*) – the url

Returns a tuple with (dirname_url, basename)

datatypes Package

datatypes Package

The datatypes module holds all DataTypes generated by fastr and all the base classes for these datatypes.

class fastr.datatypes.**AnyFile**(value=None)

Bases: *fastr.datatypes.TypeGroup*

Special Datatype in fastr that is a TypeGroup with all known DataTypes as its members.

```
_abstractmethods_ = frozenset({})
```

```
_module_ = 'fastr.datatypes'
```

```
description = 'TypeGroup AnyFile\nAnyFile (AnyFile) is a group of consisting of all UR'
```

class fastr.datatypes.**AnyType**(value=None)

Bases: *fastr.datatypes.TypeGroup*

Special Datatype in fastr that is a TypeGroup with all known DataTypes as its members.

```
_abstractmethods_ = frozenset({})
```

```
_module_ = 'fastr.datatypes'
```

```
description = 'TypeGroup AnyType\nAnyType (AnyType) is a group of consisting of all Da'
```

```
class fastr.datatypes.BaseDataType(value=None, format_=None)
Bases: fastr.abc.baseplugin.BasePlugin
```

The base class for all datatypes in the fastr type system.

```
__abstractmethods__ = frozenset({'__init__'})
```

```
__eq__(other)
```

Test the equality of two DataType objects

Parameters `other` (`(DataType)`) – the object to compare against

Returns flag indicating equality

Return type `bool`

```
__getstate__()
```

```
__hash__ = None
```

```
abstract __init__(value=None, format_=None)
```

The BaseDataType constructor.

Parameters

- `value` – value to assign to the new BaseDataType object
- `format` – the format used for the ValueType

Returns new BaseDataType object

Raises `FastrNotImplementedError` – if `id`, `name`, `version` or `description` is None

```
__module__ = 'fastr.datatypes'
```

```
__ne__(other)
```

Test if two objects are not equal. This is by default done by negating the `__eq__` operator

Parameters `other` (`(DataType)`) – the object to compare against

Returns flag indicating equality

Return type `bool`

```
__reduce_ex__(*args, **kwargs)
```

helper for pickle

```
__repr__()
```

Returns string representation of the BaseDataType

Returns string representation

Return type `str`

```
__setstate__(state)
```

```
__str__()
```

Returns the string version of the BaseDataType

Returns string version

Return type `str`

```
checksum()
```

Generate a checksum for the value of this DataType

Returns the checksum of the value

Return type `str`

```

description = ''
    Description of the DataType

dot_extension = None

extension = None
    Extension related to the Type

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/fastr/types/BaseDataType.py'
fullid = 'fastr://types/BaseDataType'
id = 'BaseDataType'

classmethod isinstance(value)
    Indicate whether value is an instance for this DataType.

        Returns the flag indicating the value is of this DataType

        Return type bool

name = 'BaseDataType'

parent = (DataTypeManager AnalyzeImageFile : <URLType: AnalyzeImageFile> AnyFile : Any)

property parsed_value
    The parsed value of object instantiation of this DataType.

property raw_value
    The raw value of object instantiation of this DataType. For datatypes that override value (like Deferred) this is the way to access the _value field.

classmethod test()
    Define the test for the BasePluginManager. Make sure we are not one of the base classes

property valid
    A boolean flag that indicates weather or not the value assigned to this DataType is valid. This property is generally overwritten by implementation of specific DataTypes.

property value
    The value of object instantiation of this DataType.

version = <Version: 1.0>
    Version of the DataType definition

class fastr.datatypes.DataType(value=None, format=None)
    Bases: fastr.datatypes.BaseDataType

    This class is the base class for all DataTypes that can hold a value.

    __abstractmethods__ = frozenset({ '__init__' })

    abstract __init__(value=None, format=None)
        The DataType constructor.

            Parameters
                • value – value to assign to the new DataType object
                • format – the format used for the ValueType

            Returns new DataType object

    __module__ = 'fastr.datatypes'

```

action (name)

This function can be overwritten by subclasses to implement certain action that should be performed. For example, the *Directory* Data-Type has an action *ensure*. This method makes sure the Directory exists. A Tool can indicate an action that should be called for an Output which will be called before execution.

Parameters `name (str)` – name of the action to execute

Returns None

class fastr.datatypes.DataTypeManager

Bases: `fastr.abc.basepluginmanager.BasePluginManager`

The `DataTypeManager` hold a mapping of all DataTypes in the fast system and can create new DataTypes from files/data structures.

__abstractmethods__ = frozenset({})**__init__()**

The `DataTypeManager` constructor will create a new `DataTypeManager` and populate it with all DataTypes it can find in the paths set in `config.types_path`.

Returns the created `DataTypeManager`

__keytransform__(key)

Key transformation for this mapping. The key transformation allows indexing by both the Data-Type name as well as the Data-Type it self.

Parameters `key (fastr.datatypes.BaseDataType or str)` – The name of the requested datatype or the datatype itself

Returns The requested datatype

__module__ = 'fastr.datatypes'**create_enumtype (type_id, options, name=None)**

Create a python class based on an XML file. This function return a completely functional python class based on the contents of a Data-Type XML file.

Such a class will be of type `EnumType`.

Parameters

- `type_id (str)` – the id of the new class
- `options (iterable)` – an iterable of options, each option should be str

Returns the newly created subclass of `EnumType`

Raises `FastrTypeError` – if the options is not an iterable of str

property fullid

The fullid of the datatype manager

get_type (name)

Read a type given a typename. This will scan all directories in `types_path` and attempt to load the newest version of the Data-Type.

Parameters `name (str)` – Name of the datatype that should be imported in the system

Returns the datatype with the requested name, or None if datatype is not found

Note: If type is already in TypeManager it will not load anything and return the already loaded version.

guess_type (*value*, *exists=True*, *options=None*, *preferred=None*)

Guess the DataType based on a value str.

Parameters

- **value** (*str*) – the value to guess the type for
- **options** (*TypeGroup*, *DataType* or tuple of *DataTypes*) – The options that are allowed to be guessed from
- **exists** (*bool*) – Indicate the value exists (if file) and can be checked for validity, if false skip validity check
- **preferred** (*iterable*) – An iterable of preferred types in case multiple types match.

Returns The resulting DataType or None if no match was found

Raises *FastrTypeError* – if the options argument is of the wrong type

The function will first create a list of all candidate DataTypes. Subsequently, it will check for each candidate if the value would valid. If there are multiple matches, the config value for preferred types is consulted to break the ties. If non of the DataTypes are in the preferred types list, a somewhat random DataType will be picked as the most optimal result.

has_type (*name*)

Check if the datatype with requested name exists

Parameters **name** (*str*) – the name of the requested datatype

Returns flag indicating if the datatype exists

Return type *bool*

static isdatatype (*item*)

Check if item is a valid datatype for the fastr system.

Parameters **item** – item to check

Returns flag indicating if the item is a fastr datatype

Return type *bool*

match_types (**args*, ***kwargs*)

Find the match between a list of DataTypes/TypeGroups, see *Resolving Datatypes* for details

Parameters

- **args** – A list of DataType/TypeGroup objects to match
- **kwargs** – A ‘preferred’ keyword argument can be used to indicate a list of DataTypes to prefer in case of ties (first has precedence over later in list)

Returns The best DataType match, or None if no match is possible.

Raises *FastrTypeError* – if not all args are subclasses of BaseDataType

match_types_any (**args*)

Find the match between a list of DataTypes/TypeGroups, see *Resolving Datatypes* for details

Parameters **args** – A list of DataType/TypeGroup objects to match

Returns A set with all DataTypes that match.

Return type *set*

Raises *FastrTypeError* – if not all args are subclasses of BaseDataType

property plugin_class

The PluginClass of the items of the BasePluginManager

poll_datatype (filename)

Poll an xml file to see if there is a definition of a datatype in it.

Parameters `filename (str)` – path of the file to poll

Returns tuple with (id, version, basetype) if a datatype is found or (None, None, None) if no datatype is found

populate()

Populate Manager. After scanning for DataTypes, create the AnyType and set the preferred types

property preferred_types**class fastr.datatypes.Deferred (value=None, format_=None)**

Bases: `fastr.datatypes.DataType`

__abstractmethods__ = frozenset({})**__getstate__()****__init__ (value=None, format_=None)**

The Deferred constructor.

Parameters

- **value** – value to assign to the new DataType object
- **format** – This is ignore but here for compatibility

Returns new Deferred object

__module__ = 'fastr.datatypes'**__repr__()**

Returns string representation of the BaseDataType

Returns string represenation

Return type `str`

__setstate__ (state)**checksum()**

Generate a checksum for the value of this DataType

Returns the checksum of the value

Return type `str`

property job**classmethod lookup (value)**

Look up the deferred target and return that object

Param value

Returns The value the deferred points to

Return type `DataType`

Raises

- **FastrKeyError** – if the deferred is not available (yet)
- **FastrValueError** – if the value is not a valid deferred url

property parsed_value

The value of object instantiation of this DataType.

property provenance**property target**

Target object for this deferred.

Raises

- *FastrKeyError* – if the deferred is not available (yet)
- *FastrValueError* – if the value is not a valid deferred url

property value

The value of object instantiation of this DataType.

```
class fastr.datatypes.EnumType (value=None, format_=None)
Bases: fastr.datatypes.DataType
```

The EnumType is the base for DataTypes that can have a value which is an option from a predefined set of possibilities (similar to an enum type in many programming languages).

```
__abstractmethods__ = frozenset({})
```

```
__init__ (value=None, format_=None)
```

The EnumType constructor.

Parameters

- **value** – value to assign to the new EnumType object
- **format** – the format used for the ValueType

Returns new EnumType object

Raises *FastrDataTypeNotInstantiableError* – if not subclassed

```
__module__ = 'fastr.datatypes'
```

```
__reduce_ex__ (*args, **kwargs)
```

helper for pickle

```
description = 'EnumType (EnumType) is a enumerate type with options:\n\nEnumType can
options = frozenset({})
```

```
version = <Version: 1.0>
```

Enums always have version 1.0

```
class fastr.datatypes.TypeGroup (value=None)
Bases: fastr.datatypes.BaseDataType
```

The TypeGroup is a special DataType that does not hold a value of its own but is used to group a number of DataTypes. For example ITK has a list of supported file formats that all tools build on ITK support. A group can be used to conveniently specify this in multiple Tools that use the same set DataTypes.

```
__abstractmethods__ = frozenset({'_members'})
```

```
__init__ (value=None)
```

Dummy constructor. TypeGroups are not instantiable and cannot hold a value of its own.

Raises *FastrDataTypeNotInstantiableError* – if called

```
__module__ = 'fastr.datatypes'
```

```
static __new__(cls, value=None, format_=None)
```

Instantiate a TypeGroup. This will match the value to the best matching type and instantiate that. Note that the returned object will not be of type TypeGroup but one of the TypeGroup members.

```
classmethod isinstance(value)
```

Indicate whether value is an instance for this DataType.

Returns the flag indicating the value is of this DataType

Return type bool

members

A descriptor that can act like a property for a class.

preference

A descriptor that can act like a property for a class.

```
class fastr.datatypes.URLType(value=None, format_=None)
```

Bases: [fastr.datatypes.DataType](#)

The URLType is the base for DataTypes that point to a resource somewhere else (typically a filesystem). The true value is actually the resource referenced by the value in this object.

```
__abstractmethods__ = frozenset({})
```

```
__eq__(other)
```

Test the equality of two DataType objects

Parameters other (URLType) – the object to compare against

Returns flag indicating equality

Return type bool

```
__hash__ = None
```

```
__init__(value=None, format_=None)
```

The URLType constructor

Parameters

- **value** – value to assign to the new URLType
- **format** – the format used for the ValueType

Returns new URLType object

```
__module__ = 'fastr.datatypes'
```

```
checksum()
```

Return the checksum of this URL type

Returns checksum string

Return type str

```
classmethod content(inval, outval=None)
```

Give the contents of a URLType, this is generally useful for filetypes that consists of multiple files (e.g. AnalyzeImageFile, DICOM). The value will indicate the main file, and the contents function can determine all files that form a single data value.

Parameters

- **inval** – a value to figure out contents for this type
- **outval** – the place where the copy should point to

Returns a list of all files part of the value (e.g. header and data file)

Return type list

property parsed_value

The parsed value of object instantiation of this DataType.

property valid

A boolean flag that indicates weather or not the value assigned to this DataType is valid. This property is generally overwritten by implementation of specific DataTypes.

class fastr.datatypes.ValueType (*value=None, format_=None*)

Bases: *fastr.datatypes.DataType*

The ValueType is the base for DataTypes that hold simple values (not an EnumType and not a file/URL). The values is generally represented by a string.

__abstractmethods__ = frozenset({})

__init__ (*value=None, format_=None*)

The ValueType constructor

Parameters

- **value** – value to assign to the new ValueType
- **format** – the format used for the ValueType

Returns new ValueType object

__module__ = 'fastr.datatypes'

fastr.datatypes.fastr_isinstance (*obj, datatype*)

Check if an object is of a specific datatype.

Parameters

- **obj** – Object to inspect
- **datatype** (*tuple, BaseDataType*) – The datatype(s) to check

Returns flag indicating object is of datatype

Return type bool

execution Package

execution Package

This package contains all modules related directly to the execution

basenoderun Module

class fastr.execution.basenoderun.BaseNodeRun

Bases: fastr.abc.updateable.Updateable, fastr.abc.serializable.Serializable

NODE_RUN_MAP = {'AdvancedFlowNode': <class 'fastr.execution.flownoderun.AdvancedFlowN

NODE_RUN_TYPES = {'AdvancedFlowNodeRun': <class 'fastr.execution.flownoderun.AdvancedF

__abstractmethods__ = frozenset({'_update'})

```
classmethod __init_subclass__(**kwargs)
    Register nodes in class for easy location
    __module__ = 'fastr.execution.basenoderun'
```

environmentmodules Module

This module contains a class to interact with EnvironmentModules

```
class fastr.execution.environmentmodules.EnvironmentModules (protected=None)
    Bases: object
```

This class can control the module environments in python. It can list, load and unload environmentmodules. These modules are then used if subprocess is called from python.

```
__dict__ = mappingproxy({ '__module__' : 'fastr.execution.environmentmodules', '__doc__':
    __init__(protected=None)
        Create the environmentmodules control object

    Parameters protected (list) – list of modules that should never be unloaded

    Returns newly created EnvironmentModules

    __module__ = 'fastr.execution.environmentmodules'

    __repr__()
        Return repr(self).

    __weakref__
        list of weak references to the object (if defined)

    avail (namestart=None)
        Print available modules in same way as commandline version

        Parameters namestart – filter on modules that start with namestart

    property avail_modules
        List of available modules

    clear()
        Unload all modules (except the protected modules as they cannot be unloaded). This should result in a clean environment.

    isloaded(module)
        Check if a specific module is loaded

        Parameters module – module to check

        Returns flag indicating the module is loaded

    load(module)
        Load specified module

        Parameters module – module to load

    property loaded_modules
        List of currently loaded modules

    reload(module)
        Reload specified module

        Parameters module – module to reload
```

swap(*module1, module2*)

Swap one module for another one

Parameters

- **module1** – module to unload
- **module2** – module to load

sync()

Sync the object with the underlying environment. Re-checks the available and loaded modules

static tostring_modvalue(*value*)

Turn a representation of a module into a string representation

Parameters **value** – module representation (either str or tuple)

Returns string representation

static totuple_modvalue(*value*)

Turn a representation of a module into a tuple representation

Parameters **value** – module representation (either str or tuple)

Returns tuple representation (name, version, default)

unload(*module*)

Unload specified module

Parameters **module** – module to unload

class fastr.execution.environmentmodules.**ModuleSystem**

Bases: enum.Enum

An enumeration.

```
__module__ = 'fastr.execution.environmentmodules'
```

```
envmod = 'enviromentmodules'
```

```
lmod = 'Lmod'
```

executionscript Module

The executionscript is the script that wraps around a tool executable. It takes a job, builds the command, executes the command (while profiling it) and collects the results.

fastr.execution.executionscript.execute_job(*job*)

Execute a Job and save the result to disk

Parameters **job** – the job to execute

fastr.execution.executionscript.main(*joblist=None*)

This is the main code. Wrapped inside a function to avoid the variables being seen as globals and to shut up pylint. Also if the joblist argument is given it can run any given job, otherwise it takes the first command line argument.

flownoderun Module**class** fastr.execution.flownoderun.**FlowNodeRun**(*node, parent*)

Bases: *fastr.execution.noderun.NodeRun*

A Flow NodeRun is a special subclass of Nodes in which the amount of samples can vary per Output. This allows non-default data flows.

```
__abstractmethods__ = frozenset({})  
_module_ = 'fastr.execution.flownoderun'
```

property blocking

A FlowNodeRun is (for the moment) always considered blocking.

Returns True

property dimnames

Names of the dimensions in the NodeRun output. These will be reflected in the SampleIdList of this NodeRun.

property outputsize

Size of the outputs in this NodeRun

set_result (job, failed_annotation)

Incorporate result of a job into the FlowNodeRun.

Parameters **job** (*Type*) – job of which the result to store

```
class fastr.execution.flownoderun.AdvancedFlowNodeRun (node, parent)  
Bases: fastr.execution.flownoderun.FlowNodeRun
```

```
__abstractmethods__ = frozenset({})
```

```
_module_ = 'fastr.execution.flownoderun'
```

execute()

Execute the node and create the jobs that need to run

Returns list of jobs to run

Return type list of *Jobs*

set_result (job, failed_annotation)

Incorporate result of a job into the FlowNodeRun.

Parameters **job** (*Type*) – job of which the result to store

inputoutputrun Module

Classes for arranging the input and output for nodes.

Exported classes:

Input – An input for a node (holding datatype). Output – The output of a node (holding datatype and value). ConstantOutput – The output of a node (holding datatype and value).

Warning: Don't mess with the Link, Input and Output internals from other places. There will be a huge chances of breaking the network functionality!

```
class fastr.execution.inputoutputrun.AdvancedFlowOutputRun (node_run, template)  
Bases: fastr.execution.inputoutputrun.OutputRun  
__abstractmethods__ = frozenset({})  
_module_ = 'fastr.execution.inputoutputrun'
```

```
class fastr.execution.inputoutputrun.BaseInputRun (node_run, template)
Bases: fastr.core.samples.HasSamples, fastr.planning.inputoutput.BaseInput
Base class for all inputs runs.

__abstractmethods__ = frozenset({'__getitem__', '_update', 'dimensions', 'fullid', 'it
__init__(node_run, template)
Instantiate a BaseInput

Parameters

- node – the parent node the input/output belongs to.
- description – the ParameterDescription describing the input/output.

Returns the created BaseInput

Raises

- FastrTypeError – if description is not of class ParameterDescription
- FastrDataTypeNotAvailableError – if the DataType requested cannot be found in the fastr.types


__module__ = 'fastr.execution.inputoutputrun'

abstract itersubinputs()
Iterator over the SubInputs

Returns iterator

example:
>>> for subinput in input_a.itersubinputs():
    print subinput
```

```
class fastr.execution.inputoutputrun.InputRun (node_run, template)
Bases: fastr.execution.inputoutputrun.BaseInputRun

Class representing an input of a node. Such an input will be connected to the output of another node or the output of an constant node to provide the input value.

__abstractmethods__ = frozenset({})

__getitem__(key)
Retrieve an item from this Input.

Parameters key (str, SampleId or tuple) – the key of the requested item, can be a key str, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int the corresponding SubInput will be returned. If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned.

Return type SampleItem or SubInput

Raises

- FastrTypeError – if key is not of a valid type
- FastrKeyError – if the key is not found


__getstate__()
Retrieve the state of the Input

Returns the state of the object
```

Rtype dict

__init__(node_run, template)
Instantiate an input.

Parameters `template` – the Input that the InputRun is based on

__module__ = 'fastr.execution.inputoutputrun'

__setstate__(state)
Set the state of the Input by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

__str__()
Get a string version for the Input

Returns the string version

Return type str

cardinality(key=None, job_data=None)
Cardinality for an Input is the sum the cardinalities of the SubInputs, unless defined otherwise.

Parameters `key` (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type int, sympy.Symbol, or None

property datatype
The datatype of this Input

property dimensions
The size of the sample collections that can accessed via this Input.

property fullid
The full defining ID for the Input

get_sourced_nodes()
Get a list of all `Nodes` connected as sources to this Input

Returns list of all connected `Nodes`

Return type list

get_sourced_outputs()
Get a list of all `Outputs` connected as sources to this Input

Returns tuple of all connected `Outputs`

Return type tuple

index(value)
Find index of a SubInput

Parameters `value` (`SubInput`) – the `SubInput` to find the index of

Returns key

Return type int, str

property input_group
The id of the InputGroup this Input belongs to.

insert(*index*)

Insert a new SubInput at index in the sources list

Parameters **key** (*int*) – positive integer for position in `_source` list to insert to

Returns newly inserted `SubInput`

Return type `SubInput`

itersubinputs()

Iterate over the `SubInputs` in this Input.

Returns iterator yielding `SubInput`

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

remove(*value*)

Remove a SubInput from the SubInputs list.

Parameters **value** (`SubInput`) – the `SubInput` to removed from this Input

property source

The mapping of `SubInputs` that are connected and have more than 0 elements.

class `fastr.execution.inputoutputrun.MacroOutputRun`(*node_run, template*)

Bases: `fastr.execution.inputoutputrun.OutputRun`

__abstractmethods__ = frozenset({})**__module__ = 'fastr.execution.inputoutputrun'****property dimensions**

The dimensions has to be implemented by any subclass. It has to provide a tuple of Dimensions.

Returns dimensions

Return type `tuple`

class `fastr.execution.inputoutputrun.NamedSubinputRun`(*parent*)

Bases: `fastr.execution.inputoutputrun.InputRun`

A named subinput for cases where the value of an input is mapping.

__abstractmethods__ = frozenset({})**__getitem__(key)**

Retrieve an item (a SubInput) from this NamedSubInput.

Parameters **key** (*int*) – the key of the requested item

Return type `Union[SubInputRun, SampleItem]`

Returns The `SubInput` corresponding with the key will be returned.

Raises

- `FastrTypeError` – if key is not of a valid type

- `FastrKeyError` – if the key is not found

__init__(parent)

Instantiate an input.

Parameters **template** – the Input that the InputRun is based on

```
__module__ = 'fastr.execution.inputoutputrun'
__str__()
    Get a string version for the NamedSubInput

    Returns the string version

    Return type str

property fullid
    The full defining ID for the NamedSubInputRun

property item_index

class fastr.execution.inputoutputrun.OutputRun(node_run, template)
    Bases:           fastr.planning.inputoutput.BaseOutput,      fastr.core.samples.
    ContainsSamples

    Class representing an output of a node. It holds the output values of the tool ran. Output fields can be connected to inputs of other nodes.

    __abstractmethods__ = frozenset({})

    __getitem__(key)
        Retrieve an item from this Output. The returned value depends on what type of key used:
        • Retrieving data using index tuple: [index_tuple]
        • Retrieving data sample_id str: [SampleId]
        • Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]
        • Retrieving a SubOutput using an int or slice: [n] or [n:m]

        Parameters key (int, slice, SampleId or tuple) – the key of the requested item, can be a number, slice, sample index tuple or a SampleId

        Returns the return value depends on the requested key. If the key was an int or slice the corresponding SubOutput will be returned (and created if needed). If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned. If the key was a list of SampleId a tuple of SampleItem will be returned.

        Return type SubInput or SampleItem or list of SampleItem

        Raises
            • FastrTypeError – if key is not of a valid type
            • FastrKeyError – if the parent Node has not been executed

    __getstate__()
        Retrieve the state of the Output

        Returns the state of the object

        Rtype dict

    __init__(node_run, template)
        Instantiate an Output

        Parameters
            • node – the parent node the output belongs to.
            • description – the ParameterDescription describing the output.
```

Returns created Output

Raises

- *FastrTypeError* – if description is not of class ParameterDescription
- *FastrDataTypeNotFoundError* – if the DataType requested cannot be found in the fastr.types

`__module__ = 'fastr.execution.inputoutputrun'`

`__setitem__(key, value)`

Store an item in the Output

Parameters

- **key** (tuple of int or SampleId) – key of the value to store
- **value** – the value to store

Returns None

Raises *FastrTypeError* – if key is not of correct type

`__setattr__(state)`

Set the state of the Output by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

`__str__()`

Get a string version for the Output

Returns the string version

Return type *str*

property automatic

Flag indicating that the Output is generated automatically without being specified on the command line

cardinality (*key=None, job_data=None*)

Cardinality of this Output, may depend on the inputs of the parent Node.

Parameters **key** (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type *int*, sympy.Symbol, or *None*

Raises

- *FastrCardinalityError* – if cardinality references an invalid *Input*
- *FastrTypeError* – if the referenced cardinality values type cannot be cast to int
- *FastrValueError* – if the referenced cardinality value cannot be cast to int

property datatype

The datatype of this Output

property fullid

The full defining ID for the Output

iterconvergingindices (*collapse_dims*)

Iterate over all data, but collapse certain dimension to create lists of data.

Parameters `collapse_dims` (*iterable of int*) – dimension to collapse

Returns iterator SampleIndex (possibly containing slices)

property listeners

The list of [Links](#) connected to this Output.

property preferred_types

The list of preferred DataTypes for this Output.

property resulting_datatype

The DataType that will the results of this Output will have.

property samples

The SampleCollection of the samples in this Output. None if the NodeRun has not yet been executed. Otherwise a SampleCollection.

property valid

Check if the output is valid, i.e. has a valid cardinality

class `fastr.execution.inputoutputrun.SourceOutputRun` (*node_run, template*)

Bases: [fastr.execution.inputoutputrun.OutputRun](#)

Output for a SourceNodeRun, this type of Output determines the cardinality in a different way than a normal NodeRun.

`__abstractmethods__ = frozenset({})`

`__getitem__(item)`

Retrieve an item from this Output. The returned value depends on what type of key used:

- Retrieving data using index tuple: [index_tuple]
- Retrieving data sample_id str: [SampleId]
- Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]
- Retrieving a [SubOutput](#) using an int or slice: [n] or [n:m]

Parameters `key` (int, slice, SampleId or tuple) – the key of the requested item, can be a number, slice, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int or slice the corresponding [SubOutput](#) will be returned (and created if needed). If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned. If the key was a list of SampleId a tuple of SampleItem will be returned.

Return type [SubInput](#) or SampleItem or list of SampleItem

Raises

- [FastrTypeError](#) – if key is not of a valid type
- [FastrKeyError](#) – if the parent NodeRun has not been executed

`__init__(node_run, template)`

Instantiate a FlowOutput

Parameters

- `node` – the parent node the output belongs to.
- `description` – the ParameterDescription describing the output.

Returns created FlowOutput

Raises

- **FastrTypeError** – if description is not of class ParameterDescription
- **FastrDataTypeNotFoundError** – if the DataType requested cannot be found in the fastr.types

__module__ = 'fastr.execution.inputoutputrun'

__setitem__ (key, value)

Store an item in the Output

Parameters

- **key** (tuple of int or SampleId) – key of the value to store
- **value** – the value to store

Returns None

Raises **FastrTypeError** – if key is not of correct type

cardinality (key=None, job_data=None)

Cardinality of this SourceOutput, may depend on the inputs of the parent NodeRun.

Parameters **key** (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type int, sympy.Symbol, or None

property dimensions

The dimensions of this SourceOutputRun

property linearized

A linearized version of the sample data, this is lazily cached linearized version of the underlying SampleCollection.

property ndims

The number of dimensions in this SourceOutput

property size

The sample size of the SourceOutput

class fastr.execution.inputoutputrun.**SubInputRun** (*input_*)

Bases: *fastr.execution.inputoutputrun.BaseInputRun*

This class is used by *Input* to allow for multiple links to an *Input*. The SubInput class can hold only a single Link to a (Sub)Output, but behaves very similar to an *Input* otherwise.

__abstractmethods__ = frozenset({})

__getitem__ (key)

Retrieve an item from this SubInput.

Parameters **key** (int, SampleId or SampleIndex) – the key of the requested item, can be a number, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int the corresponding *SubInput* will be returned. If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned.

Return type SampleItem or *SubInput*

Raises **FastrTypeError** – if key is not of a valid type

Note: As a SubInput has only one SubInput, only requesting int key 0 or -1 is allowed, and it will return self

`__getstate__()`

Retrieve the state of the SubInput

Returns the state of the object

Rtype dict

`__init__(input_)`

Instantiate an SubInput.

Parameters `input` (*Input*) – the parent of this SubInput.

Returns the created SubInput

`__module__ = 'fastr.execution.inputoutputrun'`**`__setstate__(state)`**

Set the state of the SubInput by the given state.

Parameters `state` (*dict*) – The state to populate the object with

Returns None

`__str__()`

Get a string version for the SubInput

Returns the string version

Return type str

`cardinality(key=None, job_data=None)`

Get the cardinality for this SubInput. The cardinality for a SubInputs is defined by the incoming link.

Parameters `key` (SampleIndex or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type int, sympy.Symbol, or None

`property description`

The description object of this input/output

`property dimensions`

The sample size of the SubInput

`property fullid`

The full defining ID for the SubInput

`get_sourced_nodes()`

Get a list of all *Nodes* connected as sources to this SubInput

Returns list of all connected *Nodes*

Return type list

`get_sourced_outputs()`

Get a list of all *Outputs* connected as sources to this SubInput

Returns list of all connected *Outputs*

Return type list

property input_group

The id of the InputGroup this SubInputs parent belongs to.

property item_index**iteritems()**

Iterate over the SampleItems that are in the SubInput.

Returns iterator yielding SampleItem objects

itersubinputs()

Iterate over SubInputs (for a SubInput it will yield self and stop iterating after that)

Returns iterator yielding *SubInput*

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

property node

The Node to which this SubInputs parent belongs

property source

A list with the source *Link*. The list is to be compatible with *Input*

property source_output

The *Output* linked to this SubInput

class fastr.execution.inputoutputrun.SubOutputRun (output, index)

Bases: *fastr.execution.inputoutputrun.OutputRun*

The SubOutput is an Output that represents a slice of another Output.

__abstractmethods__ = frozenset({})**__getitem__(key)**

Retrieve an item from this SubOutput. The returned value depends on what type of key used:

- Retrieving data using index tuple: [index_tuple]
- Retrieving data sample_id str: [SampleId]
- Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]
- Retrieving a *SubOutput* using an int or slice: [n] or [n:m]

Parameters **key** (int, slice, SampleId or tuple) – the key of the requested item, can be a number, slice, sample index tuple or a SampleId

Returns the return value depends on the requested key. If the key was an int or slice the corresponding *SubOutput* will be returned (and created if needed). If the key was a SampleId or sample index tuple, the corresponding SampleItem will be returned. If the key was a list of SampleId a tuple of SampleItem will be returned.

Return type *SubInput* or SampleItem or list of SampleItem

Raises *FastrTypeError* – if key is not of a valid type

__getstate__()

Retrieve the state of the SubOutput

Returns the state of the object

Rtype dict

`__init__(output, index)`

Instantiate a SubOutput

Parameters

- **output** – the parent output the suboutput slices.
- **index** (`int` or `slice`) – the way to slice the parent output

Returns created SubOutput**Raises**

- **FastrTypeError** – if the output argument is not an instance of `Output`
- **FastrTypeError** – if the index argument is not an `int` or `slice`

`__len__()`

Return the length of the Output.

Note: In a SubOutput this is always 1.

`__module__ = 'fastr.execution.inputoutputrun'`**`__setitem__(key, value)`**

A function blocking the assignment operator. Values cannot be assigned to a SubOutput.

Raises `FastrNotImplementedError` – if called**`__setattr__(state)`**

Set the state of the SubOutput by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None**`__str__()`**

Get a string version for the SubOutput

Returns the string version**Return type** `str`**`cardinality(key=None, job_data=None)`**

Cardinality of this SubOutput depends on the parent Output and `self.index`

Parameters `key` (tuple of `int` or `SampleId`) – key for a specific sample, can be sample index or id

Returns the cardinality**Return type** `int`, `sympy.Symbol`, or `None`**Raises**

- **FastrCardinalityError** – if cardinality references an invalid `Input`
- **FastrTypeError** – if the referenced cardinality values type cannot be cast to int
- **FastrValueError** – if the referenced cardinality value cannot be cast to int

`property datatype`

The datatype of this SubOutput

`property fullid`

The full defining ID for the SubOutput

property indexrep

Simple representation of the index.

property listeners

The list of [Links](#) connected to this Output.

property node

The NodeRun to which this SubOutput belongs

property preferred_types

The list of preferred DataTypes for this SubOutput.

property resulting_datatype

The DataType that will the results of this SubOutput will have.

property samples

The SampleCollection for this SubOutput

job Module

This module contains the Job class and some related classes.

```
class fastr.execution.job.InlineJob (*args, **kwargs)
    Bases: fastr.execution.job.Job
```

Job that does not actually need to run but is used for consistency in data processing and logging.

```
__init__ (*args, **kwargs)
    Create a job
```

Parameters

- **node** ([fastr.planning.node.Node](#)) – the node the job is based on
- **sample_id** – the id of the sample
- **sample_index** – the index of the sample
- **input_arguments** – the argument list
- **output_arguments** – the argument list
- **hold_jobs** – the jobs on which this jobs depend
- **preferred_types** – The list of preferred types to use

Returns

```
__module__ = 'fastr.execution.job'
```

```
collect_provenance()
```

Collect the provenance for this job

```
get_result()
```

Get the result of the job if it is available. Load the output file if found and check if the job matches the current object. If so, load and return the result.

Returns Job after execution or None if not available

Return type Job | None

```
class fastr.execution.job.Job (node, sample_id, sample_index, input_arguments, output_arguments, hold_jobs=None, preferred_types=None)
```

Bases: [fastr.abc.serializable.Serializable](#)

Class describing a job.

Arguments: tool_name - the name of the tool (str) tool_version - the version of the tool (Version) argument - the arguments used when calling the tool (list) tmpdir - temporary directory to use to store output data hold_jobs - list of jobs that need to finished before this job can run (list)

```
COMMAND_DUMP = '__fastr_command__.pickle.gz'
```

```
INFO_DUMP = '__fastr_extra_job_info__.json'
```

```
PROV_DUMP = '__fastr_prov__.json'
```

```
RESULT_DUMP = '__fastr_result__.pickle.gz'
```

```
STDERR_DUMP = '__fastr_stderr__.txt'
```

```
STDOUT_DUMP = '__fastr_stdout__.txt'
```

```
__getstate__()
```

Get the state of the job

Returns job state

Return type dict

```
__init__(node, sample_id, sample_index, input_arguments, output_arguments, hold_jobs=None, preferred_types=None)
```

Create a job

Parameters

- **node** (`fastr.planning.node.Node`) – the node the job is based on
- **sample_id** (`SampleId`) – the id of the sample
- **sample_index** (`SampleIndex`) – the index of the sample
- **input_arguments** (`Dict[str, SampleIndex]`) – the argument list
- **output_arguments** (`Dict[str, Dict[~KT, ~VT]]`) – the argument list
- **hold_jobs** (`Optional[List[str]]`) – the jobs on which this jobs depend
- **preferred_types** (`Optional[List[~T]]`) – The list of preferred types to use

Returns

```
__module__ = 'fastr.execution.job'
```

```
__repr__()
```

String representation of the Job

```
__setstate__(state)
```

Set the state of the job

Parameters `state` (dict) –

```
static cast_to_type(value, datatypes)
```

Try to cast value to one of the given datatypes. Will try all the datatypes in order.

Parameters `datatypes` (`tuple`) – Possible datatypes to cast to

Return type `DataType`

Returns casted value

```
clean()
```

collect_provenance()
Collect the provenance for this job.

property commandfile
The path of the command pickle

property commandurl
The url of the command pickle

create_payload()
Create the payload for this object based on all the input/output arguments

Returns the payload

Return type dict

ensure_tmp_dir()

execute()
Execute this job

Returns The result of the execution

Return type InterFaceResult

property extrainfofile
The path where the extra job info document is saved

property extrainfouri
The url where the extra job info document is saved

classmethod fill_output_argument(output_spec, cardinality, desired_type, requested, tm-purl)
This is an abstract class method. The method should take the argument_dict generated from calling self.get_argument_dict() and turn it into a list of commandline arguments that represent this Input/Output.

Parameters

- **cardinality** (int) – the cardinality for this output (can be non for automatic outputs)
- **desired_type** (DataType) – the desired datatype for this output
- **requested** (bool) – flag to indicate that the output is requested by Fastr

Returns the values for this output

Return type list

property fullid
The full id of the job

get_deferred(output_id, cardinality_nr, sample_id=None)
Get a deferred pointing to a specific output value in the Job

Parameters

- **output_id** (str) – the output to select from
- **cardinality_nr** (int) – the index of the cardinality
- **sample_id** (str) – the sample id to select (optional)

Returns The deferred

get_output_datatype(output_id)
Get the datatype for a specific output

Parameters **output_id** (str) – the id of the output to get the datatype for

Returns the requested datatype

Return type tuple

get_result()

Get the result of the job if it is available. Load the output file if found and check if the job matches the current object. If so, load and return the result.

Returns Job after execution or None if not available

Return type Job | None

classmethod get_value(value)

Get a value

Parameters

- **value** – the url of the value
- **datatype** – datatype of the value

Returns the retrieved value

hash_inputs()

Create hashes for all input values and store them in the info store

hash_results()

Create hashes of all output values and store them in the info store

property id

The id of this job

property logfile

The path of the result pickle

property logurl

The url of the result pickle

property provfile

The path where the prov document is saved

property provurl

The url where the prov document is saved

property resources

The compute resources required for this job

property status

The status of the job

property stderrfile

The path where the stderr text is saved

property stderrurl

The url where the stderr text is saved

property stdoutfile

The path where the stdout text is saved

property stdouturl

The url where the stdout text is saved

property tmpurl

The URL of the tmpdir to use

property tool

```
classmethod translate_argument(value)
    Translate an argument from a URL to an actual path.
```

Parameters

- **value** – value to translate
- **datatype** – the datatype of the value

Returns the translated value

```
static translate_output_results(value, datatypes, mountpoint=None)
    Translate the results for on Output
```

Parameters

- **value** – the results value for the output
- **datatypes** (*tuple*) – tuple of possible datatypes for the output
- **preferred_type** – the preferred datatype of the output

Returns the update value for the result

```
translate_results(result)
```

Translate the results of an interface (using paths etc) to the proper form using URI's instead.

Parameters **result** (*dict*) – the result data of an interface**Returns** the translated result**Return type** *dict*

```
validate_results(payload)
```

Validate the results of the Job

Returns flag indicating the results are complete and valid

```
write()
```

```
class fastr.execution.job.JobCleanupLevel
```

Bases: [enum](#), [Enum](#)


The cleanup level for Jobs that are finished.

```
__module__ = 'fastr.execution.job'
all = 'all'
no_cleanup = 'no_cleanup'
non_failed = 'non_failed'
```

```
class fastr.execution.job.JobState(_, stage, error)
```

Bases: [enum](#), [Enum](#)

The possible states a Job can be in. An overview of the states and the advised transitions are depicted in the following figure:



`__init__(_, stage, error)`

Initialize self. See help(type(self)) for accurate signature.

```
__module__ = 'fastr.execution.job'
cancelled = ('cancelled', 'done', True)
created = ('created', 'idle', False)
property done
execution_done = ('execution_done', 'in_progress', False)
execution_failed = ('execution_failed', 'in_progress', True)
failed = ('failed', 'done', True)
finished = ('finished', 'done', False)
hold = ('hold', 'idle', False)
property idle
property in_progress
nonexistent = ('nonexistent', 'idle', False)
processing_callback = ('processing_callback', 'in_progress', False)
queued = ('queued', 'idle', False)
running = ('running', 'in_progress', False)

class fastr.execution.job.SinkJob(node, sample_id, sample_index, input_arguments, output_arguments, hold_jobs=None, substitutions=None, preferred_types=None)
Bases: fastr.execution.job.Job
```

Special SinkJob for the Sink

```
__init__(node, sample_id, sample_index, input_arguments, output_arguments, hold_jobs=None, substitutions=None, preferred_types=None)
Create a job
```

Parameters

- **node** ([fastr.planning.node.Node](#)) – the node the job is based on
- **sample_id** – the id of the sample
- **sample_index** – the index of the sample
- **input_arguments** – the argument list
- **output_arguments** – the argument list
- **hold_jobs** – the jobs on which this jobs depend
- **preferred_types** – The list of preferred types to use

Returns

```
__module__ = 'fastr.execution.job'
```

```
__repr__()
```

String representation for the SinkJob

```
create_payload()
```

Create the payload for this object based on all the input/output arguments

Returns the payload

Return type `dict`

get_result()

Get the result of the job if it is available. Load the output file if found and check if the job matches the current object. If so, load and return the result.

Returns Job after execution

hash_inputs()

Create hashes for all input values and store them in the info store

property id

The id of this job

substitute (value, datatype=None)

Substitute the special fields that can be used in a SinkJob.

Parameters

- **value** (`str`) – the value to substitute fields in
- **datatype** (`BaseDataType`) – the datatype for the value

Returns string with substitutions performed

Return type `str`

property tmpurl

The URL of the tmpdir to use

validate_results (payload)

Validate the results of the SinkJob

Returns flag indicating the results are complete and valid

class `fastr.execution.job.SourceJob` (`node`, `sample_id`, `sample_index`, `input_arguments`,
`output_arguments`, `hold_jobs=None`, `preferred_types=None`)

Bases: `fastr.execution.job.Job`

Special SourceJob for the Source

__module__ = 'fastr.execution.job'

__repr__()

String representation for the SourceJob

collect_provenance()

Collect the provenance for this job

get_output_datatype (output_id)

Get the datatype for a specific output

Parameters `output_id` (`str`) – the id of the output to get the datatype for

Returns the requested datatype

Return type `BaseDataType`

hash_inputs()

Create hashes for all input values and store them in the info store

validate_results (payload)

Validate the results of the Job

Returns flag indicating the results are complete and valid

linkrun Module

The link module contain the Link class. This class represents the links in a network. These links lead from an output (BaseOutput) to an input (BaseInput) and indicate the desired data flow. Links are smart objects, in the sense that when you set their start or end point, they register themselves with the Input and Output. They do all the book keeping, so as long as you only set the source and target of the Link, the link should be valid.

Warning: Don't mess with the Link, Input and Output internals from other places. There will be a huge chances of breaking the network functionality!

```
class fastr.execution.linkrun.LinkRun (link, parent=None)
Bases: fastr.abc.updateable.Updateable, fastr.abc.serializable.Serializable
Class for linking outputs (BaseOutput) to inputs (BaseInput)
```

Examples:

```
>>> import fastr
>>> network = fastr.Network()
>>> link1 = network.create_link( n1.outputs['out1'], n2.inputs['in2'] )

link2 = Link()
link2.source = n1.outputs['out1']
link2.target = n2.inputs['in2']
```

__abstractmethods__ = frozenset({})

__dataschemafile__ = 'Link.schema.json'

__eq__ (*other*)

Test for equality between two Links

Parameters *other* ([LinkRun](#)) – object to test against

Returns True for equality, False otherwise

Return type bool

__getitem__ (*index*)

Get a an item for this Link. The item will be retrieved from the connected output, but a diverging or converging flow can change the number of samples/cardinality.

Parameters *index* ([SampleIndex](#)) – index of the item to retrieve

Returns the requested item

Return type SampleItem

Raises [FastriIndexError](#) – if the index length does not match the number dimensions in the source data (after collapsing/expanding)

__getstate__ ()

Retrieve the state of the Link

Returns the state of the object

Rtype dict

__hash__ = None

__init__ (*link, parent=None*)

Create a new Link in a Network.

Parameters

- **link** (*Link*) – the base link
- **parent** (*Network* or None) – the parent network, if None is given the *fastr.current_network* is assumed to be the parent

Returns newly created LinkRun

Raises

- **FastrValueError** – if parent is not given and *fastr.current_network* is not set
- **FastrValueError** – if the source output is not in the same network as the Link
- **FastrValueError** – if the target input is not in the same network as the Link

__module__ = 'fastr.execution.linkrun'

__repr__()

Get a string representation for the Link

Returns the string representation

Return type str

__setstate__(state)

Set the state of the Link by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

Raises **FastrValueError** – if the parent network and *fastr.current_network* are not set

cardinality(index=None)

Cardinality for a Link is given by source Output and the collapse/expand settings

Parameters **key** (*SampleIndex*) – key for a specific sample (can be only a sample index!)

Returns the cardinality

Return type int, sympy.Symbol

Raises **FastrIndexError** – if the index length does not match the number of dimension in the data

property collapse

The converging dimensions of this link. Collapsing changes some dimensions of sample lists into cardinality, reshaping the data.

Collapse can be set to a tuple or an int/str, in which case it will be automatically wrapped in a tuple. The int will be seen as indices of the dimensions to collapse. The str will be seen as the name of the dimensions over which to collapse.

Raises **FastrTypeError** – if assigning a collapse value of a wrong type

property collapse_indexes

The converging dimensions of this link as integers. Dimension names are replaced with the corresponding int.

Collapsing changes some dimensions of sample lists into cardinality, reshaping the data

classmethod createobj(state, network=None)

Create object function for Link

Parameters

- **cls** – The class to create
- **state** – The state to use to create the Link
- **network** – the parent Network

Returns newly created Link

destroy()

The destroy function of a link removes all default references to a link. This means the references in the network, input and output connected to this link. If there is no references in other places in the code, it will destroy the link (reference count dropping to zero).

This function is called when a source for an input is set to another value and the links becomes disconnected. This makes sure there is no dangling links.

property dimensions

The dimensions of the data delivered by the link. This can be different from the source dimensions because the link can make data collapse or expand.

property expand

Flag indicating that the link will expand the cardinality into a new sample dimension to be created.

property fullid

The full defining ID for the Input

property parent

The Network to which this Link belongs.

property size

The size of the data delivered by the link. This can be different from the source size because the link can make data collapse or expand.

property source

The source *BaseOutput* of the Link. Setting the source will automatically register the Link with the source BaseOutput. Updating source will also make sure the Link is unregistered with the previous source.

Raises *FastrTypeError* – if assigning a non *BaseOutput*

property status

property target

The target *BaseInput* of the Link. Setting the target will automatically register the Link with the target BaseInput. Updating target will also make sure the Link is unregistered with the previous target.

Raises *FastrTypeError* – if assigning a non *BaseInput*

macronoderun Module

class fastr.execution.macronoderun.MacroNodeRun(node, parent)

Bases: *fastr.execution.noderun.NodeRun*

MacroNodeRun encapsulates an entire network in a single node.

__abstractmethods__ = frozenset({})

__getstate__()

Retrieve the state of the MacroNodeRun

Returns the state of the object

Rtype dict

```
__init__(node, parent)
    Parameters network (fastr.planning.network.Network) – network to create
        macronode for

__module__ = 'fastr.execution.macronoderun'

__setstate__(state)
    Set the state of the NodeRun by the given state.

    Parameters state (dict) – The state to populate the object with

    Returns None

execute()
    Execute the node and create the jobs that need to run

    Returns list of jobs to run

    Return type list of Jobs

get_output_info(output)

property network_run
```

networkanalyzer Module

Module that defines the NetworkAnalyzer and holds the reference implementation.

```
class fastr.execution.networkanalyzer.DefaultNetworkAnalyzer
    Bases: fastr.execution.networkanalyzer.NetworkAnalyzer

    Default implementation of the NetworkAnalyzer.

    __module__ = 'fastr.execution.networkanalyzer'

    analyze_network(network, chunk)
        Analyze a chunk of a Network. Simply process the Nodes in the chunk sequentially.

        Parameters
            • network – Network corresponding with the chunk
            • chunk – The chunk of the network to analyze

class fastr.execution.networkanalyzer.NetworkAnalyzer
    Bases: object

    Base class for NetworkAnalyzers

    __dict__ = mappingproxy({ '__module__': 'fastr.execution.networkanalyzer', '__doc__': '' })
    __module__ = 'fastr.execution.networkanalyzer'
    __weakref__
        list of weak references to the object (if defined)

    abstract analyze_network(network, chunk)
        Analyze a chunk of a Network.

        Parameters
            • network – Network corresponding with the chunk
            • chunk – The chunk of the network to analyze
```

networkchunker Module

This module contains the NetworkChunker class and its default implementation the DefaultNetworkChunker

```
class fastr.execution.networkchunker.DefaultNetworkChunker
Bases: fastr.execution.networkchunker.NetworkChunker
```

The default implementation of the NetworkChunker. It tries to create as large as possible chunks so the execution blocks as little as possible.

```
__init__()
```

Initialize self. See help(type(self)) for accurate signature.

```
__module__ = 'fastr.execution.networkchunker'
```

```
chunck_network(network)
```

Create a list of Network chunks that can be pre-analyzed completely. Each chunk needs to be executed before the next can be analyzed and executed.

The returned chunks are (at the moment) in the format of a tuple (start, nodes) which are both tuples. The tuple contain the nodes where to start execution (should ready if previous chunks are done) and all nodes of the chunk respectively.

Parameters `network` – Network to split into chunks

Returns tuple containing chunks

```
class fastr.execution.networkchunker.NetworkChunker
```

Bases: `object`

The base class for NetworkChunkers. A Network chunker is a class that takes a Network and produces a list of chunks that can each be analyzed and executed in one go.

```
_dict_ = mappingproxy({'__module__': 'fastr.execution.networkchunker', '__doc__':
```

```
'__module__ = 'fastr.execution.networkchunker'
```

```
'__weakref__
```

list of weak references to the object (if defined)

```
abstract chunck_network(network)
```

Create a list of Network chunks that can be pre-analyzed completely. Each chunk needs to be executed before the next can be analyzed and executed.

Parameters `network` – Network to split into chunks

Returns list containing chunks

networkrun Module

Network module containing Network facilitators and analysers.

```
class fastr.execution.networkrun.NetworkRun(network)
```

Bases: `fastr.abc.serializable.Serializable`

The Network class represents a workflow. This includes all Nodes (including ConstantNodes, SourceNodes and Sinks) and Links.

```
NETWORK_DUMP_FILE_NAME = '__fastr_network__.json'
```

```
SINK_DUMP_FILE_NAME = '__sink_data__.json'
```

```
SOURCE_DUMP_FILE_NAME = '__source_data__.pickle.gz'
```

`__bool__()`

A network run is True if it finish running successfully and False otherwise

`__eq__(other)`

Compare two Networks and see if they are equal.

Parameters `other` (*Network*) –

Returns flag indicating that the Networks are the same

Return type `bool`

`__getitem__(item)`

Get an item by its fullid. The fullid can point to a link, node, input, output or even subinput/suboutput.

Parameters `item` (*str, unicode*) – fullid of the item to retrieve

Returns the requested item

`__getstate__()`

Retrieve the state of the Network

Returns the state of the object

Rtype `dict`

`__hash__ = None`**`__init__(network)`**

Create a new, empty Network

Parameters `name` (*str*) – name of the Network

Returns newly created Network

Raises `OSError` – if the tmp mount in the config is not a writable directory

`__module__ = 'fastr.execution.networkrun'`**`__ne__(other)`**

Tests for non-equality, this is the negated version `__eq__`

`__repr__()`

Return repr(self).

`__setstate__(state)`

Set the state of the Network by the given state. This completely overwrites the old state!

Parameters `state` (*dict*) – The state to populate the object with

Returns None

`abort(signal_code=None, current_frame=None)`**`check_id(id_)`**

Check if an id for an object is valid and unused in the Network. The method will always returns True if it does not raise an exception.

Parameters `id` (*str*) – the id to check

Returns True

Raises

- `FastrValueError` – if the id is not correctly formatted

- `FastrValueError` – if the id is already in use

```
property constantlist
execute (sourcedata, sinkdata, execution_plugin=None, tmpdir=None, cluster_queue=None, timstamp=None)
    Execute the Network with the given data. This will analyze the Network, create jobs and send them to the execution backend of the system.

Parameters

- sourcedata (dict) – dictionary containing all data for the sources
- sinkdata (dict) – dictionary containing directives for the sinks
- execution_plugin (str) – the execution plugin to use (None will use the config value)

Raises

- FastrKeyError – if a source has not corresponding key in sourcedata
- FastrKeyError – if a sink has not corresponding key in sinkdata

execution_finished()

property fullid
    The fullid of the Network

generate_jobs()

property global_id
    The global id of the Network, this is different for networks used in macronodes, as they still have parents.

property id
    The id of the Network. This is a read only property.

job_finished (job)
    Call-back handler for when a job is finished. Will collect the results and handle blocking jobs. This function is automatically called when the execution plugin finished a job.

    Parameters job (Job) – the job that finished

property long_id
property network
property nodegroups
    Give an overview of the nodegroups in the network

register_signals()
    Register handles to handle SIGINT and SIGTERM handlers to gracefully shut down the execution :return:

set_data (sourcedata, sinkdata)

property sinklist

property sourcelist

unregister_signals()
    Unregister the signal handlers (set to default). Sending these signals twice will result that the second time the default handler is used.
```

noderun Module

A module to maintain a run of a network node.

```
class fastr.execution.noderun.NodeRun(node, parent)
Bases: fastr.execution.basenoderun.BaseNodeRun
```

The class encapsulating a node in the network. The node is responsible for setting and checking inputs and outputs based on the description provided by a tool instance.

```
__abstractmethods__ = frozenset({})
__dataschemafile__ = 'NodeRun.schema.json'
```

```
__eq__(other)
```

Compare two Node instances with each other. This function ignores the parent and update status, but tests rest of the dict for equality. equality

Parameters `other` (`NodeRun`) – the other instances to compare to

Returns True if equal, False otherwise

```
__getstate__()
```

Retrieve the state of the NodeRun

Returns the state of the object

Rtype dict

```
__hash__ = None
```

```
__init__(node, parent)
```

Instantiate a node.

Parameters

- `node` (`Tool`) – The node to base the noderun on
- `parent` (`Network`) – the parent network of the node

Returns the newly created NodeRun

```
__module__ = 'fastr.execution.noderun'
```

```
__repr__()
```

Get a string representation for the NodeRun

Returns the string representation

Return type str

```
__setstate__(state)
```

Set the state of the NodeRun by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

```
__str__()
```

Get a string version for the NodeRun

Returns the string version

Return type str

property blocking

Indicate that the results of this NodeRun cannot be determined without first executing the NodeRun, causing a blockage in the creation of jobs. A blocking Nodes causes the Chunk borders.

```
create_job(sample_id, sample_index, job_data, job_dependencies, **kwargs)
```

Create a job based on the sample id, job data and job dependencies.

Parameters

- **sample_id** (`SampleId`) – the id of the corresponding sample
- **sample_index** (`SampleIndex`) – the index of the corresponding sample
- **job_data** (`dict`) – dictionary containing all input data for the job
- **job_dependencies** – other jobs that need to finish before this job can run

Returns the created job**Return type** `Job`**classmethod createobj** (`state, network=None`)

Create object function for generic objects

Parameters

- **cls** – The class to create
- **state** – The state to use to create the Link
- **network** – the parent Network

Returns newly created Link**property dimnames**

Names of the dimensions in the NodeRun output. These will be reflected in the SampleIdList of this NodeRun.

execute()

Execute the node and create the jobs that need to run

Returns list of jobs to run**Return type** list of `Jobs`**find_source_index** (`target_index, target, source`)**property fullid**

The full defining ID for the NodeRun inside the network

get_sourced_nodes()

A list of all Nodes connected as sources to this NodeRun

Returns list of all nodes that are connected to an input of this node**property global_id**

The global defining ID for the Node from the main network (goes out of macro nodes to root network)

property id

The id of the NodeRun

property input_groupsA list of input groups for this NodeRun. An input group is `InputGroup` object filled according to the NodeRun**property listeners**

All the listeners requesting output of this node, this means the listeners of all Outputs and SubOutputs

property merge_dimensions**property name**

Name of the Tool the NodeRun was based on. In case a Toolless NodeRun was used the class name is given.

property outputszie

Size of the outputs in this NodeRun

property parent

The parent network of this node.

property resources

Number of cores required for the execution of this NodeRun

set_result (job, failed_annotation)

Incorporate result of a job into the NodeRun.

Parameters

- **job** (*Type*) – job of which the result to store
- **failed_annotation** – A set of annotations, None if no errors else containing a tuple describing the errors

property status**property tool****update_input_groups()**

Update all input groups in this node

sinknoderun Module**class fastr.execution.sinknoderun.SinkNodeRun (node, parent)**

Bases: *fastr.execution.noderun.NodeRun*

Class which handles where the output goes. This can be any kind of file, e.g. image files, textfiles, config files, etc.

__abstractmethods__ = frozenset({})**__dataschemafile__ = 'SinkNodeRun.schema.json'****__getstate__()**

Retrieve the state of the NodeRun

Returns the state of the object

Rtype dict

__init__ (node, parent)

Instantiation of the SinkNodeRun.

Parameters

- **node** (*fastr.planning.node.Node*) – The Node that this Run is based on.
- **parent** (*NetworkRun*) – The NetworkRun that this NodeRun belongs to

Returns newly created sink node run

__module__ = 'fastr.execution.sinknoderun'**__setstate__ (state)**

Set the state of the NodeRun by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

create_job(sample_id, sample_index, job_data, job_dependencies, **kwargs)

Create a job for a sink based on the sample id, job data and job dependencies.

Parameters

- **sample_id** (SampleId) – the id of the corresponding sample
- **job_data** (*dict*) – dictionary containing all input data for the job
- **job_dependencies** – other jobs that need to finish before this job can run

Returns the created job

Return type *Job*

property datatype

The datatype of the data this sink can store.

execute()

Execute the sink node and create the jobs that need to run

Returns list of jobs to run

Return type list of *Jobs*

property input

The default input of the sink NodeRun

set_data(data)

Set the targets of this sink node.

Parameters **data** (*dict* or list of urls) – the targets rules for where to write the data

The target rules can include a few fields that can be filled out:

field	description
sample_id	the sample id of the sample written in string form
cardinality	the cardinality of the sample written
ext	the extension of the datatype of the written data, including the .
extension	the extension of the datatype of the written data, excluding the .
network	the id of the network the sink is part of
node	the id of the node of the sink
timestamp	the iso formatted datetime the network execution started
uuid	the uuid of the network run (generated using <code>uuid.uuid1</code>)

An example of a valid target could be:

```
>>> target = 'vfs://output_mnt/some/path/image_{sample_id}_{cardinality}{ext}'
```

Note: The `{ext}` and `{extension}` are very similar but are both offered. In many cases having a name.`{extension}` will feel like the correct way to do it. However, if you have DataTypes with and without extension that can both be exported by the same sink, this would cause either name.`ext` or name.`extension` to be generated. In this particular case name`{ext}` can help as it will create either name.`ext` or name.`extension`.

Note: If a datatype has multiple extensions (e.g. `.tiff` and `.tif`) the first extension defined in the extension tuple of the datatype will be used.

set_result (*job, failed_annotation*)
Incorporate result of a sink job into the Network.

Parameters

- **job** (*Type*) – job of which the result to store
- **failed_annotation** (*set*) – A set of annotations, None if no errors else containing a tuple describing the errors

sourcenoderun Module

class *fastr.execution.sourcenoderun.SourceNodeRun* (*node, parent*)
Bases: *fastr.execution.flownoderun.FlowNodeRun*

Class providing a connection to data resources. This can be any kind of file, stream, database, etc from which data can be received.

__abstractmethods__ = `frozenset({})`
__dataschemafilename__ = 'SourceNodeRun.schema.json'
__eq__ (*other*)
Compare two Node instances with each other. This function ignores the parent and update status, but tests rest of the dict for equality. equality

Parameters **other** (*NodeRun*) – the other instances to compare to

Returns True if equal, False otherwise

__getstate__()
Retrieve the state of the SourceNodeRun

Returns the state of the object

Rtype dict

__hash__ = `None`
__init__ (*node, parent*)
Instantiation of the SourceNodeRun.

Parameters

- **node** (*fastr.planning.node.Node*) – The Node that this Run is based on.
- **parent** (*NetworkRun*) – The NetworkRun that this NodeRun belongs to

Returns newly created sink node run

__module__ = 'fastr.execution.sourcenoderun'
__setstate__ (*state*)
Set the state of the SourceNodeRun by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

create_job (*sample_id, sample_index, job_data, job_dependencies, **kwargs*)
Create a job based on the sample id, job data and job dependencies.

Parameters

- **sample_id** (*SampleId*) – the id of the corresponding sample

- **sample_index** (`SampleIndex`) – the index of the corresponding sample
- **job_data** (`dict`) – dictionary containing all input data for the job
- **job_dependencies** – other jobs that need to finish before this job can run

Returns the created job

Return type `Job`

property datatype

The datatype of the data this source supplies.

property dimnames

Names of the dimensions in the SourceNodeRun output. These will be reflected in the SampleIdLists.

execute()

Execute the source node and create the jobs that need to run

Returns list of jobs to run

Return type list of `Jobs`

property output

Shorthand for `self.outputs['output']`

property outputsize

The size of output of this SourceNodeRun

set_data(data, ids=None)

Set the data of this source node.

Parameters

- **data** (`dict`, `OrderedDict` or list of urls) – the data to use
- **ids** – if data is a list, a list of accompanying ids

property sourcegroup

property valid

This does nothing. It only overloads the valid method of NodeRun(). The original is intended to check if the inputs are connected to some output. Since this class does not implement inputs, it is skipped.

```
class fastr.execution.sourcenoderun.ConstantNodeRun(node, parent)
Bases: fastr.execution.sourcenoderun.SourceNodeRun
```

Class encapsulating one output for which a value can be set. For example used to set a scalar value to the input of a node.

```
__abstractmethods__ = frozenset({})
__dataschemafile__ = 'ConstantNodeRun.schema.json'
__getstate__()
```

Retrieve the state of the ConstantNodeRun

Returns the state of the object

Rtype dict

__init__(node, parent)

Instantiation of the ConstantNodeRun.

Parameters

- **datatype** – The datatype of the output.

- **data** – the prefilled data to use.
- **id** – The url pattern.

This class should never be instantiated directly (unless you know what you are doing). Instead create a constant using the network class like shown in the usage example below.

usage example:

```
>>> import fastr
>>> network = fastr.Network()
>>> source = network.create_source(datatype=types['ITKImageFile'], id_= 
    ↴'sourceN')
```

or alternatively create a constant node by assigning data to an item in an InputDict:

```
>>> node_a.inputs['in'] = ['some', 'data']
```

which automatically creates and links a ConstantNodeRun to the specified Input

__module__ = 'fastr.execution.sourcenoderun'

__setstate__(state)

Set the state of the ConstantNodeRun by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

property data

The data stored in this constant node

execute()

Execute the constant node and create the jobs that need to run

Returns list of jobs to run

Return type list of *Jobs*

set_data (*data=None, ids=None*)

Set the data of this constant node in the correct way. This is mainly for compatibility with the parent class SourceNodeRun

Parameters

- **data** (*dict or list of urls*) – the data to use
- **ids** – if data is a list, a list of accompanying ids

helpers Package

helpers Package

```
fastr.helpers.config = # [bool] Flag to enable/disable debugging debug = False # [str] Dir
Configuration of the fastr system
```

checksum Module

This module contains a number of functions for checksumming files and objects

`fastr.helpers.checksum.checksum(filepath, algorithm='md5', hasher=None, chunkszie=32768)`

Generate the checksum of a file

Parameters

- **filepath** (`str`, `list`) – path of the file(s) to checksum
- **algorithm** (`str`) – the algorithm to use
- **hasher** (`_hashlib.HASH`) – a hasher to continue updating (rather than creating a new one)

Returns the checksum

Return type `str`

`fastr.helpers.checksum.checksum_directory(directory, algorithm='md5', hasher=None)`

Generate the checksum of an entire directory

Parameters

- **directory** (`str`) – path of the file(s) to checksum
- **algorithm** (`str`) – the algorithm to use
- **hasher** (`_hashlib.HASH`) – a hasher to continue updating (rather than creating a new one)

Returns the checksum

Return type `str`

`fastr.helpers.checksum.hashsum(objects, hasher=None)`

Generate the md5 checksum of (a) python object(s)

Parameters

- **objects** – the objects to hash
- **hasher** – the hasher to use as a base

Returns the hash generated

Return type `str`

`fastr.helpers.checksum.md5_checksum(filepath)`

Generate the md5 checksum of a file

Parameters `filepath` (`str`, `list`) – path of the file(s) to checksum

Returns the checksum

Return type `str`

`fastr.helpers.checksum.sha1_checksum(filepath)`

Generate the sha1 checksum of a file

Parameters `filepath` (`str`, `list`) – path of the file(s) to checksum

Returns the checksum

Return type `str`

classproperty Module

Module containing the code to create class properties.

class `fastr.helpers.classproperty.ClassPropertyDescriptor(fget)`

Bases: `object`

A descriptor that can act like a property for a class.

`__dict__ = mappingproxy({ '__module__': 'fastr.helpers.classproperty', '__doc__': '\n`

`__get__(obj, cls=None)`

`__init__(fget)`

Initialize self. See help(type(self)) for accurate signature.

`__module__ = 'fastr.helpers.classproperty'`

`__weakref__`

list of weak references to the object (if defined)

`fastr.helpers.classproperty.classproperty(func)`

Decorator to create a “class property”

Parameters `func` – the function to wrap

Returns a class property

Return type `ClassPropertyDescriptor`

clear_pycs Module

A small tool to wipe all .pyc files from fastr

`fastr.helpers.clear_pycs.dir_list(directory)`

Find all .pyc files

Parameters `directory` (`str`) – directory to search

Returns all .pyc files

Return type `list`

`fastr.helpers.clear_pycs.main()`

Main entry point

configmanager Module

This module defines the Fastr Config class for managing the configuration of Fastr. The config object is stored directly in the fastr top-level module.

class `fastr.helpers.configmanager.Config(*configfiles)`

Bases: `object`

Class contain the fastr configuration

`DEFAULT_FIELDS = { 'debug': (<class 'bool'>, False, 'Flag to enable/disable debugging')}`

`__dict__ = mappingproxy({ '__module__': 'fastr.helpers.configmanager', '__doc__': '\n`

`__init__(*configfiles)`

Initialize self. See help(type(self)) for accurate signature.

```

__module__ = 'fastr.helpers.configmanager'

__repr__()
    Return repr(self).

__weakref__
    list of weak references to the object (if defined)

property debug
property examplesdir
property execution_plugin
property executionscript
property filesynchelper_url
get_field(item)
property job_cleanup_level
property log_to_file
property logdir
property logging_config
property loglevel
property logtype
property mounts
property networks_path
property pim_batch_size
property pim_debug
property pim_finished_timeout
property pim_host
property pim_update_interval
property pim_username
property plugins_path
property preferred_types
property process_pool_worker_number
property protected_modules
read_config(filename)
    Read a configuration and update the configuration object accordingly

        Parameters filename – the configuration file to read

read_config_files = None
    Trace of the config files read by this object

read_config_string(value)
register_fields(fields_spec)
    Register extra fields to the configuration manager.

property reporting_plugins

```

```
property resourcesdir
property schemadir
set_field(item, value)
property slurm_job_check_interval
property slurm_partition
property source_job_limit
property systemdir
property tools_path
property types_path
property userdir
property warn_develop
property web_hostname
property web_port
property web_secret_key
web_url()
    Construct a fqdn from the web['hostname'] and web['port'] settings. :return: FQDN :rtype: str

class fastr.helpers.configmanager.EmptyDefault(data=None)
Bases: object
Empty defaultdict.

__add__(right)
__delitem__(key)
__dict__ = mappingproxy({'__module__': 'fastr.helpers.configmanager', '__doc__': ''})
__getitem__(item)
__iadd__(right)
__init__(data=None)
    Initialize self. See help(type(self)) for accurate signature.
__module__ = 'fastr.helpers.configmanager'
__radd__(other)
__setitem__(key, value)
__weakref__
    list of weak references to the object (if defined)

append(value)
asdict()
aslist()
extend(other)
merge_default(field_spec)
    Merge the default into this EmptyDefault given the field spec :param field_spec: Field specification :return:
    Merged value
```

```
prepend(value)
update(other)
```

events Module

```
class fastr.helpers.events.EventType
Bases: enum.Enum

An enumeration.

__module__ = 'fastr.helpers.events'
job_updated = 'job_updated'
log_record_emitted = 'log_record_emitted'
run_finished = 'run_finished'
run_started = 'run_started'
```

```
class fastr.helpers.events.FastrLogEventHandler(level=0)
Bases: logging.Handler
```

Logging handler that sends the log records into the event system

```
__module__ = 'fastr.helpers.events'
emit(record)
```

Do whatever it takes to actually log the specified logging record.

This version is intended to be implemented by subclasses and so raises a NotImplementedError.

```
fastr.helpers.events.emit_event(event_type, data)
```

Emit an event to all listeners :type event_type: EventType :param event_type: The type of event to emit
:param data: The data object to send along

```
fastr.helpers.events.register_listener(event_type, function)
```

Register a listeners to a specific event type

Parameters

- **event_type** (EventType) – The EventType to listen on
- **function** (Callable[[object], None]) – The callable that will be called on each event

```
fastr.helpers.events.remove_listener(event_type, function)
```

Remove a listener from a type of event

Parameters

- **event_type** (EventType) – The event type to remove the listeners from
- **function** (Callable[[object], None]) – The function to remove

filesynchelper Module

Some helper functions that aid with NFS file sync issues.

```
class fastr.helpers.filesynchelper.FileSyncHelper
Bases: object
```

```
__dict__ = mappingproxy({'__module__': 'fastr.helpers.filesynchelper', '__namespace__': ''})
__init__()
    Initialize self. See help(type(self)) for accurate signature.
__module__ = 'fastr.helpers.filesynchelper'
__weakref__
    list of weak references to the object (if defined)
has_file_promise(url)
job_finished(jobfile)
load(url)
make_file_promise(url)
store(url, data)
wait_for_file(path, timeout=300)
wait_for_job(jobfile)
wait_for_pickle(url, timeout=300)
wait_for vfs_url(vfs_url, timeout=300)

fastr.helpers.filesynchelper.filesynchelper_enabled()
```

iohelpers Module

```
fastr.helpers.iohelpers.link_or_copy(source, destination)
fastr.helpers.iohelpers.load_gpickle(path, retry_scheme=None)
fastr.helpers.iohelpers.load_json(path)
fastr.helpers.iohelpers.save_gpickle(path, data)
fastr.helpers.iohelpers.save_json(path, data, indent=2)
```

jsonschema parser Module

The JSON schema parser validates a json data structure and if possible casts data to the correct type and fills out default values. The result in a valid document that can be used to construct objects.

```
class fastr.helpers.jsonschema_parser.FastrRefResolver(base_uri, referrer, store=(), cache_remote=True, handlers=())
Bases: jsonschema.validators.RefResolver
```

Adapted version of the RefResolver for handling inter-file references more to our liking

```
__init__(base_uri, referrer, store=(), cache_remote=True, handlers=())
Create a new FastrRefResolver
```

Parameters

- **base_uri** (*str*) – URI of the referring document
- **referrer** – the actual referring document
- **store** (*dict*) – a mapping from URIs to documents to cache

- **cache_remote** (`bool`) – whether remote refs should be cached after first resolution
- **handlers** (`dict`) – a mapping from URI schemes to functions that should be used to retrieve them

```
__module__ = 'fastr.helpers.jsonschemasparser'

classmethod from_schema(schema, *args, **kwargs)
    Instantiate a RefResolver based on a schema

static readfastrschema(name)
    Open a json file based on a fastr:// url that points to a file in the fastr.schemadir

    Parameters name (str) – the url of the file to open

    Returns the resulting json schema data

static readfile(filename)
    Open a json file based on a simple filename

    Parameters filename (str) – the path of the file to read

    Returns the resulting json schema data

fastr.helpers.jsonschemasparser.any_of_draft4(validation, any_of, instance, schema)
    The oneOf directory needs to be done stepwise, because a validation even if it fails will try to change types / set defaults etc. Therefore we first create a copy of the data per subschema and test if they match. Then for all the schemas that are valid, we perform the validation on the actual data so that only the valid subschemas will effect the data.

    Parameters

        • validation – the json schema validator

        • any_of (dict) – the current oneOf

        • instance – the current object instance

        • schema (dict) – the current json schema

fastr.helpers.jsonschemasparser.extend(validation_cls)
    Extend the given jsonschema.IValidator with the Seep layer.

fastr.helpers.jsonschemasparser.getblueprinter(uri, blueprint=None)
    Instantiate the given data using the blueprinter.

    Parameters blueprint – a blueprint (JSON Schema with Seep properties)

fastr.helpers.jsonschemasparser.items_validate(validation, items, instance, schema)
    The pre-validation function for items

    Parameters

        • validation – the json schema validator

        • items (dict) – the current items

        • instance – the current object instance

        • schema (dict) – the current json schema

fastr.helpers.jsonschemasparser.not_draft4(validation, not_schema, instance, schema)
    The not needs to use a temporary copy of the instance, not to change the instance with the invalid schema

    Parameters

        • validation – the json schema validator
```

- **not_schema** (*dict*) – the current oneOf
- **instance** – the current object instance
- **schema** (*dict*) – the current json schema

`fastr.helpers.jsonschemaparser.one_of_draft4 (validator, one_of, instance, schema)`

The one_of directory needs to be done stepwise, because a validation even if it fails will try to change types / set defaults etc. Therefore we first create a copy of the data per subschema and test if they match. Once we found a proper match, we only validate that branch on the real data so that only the valid piece of schema will effect the data.

Parameters

- **validator** – the json schema validator
- **one_of** (*dict*) – the current one_of
- **instance** – the current object instance
- **schema** (*dict*) – the current json schema

`fastr.helpers.jsonschemaparser.pattern_properties_prevalid (validator, pattern_properties, instance, schema)`

The pre-validation function for patternProperties

Parameters

- **validator** – the json schema validator
- **pattern_properties** (*dict*) – the current patternProperties
- **instance** (*dict*) – the current object instance
- **schema** (*dict*) – the current json schema

`fastr.helpers.jsonschemaparser.properties_postvalidate (validator, properties, instance, schema)`

All arguments must be used because this function is called like this # pylint: disable=unused-argument The post-validation function for properties

Parameters

- **validator** – the json schema validator
- **properties** (*dict*) – the current properties
- **instance** – the current object instance
- **schema** (*dict*) – the current json schema

`fastr.helpers.jsonschemaparser.properties_prevalidate (validator, properties, instance, schema)`

The pre-validation function for properties

Parameters

- **validator** – the json schema validator
- **properties** (*dict*) – the current properties
- **instance** – the current object instance
- **schema** (*dict*) – the current json schema

lazy_module Module

This module contains the Manager class for Plugins in the fastr system

```
class fastr.helpers.lazy_module.LazyModule (name, parent, plugin_manager)
```

Bases: `module`

A module that allows content to be loaded lazily from plugins. It generally is (almost) empty and gets (partially) populated when an attribute cannot be found. This allows lazy loading and plugins depending on other plugins.

```
__getattr__ (item)
```

The getattr is called when getattribute does not return a value and is used as a fallback. In this case we try to find the value normally and will trigger the plugin manager if it cannot be found.

Parameters `item (str)` – attribute to retrieve

Returns the requested attribute

```
__init__ (name, parent, plugin_manager)
```

Initialize self. See help(type(self)) for accurate signature.

```
__module__ = 'fastr.helpers.lazy_module'
```

```
__repr__ ()
```

Return repr(self).

lockfile Module

A module implenting a lock that ensures a directory is only being used by a single fastr run.

```
class fastr.helpers.lockfile.DirectoryLock (directory)
```

Bases: `object`

A lock for a directory, it creates a directory to set the locked state and if successful writes the pid in a file inside that directory to claim the lock

```
__del__ ()
```

```
__dict__ = mappingproxy({'__module__': 'fastr.helpers.lockfile', '__doc__': '\n A lo...'})
```

```
__enter__ ()
```

```
__exit__ (type, value, traceback)
```

```
__init__ (directory)
```

Initialize self. See help(type(self)) for accurate signature.

```
__module__ = 'fastr.helpers.lockfile'
```

```
__weakref__
```

list of weak references to the object (if defined)

```
acquire ()
```

```
property lock_dir
```

```
lock_dir_name = '.fastr.lock'
```

```
property pid_file
```

```
pid_file_name = 'pid'
```

```
release ()
```

procutils Module

```
fastr.helpers.procutils.which(name)
```

Find executable by name on the PATH, returns the executable that will be found in case it is used for a Popen call

report Module

Some reporting functions, e.g. to print a report based on a job result

```
fastr.helpers.report.print_job_result(job_file, print_func=<built-in function print>)
```

rest_generation Module

```
fastr.helpers.rest_generation.create_rest_table(data, headers)
```

Create a ReST table from data. The data should be a list of columns and the headers should be a list of column names.

Parameters

- **data** (*list*) – List of lists/tuples representing the columns
- **headers** (*list*) – List of strings for the column names

Returns a string representing the table in ReST

Return type str

schematotable Module

A module to generate reStructuredText tables from json schema files

```
class fastr.helpers.schematotable.SchemaPrinter(schema, skipfirst=False)  
Bases: object
```

Object that create a table in reStructuedText from a json schema

```
_dict_ = mappingproxy({'__module__': 'fastr.helpers.schematotable', '__doc__': '\n_init_(schema, skipfirst=False)  
Create the printer object
```

Parameters

- **schema** (*dict*) – the json schema to print
- **skipfirst** (*bool*) – flag to indicate that the first line should not be printed

```
_module_ = 'fastr.helpers.schematotable'
```

```
_str_()
```

String representation of json schema (that is the printed table)

```
_weakref_
```

list of weak references to the object (if defined)

```
descend(properties)
```

Descend into a subschema

Parameters `properties` (`dict`) – the properties in the subschema

parse (`schema=None`)

Parse a schema

Parameters `schema` (`dict`) – the schema to parse

printlines()

Given a parsed schema (parsing happens when the object is constructed), print all the lines

Returns the printed table

Return type `str`

shellescape Module

Module with helper for shell escaping

`fastr.helpers.shellescape.quote_argument(arg)`

Use shlex module to quote the argument properly :type arg: `str` :param arg: argument to quote :rtype: `str` :return: argument with quotes for safe use in a bash-like shell

sysinfo Module

This module contains function to help gather system information use for the provenance of the Job execution.

`fastr.helpers.sysinfo.get_cpu_usage()`

Get the current CPU usage

Returns CPU usage info

Return type `dict`

`fastr.helpers.sysinfo.get_drmaa_info()`

Get information about the SGE cluster (if applicable)

Returns cluster info

Return type `dict`

`fastr.helpers.sysinfo.get_hostinfo()`

Get all information about the current host machine

Returns host info

Return type `dict`

`fastr.helpers.sysinfo.get_memory_usage()`

Get the current memory usage

Returns memory usage info

Return type `dict`

`fastr.helpers.sysinfo.get_mounts()`

Get the current mounts known on the system

Returns mount info

Return type `dict`

`fastr.helpers.sysinfo.get_os()`

Get information about the OS

Returns OS information

Return type dict

`fastr.helpers.sysinfo.get_processes()`

Get a list of all currently running processes

Returns process information

Return type list

`fastr.helpers.sysinfo.get_python()`

Get information about the currently used Python implementation

Returns python info

Return type dict

`fastr.helpers.sysinfo.get_sysinfo()`

Get system information (cpu, memory, mounts and users)

Returns system information

Return type dict

`fastr.helpers.sysinfo.get_users()`

Get current users on the system

Returns user info

Return type dict

`fastr.helpers.sysinfo.namedtuple_to_dict(ntuple)`

Helper function to convert a named tuple into a dict

Parameters `ntuple` (namedtuple) – the namedtuple to convert

Returns named tuple as a dict

Return type dict

xmltodict Module

This module contains tool for converting python dictionaries into XML object and vice-versa.

`fastr.helpers.xmltodict.dump(data, filehandle)`

Write a dict to an XML file

Parameters

- `data` – data to write
- `filehandle` – file handle to write to

`fastr.helpers.xmltodict.dumps(data)`

Write a dict to an XML string

Parameters `data` – data to write

Returns the XML data

Return type str

`fastr.helpers.xmltodict.load(filehandle)`

Load an xml file and parse it to a dict

Parameters `filehandle` – file handle to load

Returns the parsed data

`fastr.helpers.xmltodict.loads(data)`

Load an xml string and parse it to a dict

Parameters `data (str)` – the xml data to load

Returns the parsed data

planning Package

planning Package

inputgroup Module

`class fastr.planning.inputgroup.InputGroup(*args, **kwargs)`

Bases: `collections.OrderedDict, fastr.core.dimension.HasDimensions`

A class representing a group of inputs. Input groups allow the

`__abstractmethods__ = frozenset({})`

`__getitem__(key)`

`x.__getitem__(y) <==> x[y]`

`__init__(*args, **kwargs)`

Create a new InputGroup representation

Parameters

- `parent (NodeRun)` – the parent node

- `id (str)` – the id of the input group

Raises `FastrTypeError` – if parent is not a NodeRun

Note: This is a wrapped version of `fastr.planning.inputgroup.__init__` which triggers an update of the object after being called

`__module__ = 'fastr.planning.inputgroup'`

`__setitem__(*args, **kwargs)`

Assign an input to this input group.

Parameters

- `key (str)` – id of the input

- `value (Input)` – the input to assign

Raises `FastrTypeError` – if value of valid type

Note: This is a wrapped version of `fastr.planning.inputgroup.__setitem__` which triggers an update of the object after being called

```
__updatefunc__()
    Update the InputGroup. Triggers when a change is made to the content of the InputGroup. Automatically
    recalculates the size, primary Input etc.

__updatetriggers__ = ['__init__', '__setitem__', '__delitem__', 'clear', 'pop', 'popit']

property dimensions
    The dimensions of this InputGroup

property empty
    Bool indicating that this InputGroup is empty (has no data connected)

find_source_index(target_size, target_dimnames, source_size, source_dimnames, target_index)

property fullid

property iterinputvalues
    Iterate over the item in this InputGroup

    Returns iterator yielding SampleItems

property parent
    The parent node of this InputGroup

property primary
    The primary Input in this InputGroup. The primary Input is the Input that defines the size of this Input-
    Group. In case of ties it will be the first in the tool definition.

classmethod solve_broadcast(target_size, target_dimnames, source_size, source_dimnames,
                           target_index, nodegroups=None)
```

inputgroupcombiner Module

```
class fastr.planning.inputgroupcombiner.BaseInputGroupCombiner(parent)
Bases: fastr.core.dimension.HasDimensions

An object that takes the different input groups and combines them in the correct way.

__abstractmethods__ = frozenset({'iter_input_groups', 'merge', 'unmerge'})

__init__(parent)
    Initialize self. See help(type(self)) for accurate signature.

__iter__()

__module__ = 'fastr.planning.inputgroupcombiner'

property dimensions
    The dimensions has to be implemented by any subclass. It has to provide a tuple of Dimensions.

    Returns dimensions

    Return type tuple

property fullid
    The full id of the InputGroupCombiner

property input_groups

abstract iter_input_groups()
    Iterate over all the merged samples :return:

abstract merge(list_of_items)
    Given a list of items for each input group, it returns the combined list of items.
```

Parameters `list_of_items` (`list`) – items to combine
Returns combined list

`merge_failed_annotations` (`list_of_failed_annotations`)
`merge_payloads` (`sample_payloads`)
`merge_sample_data` (`list_of_sample_data`)
`merge_sample_id` (`list_of_sample_ids`)
`merge_sample_index` (`list_of_sample_indexes`)
`merge_sample_jobs` (`list_of_sample_jobs`)

abstract unmerge (`item`)

Given a item it will recreate the seperate items, basically this is the inverse operation of merge. However, this create an OrderedDict so that specific input groups can be easily retrieved. To get a round trip, the values of the OrderedDict should be taken:

```
>>> odict_of_items = combiner.unmerge(item)
>>> item = combiner.merge(odict_of_items.values())
```

Parameters `item` (`list`) – the item to unmerge
Returns items
Return type OrderedDict

update ()

```
class fastr.planning.inputgroupcombiner.DefaultInputGroupCombiner(parent)
Bases: fastr.planning.inputgroupcombiner.BaseInputGroupCombiner
```

The default input group combiner combines the input group in a cross product version, taking each combinations of samples between the input groups. So if there are two input groups with one with size N and the other with size M x P the result would be N x M x P samples, with all possible combinations of the samples in each input group.

```
__abstractmethods__ = frozenset({})
__module__ = 'fastr.planning.inputgroupcombiner'
iter_input_groups()
Iterate over all the merged samples :return:
```

merge (`list_of_items`)

Given a list of items for each input group, it returns the combined list of items.

Parameters `list_of_items` (`list`) – items to combine
Returns combined list

unmerge (`item`)

Given a item it will recreate the seperate items, basically this is the inverse operation of merge. However, this create an OrderedDict so that specific input groups can be easily retrieved. To get a round trip, the values of the OrderedDict should be taken:

```
>>> odict_of_items = combiner.unmerge(item)
>>> item = combiner.merge(odict_of_items.values())
```

Parameters `item` (`list`) – the item to unmerge

Returns items

Return type OrderedDict

```
class fastr.planning.inputgroupcombiner.MergingInputGroupCombiner(input_groups,
                                                               merge_dimension)
Bases: fastr.planning.inputgroupcombiner.BaseInputGroupCombiner
```

The merging input group combiner takes a similar approach as the default combiner but merges dimensions that are the same. If input group A has N(3) x M(2) samples and B has M(2) x P(4) it wil not result in N(3) x M(2) x M(2) x P(4), but merge the dimensions M leading to N(3) x M(2) x P(4) in resulting size.

```
__abstractmethods__ = frozenset({})
```

```
__init__(input_groups, merge_dimension)
```

Initialize self. See help(type(self)) for accurate signature.

```
__module__ = 'fastr.planning.inputgroupcombiner'
```

```
iter_input_groups()
```

Iterate over all the merged samples :return:

```
merge(list_of_items)
```

Given a list of items for each input group, it returns the combined list of items.

Parameters list_of_items (*list*) – items to combine

Returns combined list

```
unmerge(item)
```

Given a item it will recreate the seperate items, basically this is the inverse operation of merge. However, this create an OrderedDict so that specific input groups can be easily retrieved. To get a round trip, the values of the OrderedDict should be taken:

```
>>> odict_of_items = combiner.unmerge(item)
>>> item = combiner.merge(odict_of_items.values())
```

Parameters item (*list*) – the item to unmerge

Returns items

Return type OrderedDict

```
update()
```

inputoutput Module

Classes for arranging the input and output for nodes.

Exported classes:

Input – An input for a node (holding datatype). Output – The output of a node (holding datatype and value). ConstantOutput – The output of a node (holding datatype and value).

Warning: Don't mess with the Link, Input and Output internals from other places. There will be a huge chances of breaking the network functionality!

```
class fastr.planning.inputoutput.AdvancedFlowOutput (node, description)
Bases: fastr.planning.inputoutput.Output
```

Output for nodes that have an advanced flow. This means that the output sample id and index is not the same as the input sample id and index. The AdvancedFlowOutput has one extra dimensions that is created by the Node.

```
__abstractmethods__ = frozenset({})
__module__ = 'fastr.planning.inputoutput'
```

property dimensions

The list of the dimensions in this Output. This will be a tuple of Dimension.

```
class fastr.planning.inputoutput.BaseInput (node, description)
Bases: fastr.planning.inputoutput.BaseInputOutput
```

Base class for all inputs.

```
__abstractmethods__ = frozenset({'_update', 'dimensions', 'fullid', 'itersubinputs'})
```

```
__init__(node, description)
```

Instantiate a BaseInput

Parameters

- **node** – the parent node the input/output belongs to.
- **description** – the ParameterDescription describing the input/output.

Returns the created BaseInput

Raises

- **FastrTypeError** – if description is not of class ParameterDescription
- **FastrDataTypeNotAvailableError** – if the DataType requested cannot be found in the types

```
__lshift__(other)
```

```
__module__ = 'fastr.planning.inputoutput'
```

```
__rrshift__(other)
```

```
check_cardinality(key=None, planning=False)
```

Check if the actual cardinality matches the cardinality specified in the ParameterDescription. Optionally you can use a key to test for a specific sample.

Parameters **key** – sample_index (tuple of int) or SampleId for desired sample

Returns flag indicating that the cardinality is correct

Return type **bool**

Raises **FastrCardinalityError** – if the Input/Output has an incorrect cardinality description.

```
constant_id()
```

The id that should be used for a constant created to serve this input.

Return type **str**

```
create_link_from(value)
```

```
description_type
```

alias of *fastr.core.interface.InputSpec*

```
property item_index
```

abstract itersubinputs()

Iterator over the SubInputs

Returns iterator

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

class fastr.planning.inputoutput.BaseInputOutput(node, description)Bases: *fastr.core.dimension.HasDimensions*, *fastr.abc.updateable.Updateable*, *fastr.abc.serializable.Serializable*

Base class for Input and Output classes. It mainly implements the properties to access the data from the underlying ParameterDescription.

__abstractmethods__ = frozenset({'_update', 'dimensions', 'fullid'})**__getstate__()**

Retrieve the state of the BaseInputOutput

Returns the state of the object**Rtype** dict**__init__(node, description)**

Instantiate a BaseInputOutput

Parameters

- **node** – the parent node the input/output belongs to.
- **description** – the ParameterDescription describing the input/output.

Returns created BaseInputOutput**Raises**

- **FastrTypeError** – if description is not of class ParameterDescription
- **FastrDataTypeNotFoundError** – if the DataType requested cannot be found in the types

__iter__()

This function is blocked to avoid support for iteration using a legacy __getitem__ method.

Returns None**Raises** **FastrNotImplementedError** – always**__module__ = 'fastr.planning.inputoutput'****__ne__(other)**

Check two Node instances for inequality. This is the inverse of __eq__

Parameters **other** (*BaseInputOutput*) – the other instances to compare to**Returns** True if unequal, False otherwise**__repr__()**

Get a string representation for the Input/Output

Returns the string representation**Return type** str

`__setstate__(state)`
Set the state of the BaseInputOutput by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

`cardinality(key=None, job_data=None)`
Determine the cardinality of this Input/Output. Optionally a key can be given to determine for a sample.

Parameters `key` – key for a specific sample

Returns the cardinality

Return type `int`, `sympy.Symbol`, or `None`

`check_cardinality(key=None)`
Check if the actual cardinality matches the cardinality specified in the ParameterDescription. Optionally you can use a key to test for a specific sample.

Parameters `key` – sample_index (tuple of int) or SampleId for desired sample

Returns flag indicating that the cardinality is correct

Return type `bool`

Raises `FastrCardinalityError` – if the Input/Output has an incorrect cardinality description.

`property datatype`
The datatype of this Input/Output

`property description`
The description object of this input/output

`description_type = None`

`abstract property fullid`
The fullid of the Input/Output, the fullid should be unique and makes the object retrievable by the network.

`property id`
Id of the Input/Output

`property node`
The NodeRun to which this Input/Output belongs

`property required`
Flag indicating that the Input/Output is required

`class fastr.planning.inputoutput.BaseOutput(node, description)`
Bases: `fastr.planning.inputoutput.BaseInputOutput`

Base class for all outputs.

`__abstractmethods__ = frozenset({'_update', 'dimensions', 'fullid'})`

`__init__(node, description)`
Instantiate a BaseOutput

Parameters

- `node` – the parent node the output belongs to.
- `description` – the ParameterDescription describing the output.

Returns created BaseOutput

Raises

- **FastrTypeError** – if description is not of class ParameterDescription
- **FastrDataTypeNotFoundError** – if the DataType requested cannot be found in the types

__module__ = 'fastr.planning.inputoutput'
property automatic

Flag indicating that the Output is generated automatically without being specified on the command line

property blocking
Flag indicating that this Output will cause blocking in the execution

description_type
alias of `fastr.core.interface.OutputSpec`

class fastr.planning.inputoutput.**Input** (*node, description*)
Bases: `fastr.planning.inputoutput.BaseInput`

Class representing an input of a node. Such an input will be connected to the output of another node or the output of an constant node to provide the input value.

__abstractmethods__ = frozenset({})

__eq__ (*other*)

Compare two Input instances with each other. This function ignores the parent node and update status, but tests rest of the dict for equality.

Parameters **other** (`Input`) – the other instances to compare to

Returns True if equal, False otherwise

Return type `bool`

__getitem__ (*key*)

Retrieve an item from this Input.

Parameters **key** (`Union[int, str]`) – the key of the requested item

Return type `Union[SubInput, NamedSubInput]`

Returns The `SubInput` corresponding with the key will be returned.

Raises

- **FastrTypeError** – if key is not of a valid type
- **FastrKeyError** – if the key is not found

__getstate__ ()

Retrieve the state of the Input

Returns the state of the object

Rtype `dict`

__hash__ = `None`

__init__ (*node, description*)

Instantiate an input.

Parameters

- **node** (`NodeRun`) – the parent node of this input.
- **description** (`ParameterDescription`) – the ParameterDescription of the input.

Returns the created Input

```
__module__ = 'fastr.planning.inputoutput'
__setitem__(key, value)
    Create a link between a SubInput of this Inputs and an Output/Constant
```

Parameters

- **key** (*int*, *str*) – the key of the SubInput
- **value** (*BaseOutput*, *list*, *tuple*, *dict*, *OrderedDict*) – the target to link, can be an output or a value to create a constant for

Raises *FastrTypeError* – if key is not of a valid type

```
__setstate__(state)
    Set the state of the Input by the given state.
```

Parameters **state** (*dict*) – The state to populate the object with

Returns None

```
__str__()
    Get a string version for the Input
```

Returns the string version

Return type *str*

append (*value*)

When you want to append a link to an Input, you can use the append property. This will automatically create a new SubInput to link to.

example:

```
>>> link = node2['input'].append(node1['output'])
```

will create a new SubInput in node2[‘input’] and link to that.

cardinality (*key=None*, *job_data=None*)

Cardinality for an Input is the sum the cardinalities of the SubInputs, unless defined otherwise.

Parameters **key** (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type *int*, *sympy.Symbol*, or *None*

clear()

property **constant_id**

The id for a constant node that is attached to this input.

Return type *str*

property **datatype**

The datatype of this Input

property **dimensions**

The list names of the dimensions in this Input. This will be a list of str.

property **fullid**

The full defining ID for the Input

Return type *str*

get_sourced_nodes()

Get a list of all *Nodes* connected as sources to this Input

Returns list of all connected *Nodes*

Return type list

get_sourced_outputs()

Get a list of all *Outputs* connected as sources to this Input

Returns tuple of all connected *Outputs*

Return type tuple

property id

Id of the Input/Output

index(value)

Find index of a SubInput

Parameters **value** (*SubInput*) – the *SubInput* to find the index of

Returns key

Return type int, str

property input_group

The id of the InputGroup this Input belongs to.

Return type str

insert(index)

Insert a new SubInput at index in the sources list

Parameters **key** (int) – positive integer for position in _source list to insert to

Returns newly inserted *SubInput*

Return type *SubInput*

itersubinputs()

Iterate over the *SubInputs* in this Input.

Returns iterator yielding *SubInput*

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

remove(value)

Remove a SubInput from the SubInputs list based on the connected Link.

Parameters **value** (*SubInput*, <fastr.planning.inputoutput.SubInput>) – the *SubInput* or *Link* to removed from this Input

property source

The mapping of *SubInputs* that are connected and have more than 0 elements.

class fastr.planning.inputoutput.**MacroInput** (*node*, *description*)

Bases: *fastr.planning.inputoutput.Input*

__abstractmethods__ = frozenset({})

__module__ = 'fastr.planning.inputoutput'

```
property input_group
    The id of the InputGroup this Input belongs to.

class fastr.planning.inputoutput.MacroOutput (node, description)
Bases: fastr.planning.inputoutput.Output

__abstractmethods__ = frozenset({})
__module__ = 'fastr.planning.inputoutput'

property dimensions
    The list of the dimensions in this Output. This will be a tuple of Dimension.

class fastr.planning.inputoutput.NamedSubInput (parent)
Bases: fastr.planning.inputoutput.Input

A named subinput for cases where the value of an input is mapping.

__abstractmethods__ = frozenset({})
__getitem__ (key)
    Retrieve an item (a SubInput) from this NamedSubInput.

    Parameters key (int) – the key of the requested item
    Return type SubInput
    Returns The SubInput corresponding with the key will be returned.
    Raises
        • FastrTypeError – if key is not of a valid type
        • FastrKeyError – if the key is not found

__init__ (parent)
    Instantiate an input.

    Parameters
        • node (NodeRun) – the parent node of this input.
        • description (ParameterDescription) – the ParameterDescription of the input.
    Returns the created Input

__module__ = 'fastr.planning.inputoutput'

__str__ ()
    Get a string version for the NamedSubInput

    Returns the string version
    Return type str

property constant_id
    The id for a constant node that is attached to this input.

    Return type str

property fullid
    The full defining ID for the SubInput

property item_index

class fastr.planning.inputoutput.Output (node, description)
Bases: fastr.planning.inputoutput.BaseOutput
```

Class representing an output of a node. It holds the output values of the tool ran. Output fields can be connected to inputs of other nodes.

`__abstractmethods__ = frozenset({})`

`__eq__(other)`

Compare two Output instances with each other. This function ignores the parent node, listeners and update status, but tests rest of the dict for equality.

Parameters `other` (`fastr.planning.inputoutput.Output`) – the other instances to compare to

Returns True if equal, False otherwise

Return type `bool`

`__getitem__(key)`

Retrieve an item from this Output. The returned value depends on what type of key used:

- Retrieving data using index tuple: [index_tuple]
- Retrieving data sample_id str: [SampleId]
- Retrieving a list of data using SampleId list: [sample_id1, ..., sample_idN]
- Retrieving a `SubOutput` using an int or slice: [n] or [n:m]

Parameters `key` (`Union[int, slice]`) – the key of the requested subplot, can be a number or slice

Return type `SubOutput`

Returns the `SubOutput` for the corresponding index

Raises `FastrTypeError` – if key is not of a valid type

`__getstate__()`

Retrieve the state of the Output

Returns the state of the object

Rtype `dict`

`__hash__ = None`

`__init__(node, description)`

Instantiate an Output

Parameters

- `node` – the parent node the output belongs to.
- `description` – the ParameterDescription describing the output.

Returns created Output

Raises

- `FastrTypeError` – if description is not of class ParameterDescription
- `FastrDataTypeNotFoundError` – if the DataType requested cannot be found in the types

`__module__ = 'fastr.planning.inputoutput'`

`__setstate__(state)`

Set the state of the Output by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

__str__()
Get a string version for the Output

Returns the string version

Return type `str`

cardinality()
Cardinality of this Output, may depend on the inputs of the parent Node.

Returns the cardinality

Return type `int`, `sympy.Symbol`, or `None`

Raises

- `FastrCardinalityError` – if cardinality references an invalid `Input`
- `FastrTypeError` – if the referenced cardinality values type cannot be cast to int
- `FastrValueError` – if the referenced cardinality value cannot be cast to int

property datatype
The datatype of this Output

property dimensions
The list of the dimensions in this Output. This will be a tuple of Dimension.

property fullid
The full defining ID for the Output

property listeners
The list of `Links` connected to this Output.

property preferred_types
The list of preferred DataTypes for this Output.

property resulting_datatype
The DataType that will the results of this Output will have.

property valid
Check if the output is valid, i.e. has a valid cardinality

class `fastr.planning.inputoutput.SourceOutput` (`node, description`)
Bases: `fastr.planning.inputoutput.Output`

Output for a SourceNodeRun, this type of Output determines the cardinality in a different way than a normal NodeRun.

__abstractmethods__ = `frozenset({})`

__init__ (`node, description`)
Instantiate a FlowOutput

Parameters

- `node` – the parent node the output belongs to.
- `description` – the ParameterDescription describing the output.

Returns created FlowOutput

Raises

- **FastrTypeError** – if description is not of class ParameterDescription
- **FastrDataTypeNotFoundError** – if the DataType requested cannot be found in the types

`__module__ = 'fastr.planning.inputoutput'`

`cardinality()`

Cardinality of this SourceOutput, may depend on the inputs of the parent NodeRun.

Parameters `key` (tuple of int or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type `int`, `sympy.Symbol`, or `None`

`property linearized`

A linearized version of the sample data, this is lazily cached linearized version of the underlying SampleCollection.

`class fastr.planning.inputoutput.SubInput(input_)`

Bases: `fastr.planning.inputoutput.BaseInput`

This class is used by `Input` to allow for multiple links to an `Input`. The SubInput class can hold only a single Link to a (Sub)Output, but behaves very similar to an `Input` otherwise.

`__abstractmethods__ = frozenset({})`

`__eq__(other)`

Compare two SubInput instances with each other. This function ignores the parent, node, source and update status, but tests rest of the dict for equality.

Parameters `other` (`SubInput`) – the other instances to compare to

Returns True if equal, False otherwise

`__getitem__(key)`

Retrieve an item from this SubInput.

Parameters `key` (`int`) – the index of the requested item

Returns the corresponding `SubInput`

Return type `SubInput`

Raises `FastrTypeError` – if key is not of a valid type

Note: As a SubInput has only one SubInput, only requesting int key 0 or -1 is allowed, and it will return self

`__getstate__()`

Retrieve the state of the SubInput

Returns the state of the object

Rtype dict

`__hash__ = None`

`__init__(input_)`

Instantiate an SubInput.

Parameters `input` (`Input`) – the parent of this SubInput.

Returns the created SubInput

```
__module__ = 'fastr.planning.inputoutput'
```

setstate(*state*)
Set the state of the SubInput by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

str()
Get a string version for the SubInput

Returns the string version

Return type *str*

cardinality(*key=None, job_data=None*)
Get the cardinality for this SubInput. The cardinality for a SubInputs is defined by the incoming link.

Parameters **key** (SampleIndex or SampleId) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type *int*, sympy.Symbol, or *None*

property constant_id
The id for a constant node that is attached to this input.

Return type *str*

property description
The description object of this input/output

property dimensions
List of dimension for this SubInput

property fullid
The full defining ID for the SubInput

get_sourced_nodes()
Get a list of all *Nodes* connected as sources to this SubInput

Returns list of all connected *Nodes*

Return type *list*

get_sourced_outputs()
Get a list of all *Outputs* connected as sources to this SubInput

Returns list of all connected *Outputs*

Return type *list*

property input_group
The id of the InputGroup this SubInputs parent belongs to.

property item_index

iteritems()
Iterate over the SampleItems that are in the SubInput.

Returns iterator yielding SampleItem objects

itersubinputs()

Iterate over SubInputs (for a SubInput it will yield self and stop iterating after that)

Returns iterator yielding *SubInput*

example:

```
>>> for subinput in input_a.itersubinputs():
    print subinput
```

property node

The Node to which this SubInputs parent belongs

remove(*value*)

Remove a SubInput from parent Input.

Parameters *value* (*SubInput*) – the *SubInput* to removed from this Input

property source

A list with the source *Link*. The list is to be compatible with *Input*

property source_output

The *Output* linked to this SubInput

class fastr.planning.inputoutput.SubOutput(*output, index*)

Bases: *fastr.planning.inputoutput.Output*

The SubOutput is an Output that represents a slice of another Output.

__abstractmethods__ = frozenset({})**__eq__(*other*)**

Compare two SubOutput instances with each other. This function ignores the parent, node and update status, but tests rest of the dict for equality. equality

Parameters *other* (*SubOutput*) – the other instances to compare to

Returns True if equal, False otherwise

Return type *bool*

__getstate__()

Retrieve the state of the SubOutput

Returns the state of the object

Rtype dict

__hash__ = None**__init__(*output, index*)**

Instantiate a SubOutput

Parameters

- **output** – the parent output the suboutput slices.
- **index** (*int or slice*) – the way to slice the parent output

Returns created SubOutput

Raises

- **FastrTypeError** – if the output argument is not an instance of *Output*
- **FastrTypeError** – if the index argument is not an int or slice

__len__()

Return the length of the Output.

Note: In a SubOutput this is always 1.

__module__ = 'fastr.planning.inputoutput'**__setstate__(state)**

Set the state of the SubOutput by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

__str__()

Get a string version for the SubOutput

Returns the string version

Return type **str**

cardinality()

Cardinality of this SubOutput depends on the parent Output and `self.index`

Parameters **key** (tuple of int or `SampleId`) – key for a specific sample, can be sample index or id

Returns the cardinality

Return type **int**, `sympy.Symbol`, or `None`

Raises

- **FastrCardinalityError** – if cardinality references an invalid `Input`
- **FastrTypeError** – if the referenced cardinality values type cannot be cast to int
- **FastrValueError** – if the referenced cardinality value cannot be cast to int

property datatype

The datatype of this SubOutput

property fullid

The full defining ID for the SubOutput

property indexrep

Simple representation of the index.

property listeners

The list of `Links` connected to this Output.

property node

The NodeRun to which this SubOutput belongs

property preferred_types

The list of preferred DataTypes for this SubOutput.

property resulting_datatype

The DataType that will the results of this SubOutput will have.

property samples

The SampleCollection for this SubOutput

link Module

The link module contain the Link class. This class represents the links in a network. These links lead from an output (BaseOutput) to an input (BaseInput) and indicate the desired data flow. Links are smart objects, in the sense that when you set their start or end point, they register themselves with the Input and Output. They do all the book keeping, so as long as you only set the source and target of the Link, the link should be valid.

Warning: Don't mess with the Link, Input and Output internals from other places. There will be a huge chances of breaking the network functionality!

```
class fastr.planning.link.Link(source, target, parent, id_=None, collapse=None, expand=None)
Bases: fastr.core.dimension.HasDimensions, fastr.abc.updateable.Updateable,
fastr.abc.serializable.Serializable
```

Class for linking outputs (*BaseOutput*) to inputs (*BaseInput*)

Examples:

```
>>> import fastr
>>> network = fastr.create_network()
>>> link1 = network.create_link( n1.outputs['out1'], n2.inputs['in2'] )

link2 = Link()
link2.source = n1.outputs['out1']
link2.target = n2.inputs['in2']
```

```
__abstractmethods__ = frozenset({})
__dataschemafile__ = 'Link.schema.json'
__eq__(other)
```

Test for equality between two Links

Parameters *other* (*Link*) – object to test against

Return type *bool*

Returns True for equality, False otherwise

```
__getstate__()
```

Retrieve the state of the Link

Return type *dict*

Returns the state of the object

```
__hash__ = None
```

```
__init__(source, target, parent, id_=None, collapse=None, expand=None)
```

Create a new Link in a Network.

Parameters

- **source** (*BaseOutput*) – the source output
- **target** (*BaseInput*) – the target input
- **parent** (*Network* or None) – the parent network
- **id** – the id of the link, if no **id**_ is given, the id will be in the form of “link_{:d}”

- **collapse** (`Union[str, int, Tuple[str, ...], None]`) – the dimensions that the link has to collapse on
- **expand** (`Optional[bool]`) – Does this link need to expand the cardinality into a new sample dimension

Returns newly created Link

Raises

- **FastrValueError** – if parent is not given
- **FastrValueError** – if the source output is not in the same network as the Link
- **FastrValueError** – if the target input is not in the same network as the Link

`__module__ = 'fastr.planning.link'`

`__repr__()`

Get a string representation for the Link

Return type `str`

`__setstate__(state)`

Set the state of the Link by the given state.

Parameters `state (dict)` – The state to populate the object with

Returns None

Raises **FastrValueError** – if the parent network is not set

`cardinality(index=None)`

Cardinality for a Link is given by source Output and the collapse/expand settings

Parameters `index (Optional[SampleIndex])` – index for a specific sample (can be only a sample index!)

Return type `Union[int, Symbol]`

Returns the cardinality

Raises **FastrIndexError** – if the index length does not match the number of dimension in the data

`property collapse`

The converging dimensions of this link. Collapsing changes some dimensions of sample lists into cardinality, reshaping the data.

Collapse can be set to a tuple or an int/str, in which case it will be automatically wrapped in a tuple. The int will be seen as indices of the dimensions to collapse. The str will be seen as the name of the dimensions over which to collapse.

Raises **FastrTypeError** – if assigning a collapse value of a wrong type

`property collapse_indexes`

The converging dimensions of this link as integers. Dimension names are replaced with the corresponding int.

Collapsing changes some dimensions of sample lists into cardinality, reshaping the data

`classmethod createobj(state, network=None)`

Create object function for Link

Parameters

- `cls` – The class to create

- **state** (`dict`) – The state to use to create the Link
- **network** – the parent Network

Returns newly created Link

destroy()

The destroy function of a link removes all default references to a link. This means the references in the network, input and output connected to this link. If there is no references in other places in the code, it will destroy the link (reference count dropping to zero).

This function is called when a source for an input is set to another value and the links becomes disconnected. This makes sure there is no dangling links.

property dimensions

The dimensions of the data delivered by the link. This can be different from the source dimensions because the link can make data collapse or expand.

draw(context, graph)

property expand

Flag indicating that the link will expand the cardinality into a new sample dimension to be created.

property fullid

The full defining ID for the Input

property parent

The Network to which this Link belongs.

property source

The source `BaseOutput` of the Link. Setting the source will automatically register the Link with the source `BaseOutput`. Updating source will also make sure the Link is unregistered with the previous source.

Raises `FastrTypeError` – if assigning a non `BaseOutput`

property status

property target

The target `BaseInput` of the Link. Setting the target will automatically register the Link with the target `BaseInput`. Updating target will also make sure the Link is unregistered with the previous target.

Raises `FastrTypeError` – if assigning a non `BaseInput`

network Module

Network module containing Network facilitators and analysers.

```
class fastr.planning.network.Network(id_='unnamed_network',      version=None,      file-
                                         name=None)
Bases: fastr.abc.serializable.Serializable
```

The NetworkRun contains the entire Run state for a Network execution. It has a working copy of the network, but also includes all temporary data required for the execution. These objects are meant to be single use.

```
NETWORK_DUMP_FILE_NAME = '__fastr_network__.json'
SINK_DUMP_FILE_NAME = '__sink_data__.json'
SOURCE_DUMP_FILE_NAME = '__source_data__.pickle.gz'
__dataschemafile__ = 'Network.schema.json'
__eq__(other)
```

Compare two Networks and see if they are equal.

Parameters other (*Network*) –

Returns flag indicating that the Networks are the same

Return type `bool`

__getitem__ (*item*)
Get an item by its fullid. The fullid can point to a link, node, input, output or even subinput/suboutput.

Parameters item (*str, unicode*) – fullid of the item to retrieve

Returns the requested item

__getstate__ ()
Retrieve the state of the Network

Returns the state of the object

Rtype `dict`

__hash__ = None

__init__ (*id='unnamed_network', version=None, filename=None*)
Create a new, empty Network

Parameters name (*str*) – name of the Network

Returns newly created Network

Raises `OSError` – if the tmp mount in the config is not a writable directory

__module__ = 'fastr.planning.network'

__ne__ (*other*)
Tests for non-equality, this is the negated version `__eq__`

__repr__ ()
Return repr(self).

__setstate__ (*state*)
Set the state of the Network by the given state. This completely overwrites the old state!

Parameters state (*dict*) – The state to populate the object with

Returns None

add_link (*link*)
Add a Link to the Network. Make sure the link is in the link list and the link parent is set to this Network

Parameters link (*Link*) – link to add

Raises

- `FastrTypeError` – if link is incorrectly typed
- `FastrNetworkMismatchError` – if the link already belongs to another Network

add_node (*node*)
Add a Node to the Network. Make sure the node is in the node list and the node parent is set to this Network

Parameters node (*Node*) – node to add

Raises `FastrTypeError` – if node is incorrectly typed

add_stepid (*stepid, node*)
Add a Node to a specific step id

Parameters

- **stepid** (*str*) – the stepid that the node will be added to
- **node** (*Node*) – the node to add to the stepid

check_id (*id*)

Check if an id for an object is valid and unused in the Network. The method will always return True if it does not raise an exception.

Parameters **id** (*str*) – the id to check

Returns True

Raises

- **FastrValueError** – if the id is not correctly formatted
- **FastrValueError** – if the id is already in use

create_constant (*datatype*, *data*, *id*=*None*, *stepid*=*None*, *resources*=*None*, *nodegroup*=*None*)

Create a ConstantNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (*BaseDataType*) – The DataType of the constant node
- **data** (*datatype or list of datatype*) – The data to hold in the constant node
- **id** (*str*) – The id of the constant node to be created
- **stepid** (*str*) – The stepid to add the created constant node to
- **resources** – The resources required to run this node
- **nodegroup** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Returns the newly created constant node

Return type *ConstantNode*

create_link (*source*, *target*, *id*=*None*, *collapse*=*None*, *expand*=*None*)

Create a link between two Nodes and add it to the current Network.

Parameters

- **source** (*BaseOutput*) – the output that is the source of the link
- **target** (*BaseInput*) – the input that is the target of the link
- **id** (*str*) – the id of the link

Returns the created link

Type *Link*

create_macro (*network*, *resources*=*None*, *id*=*None*)

create_node (*tool*, *tool_version*, *id*=*None*, *stepid*=*None*, *resources*=*None*, *nodegroup*=*None*)

Create a Node in this Network. The Node will be automatically added to the Network.

Parameters

- **tool** (*Tool*) – The Tool to base the Node on
- **id** (*str*) – The id of the node to be created
- **stepid** (*str*) – The stepid to add the created node to

- **resources** – The resources required to run this node
- **nodegroup** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Returns the newly created node

Return type *Node*

create_reference (*source_data*, *output_directory*)

create_sink (*datatype*, *id_=None*, *stepid=None*, *resources=None*, *nodegroup=None*)

Create a SinkNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (*BaseDataType*) – The DataType of the sink node
- **id** (*str*) – The id of the sink node to be created
- **stepid** (*str*) – The stepid to add the created sink node to
- **resources** – The resources required to run this node

Returns the newly created sink node

Return type *SinkNode*

create_source (*datatype*, *id_=None*, *stepid=None*, *resources=None*, *nodegroup=None*)

Create a SourceNode in this Network. The Node will be automatically added to the Network.

Parameters

- **datatype** (*BaseDataType*) – The DataType of the source source_node
- **id** (*str*) – The id of the source source_node to be created
- **stepid** (*str*) – The stepid to add the created source source_node to
- **resources** – The resources required to run this node
- **nodegroup** (*str*) – The group the node belongs to, this can be important for FlowNodes and such, as they will have matching dimension names.

Returns the newly created source source_node

Return type *SourceNode*

draw (*name=None*, *draw_dimensions=True*, *hide_unconnected=True*, *context=None*, *graph=None*, *expand_macro=False*, *font_size=14*)

draw_network (*name='network_layout'*, *img_format='svg'*, *draw_dimension=True*, *hide_unconnected=True*, *expand_macro=False*, *font_size=14*)

Output a dot file and try to convert it to an image file.

Parameters **img_format** (*str*) – extension of the image format to convert to

Returns path of the image created or None if failed

Return type *str* or *None*

execute (*sourcedata*, *sinkdata*, *blocking=True*, ***kwargs*)

property fullid

The fullid of the Network, within the network scope

property global_id

The global id of the Network, this is different for networks used in macronodes, as they still have parents.

```
property id
    The id of the Network. This is a read only property.

is_valid()

namespace = None
    The namespace this network lives in, this will be set by the NetworkManager on load

property nodegroups
    Give an overview of the nodegroups in the network

property ns_id
    The namespace and id of the Tool

remove (value)
    Remove an item from the Network.

    Parameters value (Node or Link) – the item to remove

classmethod test (reference_data_dir,           network=None,           source_data=None,
                  force_remove_temp=False, tmp_results_dir=None)
    Execute the network with the source data specified and test the results against the reference data. This effectively tests the network execution.
```

Parameters

- **reference_data_dir** (*str*) – The path or vfs url of reference data to compare with
- **source_data** (*dict*) – The source data to use
- **force_remove_temp** – Make sure the tmp results directory is cleaned at end of test
- **tmp_results_dir** – Path to results directory

node Module

A module to maintain a network node.

Exported classes:

Node – A class encapsulating a tool. ConstantNode – A node encapsulating an Output to set scalar values. SourceNode – A class providing a handle to a file.

```
class fastr.planning.node.AdvancedFlowNode (tool,      id=None,      parent=None,      re-
                                              source_limits=None, nodegroup=None)
    Bases: fastr.planning.node.FlowNode
    __abstractmethods__ = frozenset({})
    __module__ = 'fastr.planning.node'

class fastr.planning.node.BaseNode
    Bases: fastr.core.dimension.HasDimensions, fastr.abc.updateable.Updateable,
            fastr.abc.serializable.Serializable
    NODE_TYPES = {'AdvancedFlowNode': <class 'fastr.planning.node.AdvancedFlowNode'>, 'Co
    __abstractmethods__ = frozenset({'_update', 'dimensions'})
    classmethod __init_subclass__(**kwargs)
        Register nodes in class for easily location
    __module__ = 'fastr.planning.node'
```

```
class fastr.planning.node.ConstantNode(datatype, data, id_=None, parent=None, resource_limits=None, nodegroup=None)
Bases: fastr.planning.node.SourceNode
```

Class encapsulating one output for which a value can be set. For example used to set a scalar value to the input of a node.

```
__abstractmethods__ = frozenset({})
__dataschemafile__ = 'ConstantNode.schema.json'
__getstate__()
```

Retrieve the state of the ConstantNode

Returns the state of the object

Rtype dict

```
__init__(datatype, data, id_=None, parent=None, resource_limits=None, nodegroup=None)
Instantiation of the ConstantNode.
```

Parameters

- **datatype** – The datatype of the output.
- **data** – the prefilled data to use.
- **id** – The url pattern.

This class should never be instantiated directly (unless you know what you are doing). Instead create a constant using the network class like shown in the usage example below.

usage example:

```
>>> import fastr
>>> network = fastr.create_network()
>>> source = network.create_source(datatype=types['ITKImageFile'], id_=
    ↪'sourceN')
```

or alternatively create a constant node by assigning data to an item in an InputDict:

```
>>> node_a.inputs['in'] = ['some', 'data']
```

which automatically creates and links a ConstantNode to the specified Input

```
__module__ = 'fastr.planning.node'
```

```
__setstate__(state)
```

Set the state of the ConstantNode by the given state.

Parameters **state** (*dict*) – The state to populate the object with

Returns None

```
property data
```

The data stored in this constant node

```
draw(context, graph, color=None)
```

```
property print_value
```

```
set_data(data=None, ids=None)
```

Set the data of this constant node in the correct way. This is mainly for compatibility with the parent class SourceNode

Parameters

- **data** (*dict or list of urls*) – the data to use
- **ids** – if data is a list, a list of accompanying ids

```
class fastr.planning.node.FlowNode(tool, id=None, parent=None, resource_limits=None, nodegroup=None)
```

Bases: *fastr.planning.node.Node*

A Flow Node is a special subclass of Nodes in which the amount of samples can vary per Output. This allows non-default data flows.

```
__abstractmethods__ = frozenset({})
__init__(tool, id=None, parent=None, resource_limits=None, nodegroup=None)
    Instantiate a flow node.
```

Parameters

- **tool** (*Tool*) – The tool to base the node on
- **id** (*str*) – the id of the node
- **parent** (*Network*) – the parent network of the node

Returns the newly created FlowNode

```
__module__ = 'fastr.planning.node'
```

property blocking

A FlowNode is (for the moment) always considered blocking.

Returns True

property dimensions

Names of the dimensions in the Node output. These will be reflected in the SampleIdList of this Node.

property outputszie

Size of the outputs in this Node

```
class fastr.planning.node.InputDict
```

Bases: *collections.OrderedDict*

The container containing the Inputs of Node. Implements helper functions for the easy linking syntax.

```
__module__ = 'fastr.planning.node'
```

__setitem__(key, value)

Set an item in the input dictionary. The behaviour depends on the type of the value. For a *BaseInput*, the input will simply be added to the list of inputs. For a *BaseOutput*, a link between the output and input will be created.

Parameters

- **key** (*str*) – id of the input to assign/link
- **value** (*BaseInput* or *BaseOutput*) – either the input to add or the output to link
- **dict_setitem** – the setitem function to use for the underlying OrderedDict insert

```
class fastr.planning.node.MacroNode(value, id=None, parent=None, resource_limits=None, nodegroup=None)
```

Bases: *fastr.planning.node.Node*

MacroNode encapsulates an entire network in a single node.

```
__abstractmethods__ = frozenset({})
```

`__eq__(other)`

Compare two MacroNode instances with each other. This function ignores the parent and update status, but tests rest of the dict for equality.

Parameters `other` (`MacroNode`) – the other instances to compare to

Returns True if equal, False otherwise

`__getstate__()`

Retrieve the state of the MacroNode

Returns the state of the object

Rtype dict

`__hash__ = None`**`__init__(value, id=None, parent=None, resource_limits=None, nodegroup=None)`**

Parameters `network` (`fastr.planning.network.Network`) – network to create macronode for

`__module__ = 'fastr.planning.node'`**`__setstate__(state)`**

Set the state of the Node by the given state.

Parameters `state` (`dict`) – The state to populate the object with

Returns None

`draw(context, graph, color=None)`**`draw_link_target(context, port_name, input=True)`****`get_output_info(output)`**

This functions maps the output dimensions based on the input dimensions of the macro. This is cached for speed as this can become rather costly otherwise

Parameters `output` – output to get info for

Returns tuple of Dimensions

`property network`

```
class fastr.planning.node.Node(tool, id=None, node_class=None, parent=None, re-
source_limits=None, nodegroup=None)
Bases: fastr.planning.node.BaseNode
```

The class encapsulating a node in the network. The node is responsible for setting and checking inputs and outputs based on the description provided by a tool instance.

`__abstractmethods__ = frozenset({})`**`__dataschemafile__ = 'Node.schema.json'`****`__eq__(other)`**

Check two Node instances for equality.

Parameters `other` (`fastr.planning.node.Node`) – the other instances to compare to

Returns True if equal, False otherwise

`__getstate__()`

Retrieve the state of the Node

Returns the state of the object

Rtype dict

__hash__ = `None`

__init__(*tool*, *id*=`None`, *node_class*=`None`, *parent*=`None`, *resource_limits*=`None`, *node_group*=`None`)
Instantiate a node.

Parameters

- **tool** (`Tool`) – The tool to base the node on
- **id** (`str`) – the id of the node
- **node_class** (`str`) – The class of the NodeRun to create (e.g. `SourceNodeRun`, `NodeRun`)
- **parent** (`Network`) – the parent network of the node
- **cores** (`int`) – number of cores required for executing this Node
- **memory** (`str`) – amount of memory required in the form d+[mMgG] where M is for megabyte and G for gigabyte
- **walltime** (`str`) – amount of time required in second or in the form HOURS:MINUTES:SECOND

Returns the newly created Node

__module__ = `'fastr.planning.node'`

__ne__(*other*)
Check two Node instances for inequality. This is the inverse of `__eq__`

Parameters **other** (`fastr.planning.node.Node`) – the other instances to compare to

Returns True if unequal, False otherwise

__repr__()
Get a string representation for the Node

Returns the string representation

Return type `str`

__setstate__(*state*)
Set the state of the Node by the given state.

Parameters **state** (`dict`) – The state to populate the object with

Returns None

__str__()
Get a string version for the Node

Returns the string version

Return type `str`

property `blocking`
Indicate that the results of this Node cannot be determined without first executing the Node, causing a blockage in the creation of jobs. A blocking Nodes causes the Chunk borders.

classmethod `createobj`(*state*, *network*=`None`)
Create object function for generic objects

Parameters

- **cls** – The class to create
- **state** – The state to use to create the Link
- **network** – the parent Network

Returns newly created Link

property dimensions

The dimensions has to be implemented by any subclass. It has to provide a tuple of Dimensions.

Returns dimensions

Return type tuple

property dimnames

Names of the dimensions in the Node output. These will be reflected in the SampleIdList of this Node.

draw(context, graph, color=None)

draw_id(context)

draw_link_target(context, port_name, input=True)

find_source_index(target_index, target, source)

property fullid

The full defining ID for the Node inside the network

get_sourced_nodes()

A list of all Nodes connected as sources to this Node

Returns list of all nodes that are connected to an input of this node

property global_id

The global defining ID for the Node from the main network (goes out of macro nodes to root network)

property id

The id of the Node

property input_groups

A list of input groups for this Node. An input group is InputGroup object filled according to the Node

inputs = None

A list of inputs of this Node

property listeners

All the listeners requesting output of this node, this means the listeners of all Outputs and SubOutputs

property merge_dimensions

property name

Name of the Tool the Node was based on. In case a Toolless Node was used the class name is given.

property nodegroup

outputs = None

A list of outputs of this Node

property outputsize

The size of output of this SourceNode

property parent

The parent is the Network this Node is part of

```
property status
```

```
property tool
```

```
update_input_groups()
```

Update all input groups in this node

```
class fastr.planning.node.OutputDict
```

Bases: `collections.OrderedDict`

The container containing the Inputs of Node. Only checks if the inserted values are actually outputs.

```
__module__ = 'fastr.planning.node'
```

```
__setitem__(key, value)
```

Set an output.

Parameters

- **key** (`str`) – the key of the item to set
- **value** (`BaseOutput`) – the output to set
- **dict_setitem** – the setitem function to use for the underlying OrderedDict insert

```
class fastr.planning.node.SinkNode(datatype, id_=None, parent=None, resource_limits=None,  
nodegroup=None)
```

Bases: `fastr.planning.node.Node`

Class which handles where the output goes. This can be any kind of file, e.g. image files, textfiles, config files, etc.

```
__abstractmethods__ = frozenset({})
```

```
__dataschemafile__ = 'SinkNode.schema.json'
```

```
__getstate__()
```

Retrieve the state of the Node

Returns the state of the object

Rtype dict

```
__init__(datatype, id_=None, parent=None, resource_limits=None, nodegroup=None)
```

Instantiation of the SourceNode.

Parameters

- **datatype** – The datatype of the output.
- **id** – the id of the node to create

Returns newly created sink node

usage example:

```
>>> import fastr  
>>> network = fastr.create_network()  
>>> sink = network.create_sink(datatype=types['ITKImageFile'], id_='SinkN')
```

```
__module__ = 'fastr.planning.node'
```

```
__setstate__(state)
```

Set the state of the Node by the given state.

Parameters **state** (`dict`) – The state to populate the object with

Returns None

```
property datatype
    The datatype of the data this sink can store.

draw(context, graph, color=None)

property input
    The default input of the sink Node

class fastr.planning.node.SourceNode(datatype, id_=None, parent=None, re-
                                             source_limits=None, nodegroup=None)
Bases: fastr.planning.node.FlowNode

Class providing a connection to data resources. This can be any kind of file, stream, database, etc from which data can be received.

__abstractmethods__ = frozenset({})

__dataschemafile__ = 'SourceNode.schema.json'

__getstate__()  

    Retrieve the state of the SourceNode

    Returns the state of the object

    Rtype dict

__init__(datatype, id_=None, parent=None, resource_limits=None, nodegroup=None)  

    Instantiation of the SourceNode.

    Parameters
        • datatype – The (id of) the datatype of the output.
        • id – The url pattern.

    This class should never be instantiated directly (unless you know what you are doing). Instead create a source using the network class like shown in the usage example below.

    usage example:

    >>> import fastr
    >>> network = fastr.create_network()
    >>> source = network.create_source(datatype=types['ITKImageFile'], id_=
    ↪'sourceN')

__module__ = 'fastr.planning.node'

__setstate__(state)  

    Set the state of the SourceNode by the given state.

    Parameters state (dict) – The state to populate the object with

    Returns None

property datatype
    The datatype of the data this source supplies.

property dimensions
    The dimensions in the SourceNode output. These will be reflected in the SampleIdLists.

draw(context, graph, color=None)

property nodegroup

property output
    Shorthand for self.outputs['output']
```

set_data (*data, ids=None*)

Set the data of this source node.

Parameters

- **data** (*dict, OrderedDict or list of urls*) – the data to use
- **ids** – if data is a list, a list of accompanying ids

property sourcegroup

property valid

This does nothing. It only overloads the valid method of Node(). The original is intended to check if the inputs are connected to some output. Since this class does not implement inputs, it is skipped.

Subpackages

test Package

test_network Module

test_node Module

plugins Package

plugins Package

The plugins module holds all plugins loaded by Fastr. It is empty on start and gets filled by the BasePluginManager

class fastr.plugins.BlockingExecution (*finished_callback=None, cancelled_callback=None*)
Bases: *fastr.plugins.executionplugin.ExecutionPlugin*

The blocking execution plugin is a special plugin which is meant for debug purposes. It will not queue jobs but immediately execute them inline, effectively blocking fastr until the Job is finished. It is the simplest execution plugin and can be used as a template for new plugins or for testing purposes.

__abstractmethods__ = frozenset({})
__init__ (*finished_callback=None, cancelled_callback=None*)
Setup the ExecutionPlugin

Parameters

- **finished_callback** – the callback to call after a job finished
- **cancelled_callback** – the callback to call after a job cancelled

Returns newly created ExecutionPlugin

__module__ = 'fastr.plugins'

cleanup()

Method to call to clean up the ExecutionPlugin. This can be to clear temporary data, close connections, etc.

Parameters **force** – force cleanup (e.g. kill instead of join a process)

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python
module = <module 'blockingexecution' from '/home/docs/checkouts/readthedocs.org/user_b

```
classmethod test()
    Test the plugin, default behaviour is just to instantiate the plugin
```

```
class fastr.plugins.CommaSepерatedValueFile
Bases: fastr.core.ioplugin.IOPPlugin
```

The CommaSepерatedValueFile an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs.

The `csv://` URL is a `vfs://` URL with a number of query variables available. The URL mount and path should point to a valid CSV file. The query variable then specify what column(s) of the file should be used.

The following variable can be set in the query:

variable	usage
value	the column containing the value of interest, can be int for index or string for key
id	the column containing the sample id (optional)
header	indicates if the first row is considered the header, can be <code>true</code> or <code>false</code> (optional)
delimiter	the delimiter used in the csv file (optional)
quote	the quote character used in the csv file (optional)
reformat	a reformatting string so that <code>value = reformat.format(value)</code> (used before relative_path)
relative_path	indicates the entries are relative paths (for files), can be <code>true</code> or <code>false</code> (optional)

The header is by default `false` if the neither the `value` and `id` are set as a string. If either of these are a string, the header is required to define the column names and it automatically is assumed `true`

The delimiter and quota characters of the file should be detected automatically using the `Sniffer`, but can be forced by setting them in the URL.

Example of valid csv URLs:

```
# Use the first column in the file (no header row assumed)
csv://mount/some/dir/file.csv?value=0

# Use the images column in the file (first row is assumed header row)
csv://mount/some/dir/file.csv?value=images

# Use the segmentations column in the file (first row is assumed header row)
# and use the id column as the sample id
csv://mount/some/dir/file.csv?value=segmentations&id=id

# Use the first column as the id and the second column as the value
# and skip the first row (considered the header)
csv://mount/some/dir/file.csv?value=1&id=0&header=true

# Use the first column and force the delimiter to be a comma
csv://mount/some/dir/file.csv?value=0&delimiter=,
```

```
__abstractmethods__ = frozenset({})
```

```
__init__()
```

Initialization for the IOPlugin

Returns newly created IOPlugin

```
__module__ = 'fastr.plugins'
```

expand_url (url)

(abstract) Expand an URL. This allows a source to collect multiple samples from a single url. The URL will have a wildcard or point to something with info and multiple urls will be returned.

Parameters `url (str)` – url to expand

Returns the resulting url(s), a tuple if multiple, otherwise a str

Return type str or tuple of str

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/crossvalidation.py'
module = <module 'commaseparatedvaluefile' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/crossvalidation.py'>
scheme = 'csv'
```

class fastr.plugins.CrossValidation

Bases: flowinterface.FlowPlugin

Advanced flow plugin that generated a cross-validation data flow. The node need an input with data and an input number of folds. Based on that the outputs test and train will be supplied with a number of data sets.

```
__abstractmethods__ = frozenset({})
```

```
__module__ = 'fastr.plugins'
```

```
static execute(payload)
```

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/crossvalidation.py'
module = <module 'crossvalidation' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/crossvalidation.py'>
```

class fastr.plugins.DRMAAExecution (finished_callback=None, cancelled_callback=None)

Bases: [fastr.plugins.executionplugin.ExecutionPlugin](#)

A DRMAA execution plugin to execute Jobs on a Grid Engine cluster. It uses a configuration option for selecting the queue to submit to. It uses the python drmaa package.

Note: To use this plugin, make sure the drmaa package is installed and that the execution is started on an SGE submit host with DRMAA libraries installed.

Note: This plugin is at the moment tailored to SGE, but it should be fairly easy to make different subclasses for different DRMAA supporting systems.

```
CANCELS_DEPENDENCIES = False
```

```
GE_NATIVE_SPEC = {'CWD': '-cwd', 'DEPENDS': '-hold_jid {hold_list}', 'DEPENDS_SEP': ', '}
```

```
NATIVE_SPEC = {'grid_engine': {'CWD': '-cwd', 'DEPENDS': '-hold_jid {hold_list}', 'DEPENDS_SEP': ', '}}
```

```
SUPPORTS_CANCEL = True
```

```
SUPPORTS_DEPENDENCY = True
```

```
SUPPORTS_HOLD_RELEASE = True
```

```
TORQUE_NATIVE_SPEC = {'CWD': '', 'DEPENDS': '-W depend=afterok:{hold_list}', 'DEPENDS_SEP': ', '}
```

```
__abstractmethods__ = frozenset({})
```

```
__init__(finished_callback=None, cancelled_callback=None)
```

Setup the ExecutionPlugin

Parameters

- **finished_callback** – the callback to call after a job finished
- **cancelled_callback** – the callback to call after a job cancelled

Returns newly created ExecutionPlugin

```
__module__ = 'fastr.plugins'
```

```
cleanup()
```

Method to call to clean up the ExecutionPlugin. This can be to clear temporary data, close connections, etc.

Parameters **force** – force cleanup (e.g. kill instead of join a process)

```
collect_jobs()
```

```
configuration_fields = {'drmaa_engine': (<class 'str'>, 'grid_engine', 'The engine to
```

```
create_native_spec (queue, walltime, memory, ncores, outputLog, errorLog, hold_job, hold)
```

Create the native spec for the DRMAA scheduler. Needs to be implemented in the subclasses

Parameters

- **queue** (*str*) – the queue to submit to
- **walltime** (*str*) – walltime specified
- **memory** (*str*) – memory requested
- **ncores** (*int*) – number of cores requested
- **outputLog** (*str*) – the location of the stdout log
- **errorLog** (*str*) – the location of stderr log
- **hold_job** (*list*) – list of jobs to depend on
- **hold** (*bool*) – flag if job should be submitted in hold mode

Returns

```
property current_jobs
```

```
dispatch_callbacks()
```

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/_native.py'
```

```
job_regression_check()
```

```
module = <module 'drmaaexec' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/_native.py'>
```

```
send_job (command, arguments, queue=None, resources=None, job_name=None, joinLogFile=False, outputLog=None, errorLog=None, hold_job=None, hold=False)
```

```
property spec_fields
```

```
submit_jobs()
```

```
classmethod test()
```

Test the plugin, default behaviour is just to instantiate the plugin

```
class fastr.plugins.DockerTarget (binary, docker_image)
```

Bases: *fastr.core.target.Target*

A tool target that is located in a Docker images. Can be run using docker-py. A docker target only need two variables: the binary to call within the docker container, and the docker container to use.

```
{  
    "arch": "*",
    "os": "*",
    "binary": "bin/test.py",
    "docker_image": "fastr/test"
}
```

```
<target os="*" arch="*" binary="bin/test.py" docker_image="fastr/test">
```

```
__abstractmethods__ = frozenset({})
```

```
__enter__()
```

Set the environment in such a way that the target will be on the path.

```
__exit__(exc_type, exc_value, traceback)
```

Cleanup the environment where needed

```
__init__(binary, docker_image)
```

Define a new docker target.

Parameters `docker_image (str)` – Docker image to use

```
__module__ = 'fastr.plugins'
```

```
property container
```

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python
```

```
module = <module 'dockertarget' from '/home/docs/checkouts/readthedocs.org/user_builds/
```

```
monitor_docker(container, resources)
```

Monitor a docker container and profile the cpu, memory and io use. Register the resource use every `_MONITOR_INTERVAL` seconds.

Parameters

- `container (ContainerCollection)` – process to monitor

- `resources (ProcessUsageCollection)` – list to append measurements to

```
run_command(command)
```

Run a command with the target

Return type `TargetResult`

```
class fastr.plugins.ElasticsearchReporter
```

Bases: `fastr.plugins.reportingplugin.ReportingPlugin`

```
__abstractmethods__ = frozenset({})
```

```
__init__()
```

The BasePlugin constructor.

Returns the created plugin

Return type `BasePlugin`

Raises `FastrPluginNotLoaded` – if the plugin did not load correctly

```
__module__ = 'fastr.plugins'
```

```
activate()
```

Activate the reporting plugin

```
configuration_fields = {'elasticsearch_debug': (<class 'bool'>, False, 'Setup elasticsearc
```

```
elasticsearch_update_status(job)
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python
job_updated(job)
module = <module 'elasticsearchreporter' from '/home/docs/checkouts/readthedocs.org/us
classmethod test()
Test the plugin, default behaviour is just to instantiate the plugin
```

class fastr.plugins.FastrInterface(*id_, document*)
 Bases: *fastr.core.interface.Interface*

The default Interface for fastr. For the command-line Tools as used by fastr. It build a commandline call based on the input/output specification.

The fields that can be set in the interface:

Attribute	Description
<i>id</i>	The id of this Tool (used internally in fastr)
inputs[]	List of Inputs that can are accepted by the Tool
	<i>id</i>
	<i>name</i>
	<i>datatype</i>
	<i>enum[]</i>
	<i>prefix</i>
	<i>cardinality</i>
	<i>repeat_prefix</i>
	<i>required</i>
	<i>nospace</i>
	<i>format</i>
	<i>default</i>
	<i>description</i>
outputs[]	List of Outputs that are generated by the Tool (and accessible to fastr)
	<i>id</i>
	<i>name</i>
	<i>datatype</i>

Continued on next page

Table 3.1 – continued from previous page

Attribute	Description
enum []	List of possible values for an EnumType (created on the fly by fastr) ¹
prefix	Commandline prefix of the Output (e.g. --out, -o)
cardinality	Cardinality of the Output
repeat_prefix	Flag indicating if for every value of the Output the prefix is repeated
required	Flag indicating if the input is required
nospace	Flag indicating if there is no space between prefix and value (e.g. --out=val)
format	For DataTypes that have multiple representations, indicate which one to use
description	Long description for an input
action	Special action (defined per DataType) that needs to be performed before creating output value (e.g. ‘ensure’ will make sure an output directory exists)
automatic	Indicate that output doesn’t require commandline argument, but is created automatically by a Tool ²
method	The collector plugin to use for the gathering automatic output, see the Collector plugins
location	Definition where to an automatically, usage depends on the method ²

```

__abstractmethods__ = frozenset({})

__dataschemafile__ = 'FastrInterface.schema.json'

__eq__(other)
    Return self==value.

__getstate__()
    Get the state of the FastrInterface object.

Returns state of interface

Return type dict

__hash__ = None

__init__(id_, document)
    The BasePlugin constructor.

```

¹ datatype and enum are conflicting entries, if both specified datatype has precedence² More details on defining automatica output are given in [TODO]

Returns the created plugin

Return type BasePlugin

Raises `FastrPluginNotLoaded` – if the plugin did not load correctly

```
__module__ = 'fastr.plugins'

__setstate__(state)
    Set the state of the Interface

check_input_id(id_)
    Check if an id for an object is valid and unused in the Tool. The method will always returns True if it does not raise an exception.

    Parameters id (str) – the id to check

    Returns True

    Raises
        • FastrValueError – if the id is not correctly formatted
        • FastrValueError – if the id is already in use

check_output_id(id_)
    Check if an id for an object is valid and unused in the Tool. The method will always returns True if it does not raise an exception.

    Parameters id (str) – the id to check

    Returns True

    Raises
        • FastrValueError – if the id is not correctly formatted
        • FastrValueError – if the id is already in use

static collect_errors(result)
    Special error collection for fastr interfaces

collect_results(result)
    Collect all results of the interface

collector_plugin_type
    alias of fastrinterface.CollectorPlugin

collectors = CollectorPluginManager [37m[42m[1mLoaded[0m json : <CollectorPlugin: Js
execute(target, payload)
    Execute the interface using a specific target and payload (containing a set of values for the arguments)

    Parameters
        • target (SampleId) – the target to use
        • payload (dict) – the values for the arguments

    Returns result of the execution

    Return type InterfaceResult

property expanding
    Indicates whether or not this Interface will result in multiple samples per run. If the flow is unaffected, this will be zero, if it is nonzero it means that number of dimension will be added to the sample array.

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python
```

get_arguments (*values*)

Get the argument list for this interface

Returns return list of arguments

get_command (*target, payload*)**get_specials** (*payload, output, cardinality_nr*)

Get special attributes. Returns tuples for specials, inputs and outputs that are used for formatting substitutions.

Parameters

- **output** – Output for which to get the specials

- **cardinality_nr** (*int*) – the cardinality number

property inputs

OrderedDict of Inputs connected to the Interface. The format should be {input_id: InputSpec}.

module = <module 'fastrinterface' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastrinterface.py'>

property outputs

OrderedDict of Output connected to the Interface. The format should be {output_id: OutputSpec}.

class fastr.plugins.FileSystem

Bases: *fastr.core.ioplugin.IOPlugin*

The FileSystem plugin is created to handle `file://` type or URLs. This is generally not a good practice, as this is not portable over between machines. However, for test purposes it might be useful.

The URL scheme is rather simple: `file://host/path` (see [wikipedia](#) for details)

We do not make use of the host part and at the moment only support localhost (just leave the host empty) leading to `file:/// URLs`.

Warning: This plugin ignores the hostname in the URL and does only accept driver letters on Windows in the form `c:/`

__abstractmethods__ = frozenset({})**__init__**()

Initialization for the IOPlugin

Returns newly created IOPlugin

__module__ = 'fastr.plugins'**fetch_url** (*inurl, outpath*)

Fetch the files from the file.

Parameters

- **inurl** – url to the item in the data store, starts with `file://`

- **outpath** – path where to store the fetch data locally

fetch_value (*inurl*)

Fetch a value from an external file file.

Parameters **inurl** – url of the value to read

Returns the fetched value

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastrinterface.py'

```
module = <module 'filesystem' from '/home/docs/checkouts/readthedocs.org/user_builds/f
path_to_url(path, mountpoint=None)
    Construct an url from a given mount point and a relative path to the mount point.
```

```
put_url(inpath, outurl)
    Put the files to the external data store.
```

Parameters

- **inpath** – path of the local data
- **outurl** – url to where to store the data, starts with `file://`

```
put_value(value, outurl)
    Put the value in the external data store.
```

Parameters

- **value** – value to store
- **outurl** – url to where to store the data, starts with `file://`

```
scheme = 'file'
```

```
url_to_path(url)
```

Get the path to a file from a url. Currently supports the `file://` scheme

Examples:

```
>>> 'file:///d:/data/project/file.ext'
'd:\data\project\file.ext'
```

Warning: `file://` will not function cross platform and is mainly for testing

```
class fastr.plugins.FlowInterface(id_, document)
    Bases: fastr.core.interface.Interface
```

The Interface use for AdvancedFlowNodes to create the advanced data flows that are not implemented in the fastr. This allows nodes to implement new data flows using the plugin system.

The definition of FlowInterfaces are very similar to the default FastrInterfaces.

Note: A flow interface should be using a specific FlowPlugin

```
__abstractmethods__ = frozenset({})
__dataschemafile__ = 'FastrInterface.schema.json'
__eq__(other)
    Return self==value.

__getstate__()
    Get the state of the FastrInterface object.

    Returns state of interface

    Return type dict

__hash__ = None
```

__init__(id_, document)

The BasePlugin constructor.

Returns the created plugin

Return type BasePlugin

Raises *FastrPluginNotLoaded* – if the plugin did not load correctly

__module__ = 'fastr.plugins'**__setstate__(state)**

Set the state of the Interface

execute(target, payload)

Execute the interface given the target and payload. The payload should have the form:

```
{  
    'input': {  
        'input_id_a': (value, value),  
        'input_id_b': (value, value)  
    },  
    'output': {  
        'output_id_a': (value, value),  
        'output_id_b': (value, value)  
    }  
}
```

Parameters

- **target** – the target to call
- **payload** – the payload to use

Returns the result of the execution

Return type (tuple of) *InterfaceResult*

property expanding

Indicates whether or not this Interface will result in multiple samples per run. If the flow is unaffected, this will be zero, if it is nonzero it means that number of dimension will be added to the sample array.

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python  
flow_plugin_type  
    alias of flowinterface.FlowPlugin  
flow_plugins = FlowPluginManager [37m[42m[1mLoaded[0m CrossValidation : <FlowPlugin:  
property inputs  
    OrderedDict of Inputs connected to the Interface. The format should be {input_id: InputSpec}.  
module = <module 'flowinterface' from '/home/docs/checkouts/readthedocs.org/user_build  
property outputs  
    OrderedDict of Output connected to the Interface. The format should be {output_id: OutputSpec}.  
class fastr.plugins.HTTPPPlugin  
Bases: fastr.core.ioplugin.IOPPlugin
```

Warning: This Plugin is still under development and has not been tested at all. example url: <https://server.io/path/to/resource>

```
__abstractmethods__ = frozenset({})
```

```
__init__()
```

Initialization for the IOPlugin

Returns newly created IOPlugin

```
__module__ = 'fastr.plugins'
```

```
fetch_url(inurl, outpath)
```

Download file from server.

Parameters

- **inurl** – url to the file.

- **outpath** – path to store file

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/IOPlugin.py
```

```
module = <module 'httpplugin' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/httpplugin.py'>
```

```
scheme = ('https', 'http')
```

```
class fastr.plugins.LinearExecution(finished_callback=None, cancelled_callback=None)
```

Bases: [fastr.plugins.executionplugin.ExecutionPlugin](#)

An execution engine that has a background thread that executes the jobs in order. The queue is a simple FIFO queue and there is one worker thread that operates in the background. This plugin is meant as a fallback when other plugins do not function properly. It does not multi-processing so it is safe to use in environments that do not support that.

```
__abstractmethods__ = frozenset({})
```

```
__init__(finished_callback=None, cancelled_callback=None)
```

Setup the ExecutionPlugin

Parameters

- **finished_callback** – the callback to call after a job finished

- **cancelled_callback** – the callback to call after a job cancelled

Returns newly created ExecutionPlugin

```
__module__ = 'fastr.plugins'
```

```
cleanup()
```

Method to call to clean up the ExecutionPlugin. This can be to clear temporary data, close connections, etc.

Parameters **force** – force cleanup (e.g. kill instead of join a process)

```
exec_worker()
```

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/LinearExecution.py
```

```
module = <module 'linearexecution' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/linearexecution.py'>
```

```
classmethod test()
```

Test the plugin, default behaviour is just to instantiate the plugin

```
class fastr.plugins.LocalBinaryTarget (binary, paths=None, environment_variables=None,
                                         initscripts=None, modules=None, interpreter=None,
                                         **kwargs)
Bases: fastr.core.target.SubprocessBasedTarget
```

A tool target that is a local binary on the system. Can be found using environmentmodules or a path on the executing machine. A local binary target has a number of fields that can be supplied:

- **binary** (required): the name of the binary/script to call, can also be called `bin` for backwards compatibility.
- **modules**: list of modules to load, this can be environmentmodules or lmod modules. If modules are given, the paths, environment_variables and initscripts are ignored.
- **paths**: a list of paths to add following the structure `{ "value": "/path/to/dir", "type": "bin" }`. The types can be `bin` if it should be added to \$PATH or `lib` if it should be added to the library path (e.g. \$LD_LIBRARY_PATH for linux).
- **environment_variables**: a dictionary of environment variables to set.
- **initscript**: a list of script to run before running the main tool
- **interpreter**: the interpreter to use to call the binary e.g. `python`

The LocalBinaryTarget will first check if there are modules given and the module subsystem is loaded. If that is the case it will simply unload all current modules and load the given modules. If not it will try to set up the environment itself by using the following steps:

1. Prepend the bin paths to \$PATH
2. Prepend the lib paths to the correct environment variable
3. Setting the other environment variables given (\$PATH and the system library path are ignored and cannot be set that way)
4. Call the initscripts one by one

The definition of the target in JSON is very straightforward:

```
{
  "binary": "bin/test.py",
  "interpreter": "python",
  "paths": [
    {
      "type": "bin",
      "value": "vfs://apps/test/bin"
    },
    {
      "type": "lib",
      "value": "./lib"
    }
  ],
  "environment_variables": {
    "othervar": 42,
    "short_var": 1,
    "testvar": "value1"
  },
  "initscripts": [
    "bin/init.sh"
  ],
  "modules": ["elastix/4.8"]
}
```

In XML the definition would be in the form of:

```
<target os="linux" arch="*" modules="elastix/4.8" bin="bin/test.py" interpreter=
    ↪"python">
  <paths>
    <path type="bin" value="vfs://apps/test/bin" />
    <path type="lib" value=".lib" />
  </paths>
  <environment_variables short_var="1">
    <testvar>value1</testvar>
    <othervar>42</othervar>
  </environment_variables>
  <initscripts>
    <initscript>bin/init.sh</initscript>
  </initscripts>
</target>
```

```
DYNAMIC_LIBRARY_PATH_DICT = {'darwin': 'DYLD_LIBRARY_PATH', 'linux': 'LD_LIBRARY_PATH'}
__abstractmethods__ = frozenset({})

__enter__()
    Set the environment in such a way that the target will be on the path.

__exit__(exc_type, exc_value, traceback)
    Cleanup the environment

__init__(binary, paths=None, environment_variables=None, initscripts=None, modules=None, interpreter=None, **kwargs)
    Define a new local binary target. Must be defined either using paths and optionally environment_variables and initscripts, or enviroment modules.

__module__ = 'fastr.plugins'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python'
module = <module 'localbinarytarget' from '/home/docs/checkouts/readthedocs.org/user_b
property paths

run_command(command)
    Run a command with the target
```

Return type `TargetResult`

```
class fastr.plugins.MacroTarget(network_file, method=None, function='main')
Bases: fastr.core.target.Target
```

A target for MacroNodes. This target cannot be executed as the MacroNode handles execution differently. But this contains the information for the MacroNode to find the internal Network.

```
__abstractmethods__ = frozenset({})

__init__(network_file, method=None, function='main')
    Define a new local binary target. Must be defined either using paths and optionally environment_variables and initscripts, or enviroment modules.

__module__ = 'fastr.plugins'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python'
module = <module 'macrotarget' from '/home/docs/checkouts/readthedocs.org/user_buil
```

run_command(*command*)

Run a command with the target

classmethod test()

Test if singularity is available on the path

class fastr.plugins.NipypeInterface(*id_*, *nipype_cls=None*, *document=None*)

Bases: *fastr.core.interface.Interface*

Experimental interfaces to using nipype interfaces directly in fastr tools, only using a simple reference.

To create a tool using a nipype interface just create an interface with the correct type and set the nipype argument to the correct class. For example in an xml tool this would become:

```
<interface class="NipypeInterface">
    <nipype_class>nipype.interfaces.elastix.Registration</nipype_class>
</interface>
```

Note: To use these interfaces nipype should be installed on the system.

Warning: This interface plugin is basically functional, but highly experimental!

__abstractmethods__ = frozenset({})**__eq__(other)**

Return self==value.

__getstate__()

Retrieve the state of the Interface

Returns the state of the object

Rtype dict

__hash__ = None**__init__(*id_*, *nipype_cls=None*, *document=None*)**

The BasePlugin constructor.

Returns the created plugin

Return type BasePlugin

Raises *FastrPluginNotLoaded* – if the plugin did not load correctly

__module__ = 'fastr.plugins'**__setstate__(*state*)**

Set the state of the Interface

execute(*target*, *payload*)

Execute the interface using a specific target and payload (containing a set of values for the arguments)

Parameters

- **target** (*SampleId*) – the target to use
- **payload** (*dict*) – the values for the arguments

Returns result of the execution

Return type *InterfaceResult*

property expanding

Indicates whether or not this Interface will result in multiple samples per run. If the flow is unaffected, this will be zero, if it is nonzero it means that number of dimension will be added to the sample array.

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/_base.py:103'
```

get_type (trait)

property inputs

OrderedDict of Inputs connected to the Interface. The format should be {input_id: InputSpec}.

```
module = <module 'nipypeinterface' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/_base.py:103'>
```

property outputs

OrderedDict of Output connected to the Interface. The format should be {output_id: OutputSpec}.

classmethod test()

Test the plugin, interfaces do not need to be tested on import

```
class fastr.plugins.Null
```

Bases: *fastr.core.ioplugin.IOPlugin*

The Null plugin is created to handle null:// type or URLs. These URLs are indicating the sink should not do anything. The data is not written to anywhere. Besides the scheme, the rest of the URL is ignored.

```
__abstractmethods__ = frozenset({})
```

__init__()

Initialization for the IOPlugin

Returns newly created IOPlugin

```
__module__ = 'fastr.plugins'
```

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/null.py:11'
```

```
module = <module 'null' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/null.py:11'>
```

put_url (inpath, outurl)

Put the files to the external data store.

Parameters

- **inpath** – path of the local data
- **outurl** – url to where to store the data, starts with file://

put_value (value, outurl)

Put the value in the external data store.

Parameters

- **value** – value to store
- **outurl** – url to where to store the data, starts with file://

```
scheme = 'null'
```

```
class fastr.plugins.PimReporter
```

Bases: *fastr.plugins.reportingplugin.ReportingPlugin*

```
SUPPORTED_APIS = {2: <class 'pimreporter.PimAPIv2'>}
```

```
__abstractmethods__ = frozenset({})
```

```
__init__()
    The BasePlugin constructor.

        Returns the created plugin

        Return type BasePlugin

        Raises FastrPluginNotLoaded – if the plugin did not load correctly

__module__ = 'fastr.plugins'

activate()
    Activate the reporting plugin

configuration_fields = {'pim_batch_size': (<class 'int'>, 100, 'Maximum number of job'}
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/pimreporter.py'
job_updated(job)
log_record_emitted(record)
module = <module 'pimreporter' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/pimreporter.py'>
run_finished(run)
run_started(run)

class fastr.plugins.ProcessPoolExecution(finished_callback=None, cancelled_callback=None, nr_of_workers=None)
    can-
    celled_callback=None, nr_of_workers=None)
Bases: fastr.plugins.executionplugin.ExecutionPlugin
```

A local execution plugin that uses multiprocessing to create a pool of worker processes. This allows fastr to execute jobs in parallel with true concurrency. The number of workers can be specified in the fastr configuration, but the default amount is the number of cores - 1 with a minimum of 1.

Warning: The ProcessPoolExecution does not check memory requirements of jobs and running many workers might lead to memory starvation and thus an unresponsive system.

```
__abstractmethods__ = frozenset({})
__init__(finished_callback=None, cancelled_callback=None, nr_of_workers=None)
    Setup the ExecutionPlugin
```

Parameters

- **finished_callback** – the callback to call after a job finished
- **cancelled_callback** – the callback to call after a job cancelled

Returns newly created ExecutionPlugin

```
__module__ = 'fastr.plugins'
```

```
cleanup()
```

Method to call to clean up the ExecutionPlugin. This can be to clear temporary data, close connections, etc.

Parameters **force** – force cleanup (e.g. kill instead of join a process)

```
configuration_fields = {'process_pool_worker_number': (<class 'int'>, 3, 'Number of workers')
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/processpoolexecution.py'
```

job_finished_callback(result)

Reciever for the callback, it will split the result tuple and call job_finished

Parameters `result` (`tuple`) – return value of run_job

```
module = <module 'processpoolexecution' from '/home/docs/checkouts/readthedocs.org/user
```

classmethod test()

Test the plugin, default behaviour is just to instantiate the plugin

```
class fastr.plugins.RQExecution(finished_callback=None, cancelled_callback=None)
```

Bases: `fastr.plugins.executionplugin.ExecutionPlugin`

A execution plugin based on Redis Queue. Fastr will submit jobs to the redis queue and workers will peel the jobs from the queue and process them.

This system requires a running redis database and the database url has to be set in the fastr configuration.

Note: This execution plugin required the `redis` and `rq` packages to be installed before it can be loaded properly.

```
__abstractmethods__ = frozenset({})
```

```
__init__(finished_callback=None, cancelled_callback=None)
```

Setup the ExecutionPlugin

Parameters

- `finished_callback` – the callback to call after a job finished
- `cancelled_callback` – the callback to call after a job cancelled

Returns newly created ExecutionPlugin

```
__module__ = 'fastr.plugins'
```

```
check_finished()
```

```
cleanup()
```

Method to call to clean up the ExecutionPlugin. This can be to clear temporary data, close connections, etc.

Parameters `force` – force cleanup (e.g. kill instead of join a process)

```
configuration_fields = {'rq_host': (<class 'str'>, 'redis://localhost:6379/0', 'The u
```

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/pytho
```

```
module = <module 'rqexecution' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/
```

```
classmethod run_job(job_id, job_command, job_stdout, job_stderr)
```

classmethod test()

Test the plugin, default behaviour is just to instantiate the plugin

```
class fastr.plugins.Reference
```

Bases: `fastr.core.ioplugin.IOPlugin`

The Reference plugin is create to handle `ref://` type or URLs. These URLs are to make the sink just write a simple reference file to the data. The reference file contains the DataType and the value so the result can be reconstructed. It for files just leaves the data on disk by reference. This plugin is not useful for production, but is used for testing purposes.

```
__abstractmethods__ = frozenset({})
```

```
__init__()
    Initialization for the IOPlugin

    Returns newly created IOPlugin

_module_ = 'fastr.plugins'
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/S3Filesystem.py'
module = <module 'reference' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/S3Filesystem.py'>
push_sink_data(value, outurl, datatype=None)
    Write out the sink data from the inpath to the outurl.
```

Parameters

- **value** (*str*) – the path of the data to be pushed
- **outurl** (*str*) – the url to write the data to
- **datatype** (*DataType*) – the datatype of the data, used for determining the total contents of the transfer

Returns None

```
scheme = 'ref'

class fastr.plugins.S3Filesystem
    Bases: fastr.core.ioplugin.IOPlugin
```

Warning: As this IOPlugin is under development, it has not been thoroughly tested.

example url: s3://bucket.server/path/to/resource

```
__abstractmethods__ = frozenset({})
__init__()
    Initialization for the IOPlugin

    Returns newly created IOPlugin

_module_ = 'fastr.plugins'
cleanup()
    (abstract) Clean up the IOPlugin. This is to do things like closing files or connections. Will be called when the plugin is no longer required.
```

```
expand_url(url)
    Expand an S3 URL. This allows a source to collect multiple samples from a single url.
```

Parameters **url** (*str*) – url to expand

Returns the resulting url(s), a tuple if multiple, otherwise a str

Return type *str* or tuple of *str*

```
fetch_url(inurl, outpath)
    Get the file(s) or values from s3.
```

Parameters

- **inurl** – url to the item in the data store
- **outpath** – path where to store the fetch data locally

```
fetch_value(inurl)
Fetch a value from S3

    Parameters inurl – url of the value to read

    Returns the fetched value

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.11/site-packages/fastr/plugins/s3filestorage.py'
module = <module 's3filesystem' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.11/site-packages/fastr/plugins/s3filestorage.py'>
put_url(inpath, outurl)
Upload the files to the S3 storage

    Parameters

        • inpath – path to the local data

        • outurl – url to where to store the data in the external data store.

put_value(value, outurl)
Put the value in S3

    Parameters

        • value – value to store

        • outurl – url to where to store the data, starts with file://

scheme = ('s3', 's3list')

classmethod test()
Test the plugin, default behaviour is just to instantiate the plugin

class fastr.plugins.SimpleReport
Bases: fastr.plugins.reportingplugin.ReportingPlugin

    __abstractmethods__ = frozenset({})

    __module__ = 'fastr.plugins'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.11/site-packages/fastr/plugins/simplereport.py'
module = <module 'simplereport' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.11/site-packages/fastr/plugins/simplereport.py'>
run_finished(run)

class fastr.plugins.SingularityTarget(binary, container, interpreter=None)
Bases: fastr.core.target.SubprocessBasedTarget

A tool target that is run using a singularity container, see the singularity website

    • binary (required): the name of the binary/script to call, can also be called bin for backwards compatibility.

    • container (required): the singularity container to run, this can be in url form for singularity
        pull or as a path to a local container

    • interpreter: the interpreter to use to call the binary e.g. python

SINGULARITY_BIN = 'singularity'

    __abstractmethods__ = frozenset({})

    __enter__()
        Set the environment in such a way that the target will be on the path.
```

```
__exit__(exc_type, exc_value, traceback)
    Cleanup the environment

__init__(binary, container, interpreter=None)
    Define a new local binary target. Must be defined either using paths and optionally environment_variables
    and initscripts, or enviroment modules.

__module__ = 'fastr.plugins'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/slurm_execution.py'
module = <module 'singularitytarget' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/slurm_execution.py'>
run_command(command)
    Run a command with the target

classmethod test()
    Test if singularity is available on the path

class fastr.plugins.SlurmExecution(finished_callback=None, cancelled_callback=None)
    Bases: fastr.plugins.executionplugin.ExecutionPlugin

    SBATCH = 'sbatch'
    SCANCEL = 'scancel'
    SCONTROL = 'scontrol'
    SQUEUE = 'squeue'
    SQUEUE_FORMAT = '{"id": %18i, "status": "%.2t"}'
    STATUS_MAPPING = {'F': <JobState.failed: ('failed', 'done', True)>, 'R': <JobState.running: ('running', False)>}
    SUPPORTS_CANCEL = True
    SUPPORTS_DEPENDENCY = True
    SUPPORTS_HOLD_RELEASE = True
    __abstractmethods__ = frozenset({})

    __init__(finished_callback=None, cancelled_callback=None)
        Setup the ExecutionPlugin

            Parameters
                • finished_callback – the callback to call after a job finished
                • cancelled_callback – the callback to call after a job cancelled

            Returns newly created ExecutionPlugin

__module__ = 'fastr.plugins'

cleanup()
    Method to call to clean up the ExecutionPlugin. This can be to clear temporary data, close connections,
    etc.

    Parameters force – force cleanup (e.g. kill instead of join a process)

configuration_fields = {'slurm_job_check_interval': (<class 'int'>, 30, 'The interval between checks for job status')}
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/slurm_execution.py'
job_status_check()

module = <module 'slurmexecution' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/slurm_execution.py'>
```

```
classmethod test()
    Test the plugin, default behaviour is just to instantiate the plugin

class fastr.plugins.StrongrExecution(finished_callback=None, cancelled_callback=None)
    Bases: fastr.plugins.executionplugin.ExecutionPlugin

A execution plugin based on Redis Queue. Fastr will submit jobs to the redis queue and workers will poll the
jobs from the queue and process them.

This system requires a running redis database and the database url has to be set in the fastr configuration.
```

Note: This execution plugin required the `redis` and `rq` packages to be installed before it can be loaded properly.

```
__abstractmethods__ = frozenset({})
__init__(finished_callback=None, cancelled_callback=None)
    Setup the ExecutionPlugin

    Parameters
        • finished_callback – the callback to call after a job finished
        • cancelled_callback – the callback to call after a job cancelled

    Returns newly created ExecutionPlugin

__module__ = 'fastr.plugins'
check_finished()
cleanup()
    Method to call to clean up the ExecutionPlugin. This can be to clear temporary data, close connections,
    etc.

    Parameters force – force cleanup (e.g. kill instead of join a process)

configuration_fields = {}
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/executionplugin.py'
module = <module 'strongreexecution' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/executionplugin.py'>
classmethod test()
    Test the plugin, default behaviour is just to instantiate the plugin

class fastr.plugins.VirtualFileSystem
    Bases: fastr.core.vfs.VirtualFileSystem, fastr.core.ioplugin.IOPlugin
```

The virtual file system class. This is an IOPlugin, but also heavily used internally in fastr for working with directories. The VirtualFileSystem uses the `vfs://` url scheme.

A typical virtual filesystem url is formatted as `vfs://mountpoint/relative/dir/from/mount.ext`

Where the `mountpoint` is defined in the [Config file](#). A list of the currently known mountpoints can be found in the `fastr.config` object

```
>>> fastr.config.mounts
{'example_data': '/home/username/fastr-feature-documentation/fastr/fastr/examples/
˓→data',
 'home': '/home/username/',
 'tmp': '/home/username/FastrTemp'}
```

This shows that a url with the mount home such as `vfs://home/tempdir/testfile.txt` would be translated into `/home/username/tempdir/testfile.txt`.

There are a few default mount points defined by Fastr (that can be changed via the config file).

mountpoint	default location
home	the users home directory (<code>expanduser('~/')</code>)
tmp	the fastr temporary dir, defaults to <code>tempfile.gettempdir()</code>
example_data	the fastr example data directory, defaults <code>\$FASTRDIR/example/data</code>

```
__abstractmethods__ = frozenset({})

__module__ = 'fastr.plugins'

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/virtualfilesystem.py'
module = <module 'virtualfilesystem' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/virtualfilesystem.py'>
scheme = 'vfs'

class fastr.plugins.VirtualFileSystemRegularExpression
Bases: fastr.core.ioplugin.IOPlugin
```

The `VirtualFileSystemValueList` is an expand-only type of `IOPlugin`. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs.

A `vfsexpr://` URL is a `vfsexpr://` URL that can contain regular expressions on every level of the path. The regular expressions follow the `re module` definitions.

An example of a valid URLs would be:

```
vfsexpr://tmp/network_dir/.*/*/__fastr_result__.pickle.gz
vfsexpr://tmp/network_dir/nodeX/(?P<id>.*)/__fastr_result__.pickle.gz
```

The first URL would result in all the `__fastr_result__.pickle.gz` in the working directory of a Network. The second URL would only result in the file for a specific node (nodeX), but by adding the named group `id` using `(?P<id>.*)` the sample id of the data is automatically set to that group (see [Regular Expression Syntax](#) under the special characters for more info on named groups in regular expression).

Concretely if we would have a directory `vfsexpr://mount/somedir` containing:

```
image_1/Image.nii
image_2/image.nii
image_3/anotherimage.nii
image_5/inconsistentnamingftw.nii
```

we could match these files using `vfsexpr://mount/somedir/(?P<id>image_\d+)/.*\.nii` which would result in the following source data after expanding the URL:

```
{'image_1': 'vfsexpr://mount/somedir/image_1/Image.nii',
'image_2': 'vfsexpr://mount/somedir/image_2/image.nii',
'image_3': 'vfsexpr://mount/somedir/image_3/anotherimage.nii',
'image_5': 'vfsexpr://mount/somedir/image_5/inconsistentnamingftw.nii'}
```

Showing the power of this regular expression filtering. Also it shows how the ID group from the URL can be used to have sensible sample ids.

Warning: due to the nature of regexp on multiple levels, this method can be slow when having many matches on the lower level of the path (because the tree of potential matches grows) or when directories that are parts of the path are very large.

```
__abstractmethods__ = frozenset({})

__init__()
    Initialization for the IOPlugin

    Returns newly created IOPlugin

__module__ = 'fastr.plugins'

expand_url(url)
    (abstract) Expand an URL. This allows a source to collect multiple samples from a single url. The URL will have a wildcard or point to something with info and multiple urls will be returned.

    Parameters url (str) – url to expand

    Returns the resulting url(s), a tuple if multiple, otherwise a str

    Return type str or tuple of str

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/VirtualFileSystemValueList.py'
module = <module 'virtualfilesystemregularexpression' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/_vfsexpr.py'>
scheme = 'vfsregex'

class fastr.plugins.VirtualFileSystemValueList
Bases: fastr.core.ioplugin.IOPlugin
```

The VirtualFileSystemValueList is an expand-only type of IOPlugin. No URLs can actually be fetched, but it can expand a single URL into a larger amount of URLs. A vfslist:// URL basically is a url that points to a file using vfs. This file then contains a number lines each containing another URL.

If the contents of a file vfs://mount/some/path/contents would be:

```
vfs://mount/some/path/file1.txt
vfs://mount/some/path/file2.txt
vfs://mount/some/path/file3.txt
vfs://mount/some/path/file4.txt
```

Then using the URL vfslist://mount/some/path/contents as source data would result in the four files being pulled.

Note: The URLs in a vfslist file do not have to use the vfs scheme, but can use any scheme known to the Fastr system.

```
__abstractmethods__ = frozenset({})

__init__()
    Initialization for the IOPlugin

    Returns newly created IOPlugin

__module__ = 'fastr.plugins'

expand_url(url)
    (abstract) Expand an URL. This allows a source to collect multiple samples from a single url. The URL will have a wildcard or point to something with info and multiple urls will be returned.
```

Parameters `url (str)` – url to expand

Returns the resulting url(s), a tuple if multiple, otherwise a str

Return type str or tuple of str

```
filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/XNATStorage.py'
module = <module 'virtualfilesystemvalue' from '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python3.6/site-packages/fastr/plugins/XNATStorage.py'>
scheme = 'vfslist'

class fastr.plugins.XNATStorage(IOPPlugin):
    Bases: fastr.core.ioplugin.IOPPlugin
```

Warning: As this IOPlugin is under development, it has not been thoroughly tested.

The XNATStorage plugin is an IOPlugin that can download data from and upload data to an XNAT server. It uses its own `xnat://` URL scheme. This is a scheme specific for this plugin and though it looks somewhat like the XNAT rest interface, a different type of URL.

Data resources can be accessed directly by a data url:

```
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/
  ↳experiments/experiment001/scans/T1/resources/DICOM
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/
  ↳experiments/*_BRAIN/scans/T1/resources/DICOM
```

In the second URL you can see a wildcard being used. This is possible at long as it resolves to exactly one item.

The `id` query element will change the field from the default experiment to subject and the `label` query element sets the use of the label as the fastr id (instead of the XNAT id) to True (the default is False)

To disable https transport and use http instead the query string can be modified to add `insecure=true`. This will make the plugin send requests over http:

```
xnat://xnat.example.com/data/archive/projects/sandbox/subjects/subject001/
  ↳experiments/*_BRAIN/scans/T1/resources/DICOM?insecure=true
```

For sinks it is important to know where to save the data. Sometimes you want to save data in a new assessor/resource and it needs to be created. To allow the Fastr sink to create an object in XNAT, you have to supply the type as a query parameter:

```
xnat://xnat.bmia.nl/data/archive/projects/sandbox/subjects/S01/experiments/_BRAIN/
  ↳assessors/test_assessor/resources/IMAGE/files/image.nii.gz?resource_
  ↳type=xnat:resourceCatalog&assessor_type=xnat:qcAssessmentData
```

Valid options are: `subject_type`, `experiment_type`, `assessor_type`, `scan_type`, and `resource_type`.

If you want to do a search where multiple resources are returned, it is possible to use a search url:

```
xnat://xnat.example.com/search?projects=sandbox&subjects=subject [0-9] [0-9] [0-9] &
  ↳experiments=*_BRAIN&scans=T1&resources=DICOM
```

This will return all DICOMs for the T1 scans for experiments that end with _BRAIN that belong to a subject XXX where XXX is a 3 digit number. By default the ID for the samples will be the experiment XNAT ID (e.g. XNAT_E00123). The wildcards that can be used are the same UNIX shell-style wildcards as provided by the module `fnmatch`.

It is possible to change the id to a different fields id or label. Valid fields are project, subject, experiment, scan, and resource:

```
xnat://xnat.example.com/search?projects=sandbox&subjects=subject[0-9][0-9][0-9]&
 ↵experiments=*_BRAIN&scans=T1&resources=DICOM&id=subject&label=true
```

The following variables can be set in the search query:

variable	default	usage
projects	*	The project(s) to select, can contain wildcards (see <code>fnmatch</code>)
subjects	*	The subject(s) to select, can contain wildcards (see <code>fnmatch</code>)
experi- ments	*	The experiment(s) to select, can contain wildcards (see <code>fnmatch</code>)
scans	*	The scan(s) to select, can contain wildcards (see <code>fnmatch</code>)
resources	*	The resource(s) to select, can contain wildcards (see <code>fnmatch</code>)
id	experiment	What field to use as the id, can be: project, subject, experiment, scan, or resource
label	false	Indicate the XNAT label should be used as fastr id, options true or false
insecure	false	Change the url scheme to be used to http instead of https
verify	true	(Dis)able the verification of SSL certificates
regex	false	Change search to use regex <code>re.match()</code> instead of fnmatch for matching
overwrite	false	Tell XNAT to overwrite existing files if a file with the name is already present

For storing credentials the `.netrc` file can be used. This is a common way to store credentials on UNIX systems. It is required that the file is only accessible by the owner only or a `NetrcParseError` will be raised. A `netrc` file is really easy to create, as its entries look like:

```
machine xnat.example.com
  login username
  password secret123
```

See the `netrc` module or the [GNU inet utils website](#) for more information about the `.netrc` file.

Note: On windows the location of the `netrc` file is assumed to be `os.path.expanduser('~/_.netrc')`. The leading underscore is because windows does not like filename starting with a dot.

Note: For scan the label will be the scan type (this is initially the same as the series description, but can be updated manually or the XNAT scan type cleanup).

Warning: labels in XNAT are not guaranteed to be unique, so be careful when using them as the sample ID.

For background on XNAT, see the [XNAT API DIRECTORY](#) for the REST API of XNAT.

```
__abstractmethods__ = frozenset({})

__init__()
    Initialization for the IOPlugin

    Returns newly created IOPlugin

__module__ = 'fastr.plugins'
```

```
cleanup()
    (abstract) Clean up the IOPlugin. This is to do things like closing files or connections. Will be called
    when the plugin is no longer required.

connect(server, path='', insecure=False, verify=True)

expand_url(url)
    (abstract) Expand an URL. This allows a source to collect multiple samples from a single url. The
    URL will have a wildcard or point to something with info and multiple urls will be returned.

        Parameters url(str) – url to expand

        Returns the resulting url(s), a tuple if multiple, otherwise a str

        Return type str or tuple of str

fetch_url(inurl, outpath)
    Get the file(s) or values from XNAT.

        Parameters

            • inurl – url to the item in the data store

            • outpath – path where to store the fetch data locally

filename = '/home/docs/checkouts/readthedocs.org/user_builds/fastr/envs/3.1.2/lib/python
module = <module 'xnatstorage' from '/home/docs/checkouts/readthedocs.org/user_builds/
parse_uri(url)

put_url(inpath, outurl)
    Upload the files to the XNAT storage

        Parameters

            • inpath – path to the local data

            • outurl – url to where to store the data in the external data store.

scheme = ('xnat', 'xnat+http', 'xnat+https')

property server
static upload(resource, in_path, location, retries=3, overwrite=False)

property xnat

fastr.plugins.json
    alias of fastr.plugins.JsonCollector

fastr.plugins.path
    alias of fastr.plugins.PathCollector

fastr.plugins.stdout
    alias of fastr.plugins.StdoutCollector
```

executionplugin Module

```
class fastr.plugins.executionplugin.ExecutionPlugin(finished_callback=None,    can-
                                         celled_callback=None)
Bases: fastr.abc.baseplugin.Plugin
```

This class is the base for all Plugins to execute jobs somewhere. There are many methods already in place for taking care of stuff.

There are fall-backs for certain features, but if a system already implements those it is usually preferred to skip the fall-back and let the external system handle it. There are a few flags to enable disable these features:

- `cls.SUPPORTS_CANCEL` indicates that the plugin can cancel queued jobs
- `cls.SUPPORTS_HOLD_RELEASE` indicates that the plugin can queue jobs in a hold state and can release them again (if not, the base plugin will create a hidden queue for held jobs). The plugin should respect the `Job.status == JobState.hold` when queueing jobs.
- `cls.SUPPORTS_DEPENDENCY` indicate that the plugin can manage job dependencies, if not the base plugin job dependency system will be used and jobs with only be submitted when all dependencies are met.
- `cls.CANCELS_DEPENDENCIES` indicates that if a job is cancelled it will automatically cancel all jobs depending on that job. If not the plugin traverse the dependency graph and kill each job manual.

Note: If a plugin supports dependencies it is assumed that when a job gets cancelled, the depending job also get cancelled automatically!

Most plugins should only need to redefine a few abstract methods:

- `__init__` the constructor
- `cleanup` a clean up function that frees resources, closes connections, etc
- `_queue_job` the method that queues the job for execution

Optionally an extra job finished callback could be added:

- `_job_finished` extra callback for when a job finishes

If `SUPPORTS_CANCEL` is set to True, the plugin should also implement:

- `_cancel_job` cancels a previously queued job

If `SUPPORTS_HOLD_RELEASE` is set to True, the plugin should also implement:

- `_hold_job` hold_job a job that is currently held
- `_release_job` releases a job that is currently held

If `SUPPORTED_DEPENDENCY` is set to True, the plugin should:

- Make sure to use the `Job.hold_jobs` as a list of its dependencies

Not all of the functions need to actually do anything for a plugin. There are examples of plugins that do not really need a `cleanup`, but for safety you need to implement it. Just using a `pass` for the method could be fine in such a case.

Warning: When overwriting other functions, extreme care must be taken not to break the plugins working, as there is a lot of bookkeeping that can go wrong.

`CANCELS_DEPENDENCIES = False`

Indicates that when a job is cancelled the dependencies

`SUPPORTS_CANCEL = False`

Indicates if the plugin can cancel queued jobs

`SUPPORTS_DEPENDENCY = False`

Indicate if the plugin can manage job dependencies, if not the base plugin job dependency system will be used and jobs with only be submitted when all dependencies are met.

SUPPORTS_HOLD_RELEASE = False

Indicates if the plugin can queue jobs in a hold state and can release them again (if not, the base plugin will create a hidden queue for held jobs)

__abstractmethods__ = frozenset({'__init__', '__queue_job', 'cleanup'})**__del__()**

Cleanup if the variable was deleted on purpose

__enter__()**__exit__(type_, value, tb)****abstract __init__(finished_callback=None, cancelled_callback=None)**

Setup the ExecutionPlugin

Parameters

- **finished_callback** – the callback to call after a job finished
- **cancelled_callback** – the callback to call after a job cancelled

Returns newly created ExecutionPlugin

__module__ = 'fastr.plugins.executionplugin'**cancel_job(job)**

Cancel a job previously queued

Parameters job – job to cancel**check_job_requirements(job_id)**

Check if the requirements for a job are fulfilled.

Parameters job_id – job to check

Returns directive what should happen with the job

Return type *JobAction***check_job_status(job_id)**

Get the status of a specified job

Parameters job_id – the target job

Returns the status of the job (or None if job not found)

clean_free_jobs(job)**abstract cleanup()**

Method to call to clean up the ExecutionPlugin. This can be to clear temporary data, close connections, etc.

Parameters force – force cleanup (e.g. kill instead of join a process)**get_job(job_id)****get_status(job)****hold_job(job)****job_finished(job, errors=None, blocking=False)**

The default callback that is called when a Job finishes. This will create a new thread that handles the actual callback.

Parameters

- **job** ([Job](#)) – the job that finished

- **errors** – optional list of errors encountered
- **blocking** (`bool`) – if blocking, do not create threads

Returns

```
process_callbacks()
queue_job(job)
    Add a job to the execution queue
        Parameters job (Job) – job to add
```

```
register_job(job)
```

```
release_job(job)
    Release a job that has been put on hold
```

Parameters `job` – job to release

```
show_jobs(req_status=None)
```

 List the queued jobs, possible filtered by status

Parameters `req_status` – requested status to filter on

Returns list of jobs

```
signal_dependent_jobs(job_id)
```

 Check all depedent jobs and process them if all their dependencies are met. :param job_id: :return:

```
class fastr.plugins.executionplugin.JobAction
```

Bases: `enum.Enum`

Job actions that can be performed. This is used for checking if held jobs should be queued, held longer or be cancelled.

```
__module__ = 'fastr.plugins.executionplugin'
cancel = 'cancel'
hold = 'hold'
queue = 'queue'
```

reportingplugin Module

```
class fastr.plugins.reportingplugin.ReportingPlugin
```

Bases: `fastr.abc.baseplugin.Plugin`

Base class for all reporting plugins. The plugin has a number of methods that can be implemented that will be called on certain events. On these events the plugin can inspect the presented data and take reporting actions.

```
__abstractmethods__ = frozenset({})
__module__ = 'fastr.plugins.reportingplugin'
activate()
deactivate()
job_updated(job)
log_record_emitted(record)
run_finished(run)
```

```
run_started(run)
```

Subpackages

managers Package

managers Package

executionpluginmanager Module

This module holds the ExecutionPluginManager as well as the base-class for all ExecutionPlugins.

```
class fastr.plugins.managers.executionpluginmanager.ExecutionPluginManager(parent)
Bases: fastr.plugins.managers.pluginmanager.PluginSubManager
```

Container holding all the ExecutionPlugins known to the Fastr system

```
__abstractmethods__ = frozenset({})
```

```
__init__(parent)
```

Initialize a ExecutionPluginManager and load plugins.

Parameters

- **path** – path to search for plugins
- **recursive** – flag for searching recursively

Returns newly created ExecutionPluginManager

```
__module__ = 'fastr.plugins.managers.executionpluginmanager'
```

interfacemanager Module

This module holds the ExecutionPluginManager as well as the base-class for all ExecutionPlugins.

```
class fastr.plugins.managers.interfacemanager.InterfacePluginManager(parent)
Bases: fastr.plugins.managers.pluginmanager.PluginSubManager
```

Container holding all the CollectorPlugins

```
__abstractmethods__ = frozenset({})
```

```
__init__(parent)
```

Create the Coll :param path: :param recursive: :return:

```
__module__ = 'fastr.plugins.managers.interfacemanager'
```

iopluginmanager Module

```
class fastr.plugins.managers.iopluginmanager.IOPPluginManager(parent)
Bases: fastr.plugins.managers.pluginmanager.PluginSubManager
```

A mapping containing the IOPlugins known to this system

```
__abstractmethods__ = frozenset({})
```

`__init__(parent)`
Create the IOPluginManager and populate it.

Returns newly created IOPluginManager

`__iter__()`
Get an iterator from the BaseManager. The iterator will iterate over the keys of the BaseManager.

Returns the iterator

Return type dictionary-keyiterator

`__keytransform__(key)`
Identity transform for the keys. This function can be reimplemented by a subclass to implement a different key transform.

Parameters `key` – key to transform

Returns the transformed key (in this case the same key as inputted)

`_module_ = 'fastr.plugins.managers.iopluginmanager'`

`cleanup()`
Cleanup all plugins, this closes files, connections and other things that could be left dangling otherwise.

`static create_ioplugin_tool(tools, interfaces)`
Create the tools which handles sinks and sources. The command of this tool is the main of core.ioplugin.

`expand_url(url)`
Expand the url by filling the wildcards. This function checks the url scheme and uses the expand function of the correct IOPlugin.

Parameters `url (str)` – url to expand

Returns list of urls

Return type list of str

`pull_source_data(url, outdir, sample_id, datatype=None)`
Retrieve data from an external source. This function checks the url scheme and selects the correct IOPlugin to retrieve the data.

Parameters

- `url` – url to pull
- `outdir (str)` – the directory to write the data to
- `datatype (DataType)` – the datatype of the data, used for determining the total contents of the transfer

Returns None

`push_sink_data(inpath, outurl, datatype=None)`
Send data to an external source. This function checks the url scheme and selects the correct IOPlugin to retrieve the data.

Parameters

- `inpath (str)` – the path of the data to be pushed
- `outurl (str)` – the url to write the data to
- `datatype (DataType)` – the datatype of the data, used for determining the total contents of the transfer

`put_url (inpath, outurl)`

Put the files to the external data store.

Parameters

- **inpath** – path to the local data
- **outurl** – url to where to store the data in the external data store.

`static register_url_scheme (scheme)`

Register a custom scheme to behave http like. This is needed to parse all things properly with urlparse.

Parameters **scheme** – the scheme to register

`url_to_path (url)`

Retrieve the path for a given url

Parameters **url** (*str*) – the url to parse

Returns the path corresponding to the input url

Return type *str*

networkmanager Module

This module contains the tool manager class

`class fastr.plugins.managers.networkmanager.NetworkManager (path)`

Bases: *fastr.plugins.managers.objectmanager.ObjectManager*

`__abstractmethods__ = frozenset({})`

`__module__ = 'fastr.plugins.managers.networkmanager'`

`get_object_version (obj)`

Get the version of a given object

Parameters **object** – the object to use

Returns the version of the object

`property object_class`

The class of the objects to populate the manager with

objectmanager Module

This module contains the object manager class

`class fastr.plugins.managers.objectmanager.ObjectManager (path)`

Bases: *fastr.abc.basemanager.BaseManager*

Class for managing all the objects loaded in the fastr system

`__abstractmethods__ = frozenset({'get_object_version', 'object_class'})`

`__contains__ (key)`

Check if an item is in the ObjectManager

Parameters **key** (*str or tuple*) – object id or tuple (Objectid, version)

Returns flag indicating the item is in the manager

`__getitem__(key)`
Retrieve a Object from the ObjectManager. You can request by only an id, which results in the newest version of the Object being returned, or request using both an id and a version.

Parameters `key (str or tuple)` – object id or tuple (Objectid, version)

Returns the requested Object

Raises `FastrObjectUnknownError` – if a non-existing Object was requested

`__init__(path)`
Create a ObjectManager and scan path to search for Objects

Parameters `path (str or iterable of str)` – the path(s) to scan for Objects

Returns newly created ObjectManager

`__keytransform__(key)`
Key transform, used for allowing indexing both by id-only and by (id, version)

Parameters `key` – key to transform

Returns key in form (id, version)

`__module__ = 'fastr.plugins.managers.objectmanager'`

abstract `get_object_version(obj)`
Get the version of a given object

Parameters `object` – the object to use

Returns the version of the object

abstract `property object_class`
The class of the objects to populate the manager with

`objectversions(obj)`
Return a list of available versions for the object

Parameters `object` – The object to check the versions for. Can be either a *Object* or a *str*.

Returns List of version objects. Returns *None* when the given object is not known.

`todict()`
Return a dictionary version of the Manager

Returns manager as a dict

pluginmanager Module

This module contains the Manager class for Plugins in the fastr system

`class fastr.plugins.managers.pluginmanager.PluginManager(path=None)`
Bases: `fastr.abc.basepluginmanager.BasePluginManager`

`__abstractmethods__ = frozenset({})`

`__init__(path=None)`

Create a BasePluginManager and scan the give path for matching plugins

Parameters

- `path (str)` – path to scan
- `recursive (bool)` – flag to indicate a recursive search

- **module** (*module*) – the module to register plugins into

Returns newly created plugin manager

Raises *FastrTypeError* – if self._plugin_class is set to a class not subclassing BasePlugin

```
__module__ = 'fastr.plugins.managers.pluginmanager'
```

```
__setitem__(key, value)
```

Store an item in the BaseManager, will ignore the item if the key is already present in the BaseManager.

Parameters

- **name** – the key of the item to save
- **value** – the value of the item to save

Returns None

```
property plugin_class
```

The plugin manager contains any Plugin subclass

```
class fastr.plugins.managers.pluginmanager.PluginSubManager(parent, plu-  
gin_class)
```

Bases: fastr.abc.basepluginmanager.BasePluginManager

A PluginManager that is a selection of a parent plugin manger. It uses the PluginsView to only expose part of the parent PluginManager. This is used to create plugin plugins.managers for only certain types of plugins (e.g. IOPlugins) without loading them multiple times.

```
__abstractmethods__ = frozenset({})
```

```
__init__(parent, plugin_class)
```

Create a BasePluginManager and scan the give path for matching plugins

Parameters

- **path** (*str*) – path to scan
- **recursive** (*bool*) – flag to indicate a recursive search
- **module** (*module*) – the module to register plugins into

Returns newly created plugin manager

Raises *FastrTypeError* – if self._plugin_class is set to a class not subclassing BasePlugin

```
__module__ = 'fastr.plugins.managers.pluginmanager'
```

```
property data
```

The actual data dict underlying this Manager

```
property plugin_class
```

PluginSubManagers only expose the plugins of a certain class

```
class fastr.plugins.managers.pluginmanager.PluginsView(parent, plugin_class)
```

Bases: collections.abc.MutableMapping

A collection that acts like view of the plugins of another plugin manager. This is a proxy object that only gives access the plugins of a certain plugin class. It behaves like a mapping and is used as the data object for a PluginSubManager.

```
__abstractmethods__ = frozenset({})
```

```
__delitem__(key)
```

```
__dict__ = mappingproxy({'__module__': 'fastr.plugins.managers.pluginmanager', '__doc__': None})
```

```

__getitem__ (item)
__init__ (parent, plugin_class)
    Constructor for the plugins view

Parameters
    • parent (BasePluginManager) – the parent plugin manager
    • plugin_class (class) – the class of the plugins to expose

__iter__()
__len__()
__module__ = 'fastr.plugins.managers.pluginmanager'
__setitem__ (key, value)
__weakref__
    list of weak references to the object (if defined)

filter_plugin (plugin)

```

targetmanager Module

This module holds the ExecutionPluginManager as well as the base-class for all ExecutionPlugins.

```

class fastr.plugins.managers.targetmanager.TargetManager (parent)
    Bases: fastr.plugins.managers.pluginmanager.PluginSubManager
    Container holding all the ExecutionPlugins known to the Fastr system

    __abstractmethods__ = frozenset({})

    __init__ (parent)
        Initialize a ExecutionPluginManager and load plugins.

        Returns newly created ExecutionPluginManager

    __module__ = 'fastr.plugins.managers.targetmanager'

```

toolmanager Module

This module contains the tool manager class

```

class fastr.plugins.managers.toolmanager.ToolManager (path)
    Bases: fastr.plugins.managers.objectmanager.ObjectManager

    __abstractmethods__ = frozenset({})

    __module__ = 'fastr.plugins.managers.toolmanager'

    get_object_version (obj)
        Get the version of a given object

        Parameters object – the object to use
        Returns the version of the object

    property object_class
        The class of the objects to populate the manager with

```

`populate()`

Populate the manager with the data. This is a method that will be called when the Managers data is first accessed. This way we avoid doing expensive directory scans when the data is never requested.

`toolversions(tool)`

Return a list of available versions for the tool

Parameters `tool` – The tool to check the versions for. Can be either a *Tool* or a *str*.

Returns List of version objects. Returns *None* when the given tool is not known.

test Package

test Package

test_datatypes Module

utils Package

utils Package

A collections of utils for fastr (command line tools or non-core functionality)

compare Module

Module to compare various fastr specific things such as a execution directory or a reference directory.

`fastr.utils.compare.compare_execution_dir(path1, path2)`

`fastr.utils.compare.compare_job_dirs(sample, node, node_dir1, node_dir2)`

`fastr.utils.compare.compare_job_output_data(output, job1, job2)`

`fastr.utils.compare.compare_set(set1, set2, path, sub_compare_func, f_args=None, f_kwargs=None)`

Compare two sets and dispatch each item to a sub comparison function

Parameters

- `set1` (*Iterable*) – first set of items
- `set2` (*Iterable*) – second set of items
- `path` (*str*) – identifier of the data location
- `sub_compare_func` – function to apply to items
- `f_args` – args to pass to sub_compare_func
- `f_kwargs` – kwargs to pass to sub_compare_func

Returns generator that iterates over the differences

Return type generator

`fastr.utils.compare.compare_value_dict_item(key, data1, data2, path)`

`fastr.utils.compare.compare_value_list(data1, data2, path, key=None)`

dicteq Module

Some helper function to compare dictionaries and find the parts of the dict that are different. This is mostly to help in debugging.

`fastr.utils.dicteq(self, other)`

Compare two dicts for equality

Parameters

- **self** – the first object to compare
- **other** – the oth

Returns

`fastr.utils.dicteq.diffdict(self, other, path=None, visited=None)`

Find the differences in two dictionaries.

Parameters

- **self** – the first object to compare
- **other** (`dict`) – other dictionary
- **path** (`list`) – the path for nested dicts (too keep track of recursion)

Returns list of messages indicating the differences

Return type `list`

`fastr.utils.dicteq.diffobj(self, other, path=None, visited=None)`

Compare two objects by comparing their `__dict__` entries

Parameters

- **self** – the first object to compare
- **other** – other objects to compare
- **path** (`list`) – the path for nested dicts (too keep track of recursion)

Returns list of messages

Return type `list`

`fastr.utils.dicteq.diffobj_str(self, other)`

Compare two objects by comparing their `__dict__` entries, but returns the differences in a single string ready for logging.

Parameters

- **self** – the first object to compare
- **other** – other object to compare to

Returns the description of the differences

Return type `str`

gettools Module

`fastr.utils.gettools.main()`

multiprocesswrapper Module

```
fastr.utils.multiprocesswrapper.function_wrapper(filepath, fnc_name, *args, **kwargs)
```

verify Module

```
fastr.utils.verify.verify_resource_loading(filename, log=<Logger fastr (INFO)>)
```

Verify that a resource file can be loaded. Returns loaded object.

Parameters

- **filename** (`str`) – path of the object to load
- **log** – the logger to use to send messages to

Returns loaded resource

```
fastr.utils.verify.verify_tool(filename, log=<Logger fastr (INFO)>, perform_tests=True)
```

Verify that a file

Subpackages

cmd Package

cmd Package

```
fastr.utils.cmd.add_parser_doc_link(parser, filepath)
```

```
fastr.utils.cmd.find_commands()
```

```
fastr.utils.cmd.get_command_module(command)
```

```
fastr.utils.cmd.main()
```

```
fastr.utils.cmd.print_help(commands=None)
```

cat Module

```
fastr.utils.cmd.cat.fastr_cat(infile, path)
```

```
fastr.utils.cmd.cat.get_parser()
```

```
fastr.utils.cmd.cat.main()
```

Print information from a job file

dump Module

```
fastr.utils.cmd.dump.create_zip(directory, output_file)
```

```
fastr.utils.cmd.dump.get_parser()
```

```
fastr.utils.cmd.dump.main()
```

Dump the contents of a network run tempdir into a zip for remote assistance

execute Module

```
fastr.utils.cmd.execute.get_parser()  
fastr.utils.cmd.execute.main()  
    Execute a fastr job file
```

extract_argparse Module

```
fastr.utils.cmd.extract_argparse.cardinality_from_nargs(value)  
fastr.utils.cmd.extract_argparse.datatype_from_type(type_, metavar)  
fastr.utils.cmd.extract_argparse.extract_argparser(filepath)  
fastr.utils.cmd.extract_argparse.find_argparser(entry, basename='/home/docs/checkouts/readthedocs.org/user_build')  
fastr.utils.cmd.extract_argparse.get_parser()  
fastr.utils.cmd.extract_argparse.main()  
    Create a stub for a Tool based on a python script using argparse
```

provenance Module

```
fastr.utils.cmd.provenance.get_parser()  
fastr.utils.cmd.provenance.get_prov_document(result)  
fastr.utils.cmd.provenance.main()  
    Get PROV information from the result pickle.
```

pylint Module

```
fastr.utils.cmd pylint.get_parser()  
fastr.utils.cmd pylint.main()  
    Tiny wrapper in pylint so the output can be saved to a file (for test automation)  
fastr.utils.cmd pylint.run_pylint(out_file, pylint_args)
```

report Module

```
fastr.utils.cmd.report.get_parser()  
fastr.utils.cmd.report.main()  
    Print report of a job result (__fastr_result__.pickle.gz) file
```

run Module

```
fastr.utils.cmd.run.create_network_parser(network)  
fastr.utils.cmd.run.get_parser()  
fastr.utils.cmd.run.main()  
    Run a Network from the commandline
```

sink Module

```
fastr.utils.cmd.sink.get_parser()  
fastr.utils.cmd.sink.main()  
    Command line access to the IOPlugin sink  
fastr.utils.cmd.sink.sink()
```

source Module

```
fastr.utils.cmd.source.get_parser()  
fastr.utils.cmd.source.main()  
    Command line access to the IOPlugin source  
fastr.utils.cmd.source.source()
```

test Module

```
fastr.utils.cmd.test.check_network(args)  
fastr.utils.cmd.test.check_networks(args)  
fastr.utils.cmd.test.check_tool(args)  
fastr.utils.cmd.test.check_tools(args)  
fastr.utils.cmd.test.directory(path)  
    Make sure the path is a valid directory for argparse  
fastr.utils.cmd.test.get_parser()  
fastr.utils.cmd.test.main()  
    Run the tests of a tool to verify the proper function  
fastr.utils.cmd.test.tool(value)  
    Make sure the value is a correct tool for argparse or reference directory
```

trace Module

```
fastr.utils.cmd.trace.get_parser()  
fastr.utils.cmd.trace.main()  
    Trace samples/sinks from a run  
fastr.utils.cmd.trace.print_sample_sink(sink_data, dirname, sample_sink_tuples, verbose)  
fastr.utils.cmd.trace.print_samples(sink_data, sample_ids, verbose)  
fastr.utils.cmd.trace.print_sinks(sink_data, sink_ids, verbose)  
fastr.utils.cmd.trace.read_sink_data(infile)  
fastr.utils.cmd.trace.switch_sample_sink(sink_data)
```

upgrade Module

```
class fastr.utils.cmd.upgrade.FastrNamespaceType (toollist, typelist)
    Bases: tuple

    __getnewargs__ ()
        Return self as a plain tuple. Used by copy and pickle.

    __module__ = 'fastr.utils.cmd.upgrade'

    static __new__ (_cls, toollist, typelist)
        Create new instance of FastrNamespaceType(toollist, typelist)

    __repr__ ()
        Return a nicely formatted representation string

    __slots__ = ()

property toollist
    Alias for field number 0

property typelist
    Alias for field number 1

class fastr.utils.cmd.upgrade.dummy_container
    Bases: object

    __dict__ = mappingproxy({'__module__': 'fastr.utils.cmd.upgrade', '__getitem__': <funct>})

    __getitem__ (value)
        __module__ = 'fastr.utils.cmd.upgrade'

    __weakref__
        list of weak references to the object (if defined)

fastr.utils.cmd.upgrade.find_tool (toolspec)
fastr.utils.cmd.upgrade.get_parser ()
fastr.utils.cmd.upgrade.main ()
    Upgrade a fastr 2.x python file to fastr 3.x syntax
fastr.utils.cmd.upgrade.upgrade_network (infile, outfile)
fastr.utils.cmd.upgrade.upgrade_tool (infile, outfile)
```

verify Module

```
fastr.utils.cmd.verify.get_parser ()
fastr.utils.cmd.verify.main ()
    Verify fastr resources, at the moment only tool definitions are supported.
```

webapp Module

```
fastr.utils.cmd.webapp.get_parser ()
fastr.utils.cmd.webapp.main ()
    Start the fastr webapp and open in a new browser tab
fastr.utils.cmd.webapp.open_url (url)
```

secrets Package

secrets Package

secretprovider Module

secretservice Module

Subpackages

exceptions Package

exceptions Package

couldnotdeletecredentials Module

couldnotretrievecredentials Module

couldnotsetcredentials Module

notimplemented Module

providerNotFound Module

providers Package

providers Package

keyringprovider Module

netrcprovider Module

web Package

web Package

api Module

```
class fastr.web.api.NetworkApi(api=None, *args, **kwargs)
Bases: flask_restplus.resource.Resource
    __module__ = 'fastr.web.api'
    endpoint = 'api_network'
    get(id_)
        Get a Network json description from the server
    mediatypes()
```

```

methods = {'GET'}

class fastr.web.api.NetworkListApi(api=None, *args, **kwargs)
    Bases: flask_restplus.resource.Resource

        _module_ = 'fastr.web.api'
        endpoint = 'api_networks'

        get()
            Get a list of the networks

        mediatypes()

        methods = {'GET'}

class fastr.web.api.ObjectUrl(object_classs, **kwargs)
    Bases: flask_restplus.fields.Raw

        _init_(object_classs, **kwargs)
            Initialize self. See help(type(self)) for accurate signature.

        _module_ = 'fastr.web.api'
        _schema_type_ = 'string'
        _slotnames_ = []

        format(value)
            Formats a field's value. No-op by default - field classes that modify how the value of existing object keys
            should be presented should override this and apply the appropriate formatting.

            Parameters value – The value to format

            Raises MarshallingError – In case of formatting problem

        Ex:

class TitleCase(Raw):
    def format(self, value):
        return unicode(value).title()

class fastr.web.api.Run(id_, network, source_data, sink_data)
    Bases: object

        _dict_ = mappingproxy({'_module_': 'fastr.web.api', '_init_': <function Run.*>})

        _init_(id_, network, source_data, sink_data)
            Initialize self. See help(type(self)) for accurate signature.

        _module_ = 'fastr.web.api'
        _weakref_
            list of weak references to the object (if defined)

        abort()

        run_network(network, source_data, sink_data, abort_lock)

        status()

class fastr.web.api.RunApi(api=None, *args, **kwargs)
    Bases: flask_restplus.resource.Resource

        Run API documentation

        _module_ = 'fastr.web.api'

```

```
delete(id_)
    Abort a Network run and stop all associated execution

endpoint = 'api_run'

get(id_)
    Get information about a Network run

mediatypes()
methods = {'DELETE', 'GET'}

class fastr.web.api.RunListApi(api=None, *args, **kwargs)
Bases: flask_restplus.resource.Resource

    __module__ = 'fastr.web.api'
    endpoint = 'api_runs'

get()
    Get a list of all Network runs on the server

mediatypes()
methods = {'GET', 'POST'}

post()
    Create a new Network run and start execution

request_parser = <flask_restplus.reqparse.RequestParser object>

class fastr.web.api.StatusApi(api=None, *args, **kwargs)
Bases: flask_restplus.resource.Resource

    __module__ = 'fastr.web.api'
    endpoint = 'api_status'

get(id_)
    Get the status of a Network Run on the server

mediatypes()
methods = {'GET'}

class fastr.web.api.SubUrl(object_classs, subfield, **kwargs)
Bases: flask_restplus.fields.Raw

    __init__(object_classs, subfield, **kwargs)
        Initialize self. See help(type(self)) for accurate signature.

    __module__ = 'fastr.web.api'
    __schema_type__ = 'string'

format(value)
    Formats a field's value. No-op by default - field classes that modify how the value of existing object keys should be presented should override this and apply the appropriate formatting.

    Parameters value – The value to format
    Raises MarshallingError – In case of formatting problem

Ex:
```

```

class TitleCase(Raw):
    def format(self, value):
        return unicode(value).title()

class fastr.web.api.ToolApi(api=None, *args, **kwargs)
Bases: flask_restplus.resource.Resource

    __module__ = 'fastr.web.api'
    endpoint = 'api_version_tool'
    get(id_, version=None)
        Get a Tool json description from the server
    mediatypes()
    methods = {'GET'}

class fastr.web.api.ToolListApi(api=None, *args, **kwargs)
Bases: flask_restplus.resource.Resource

    __module__ = 'fastr.web.api'
    endpoint = 'api_tools'
    getmediatypes()
    methods = {'GET'}

fastr.web.api.network_lock_thread(lock, network)
fastr.web.api.network_runner(network, source_data, sink_data, chuck_status, job_status,
                             job_results, abort_lock)
fastr.web.api.update_job_result(job, job_status, job_results)
fastr.web.api.update_status(job, job_status)

```

run Module

```

fastr.web.run.main()
fastr.web.run.runapp(debug=False)

```

views Module

```

fastr.web.views.doc()
fastr.web.views.index()
fastr.web.views.network(name=None)
fastr.web.views.networks()
fastr.web.views.prov()
fastr.web.views.shutdown()
fastr.web.views.shutdown_server()

```

```
fastr.web.views.tool (toolname=None, version=None)
fastr.web.views.websocket_client ()
```

**CHAPTER
FOUR**

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

f

fastr.__init__, 79
fastr.api, 88
fastr.core, 90
fastr.core.cardinality, 90
fastr.core.dimension, 95
fastr.core.interface, 96
fastr.core.ioplugin, 98
fastr.core.provenance, 100
fastr.core.resourcelimit, 101
fastr.core.samples, 102
fastr.core.target, 109
fastr.core.test, 117
fastr.core.tool, 111
fastr.core.version, 113
fastr.core.vfs, 115
fastr.data, 117
fastr.data.url, 117
fastr.datatypes, 119
fastr.exceptions, 79
fastr.execution, 127
fastr.execution.basenoderun, 127
fastr.execution.environmentmodules, 128
fastr.execution.executionscript, 129
fastr.execution.flownoderun, 129
fastr.execution.inputoutputrun, 130
fastr.execution.job, 141
fastr.execution.linkrun, 149
fastr.execution.macronoderun, 151
fastr.execution.networkanalyzer, 152
fastr.execution.networkchunker, 153
fastr.execution.networkrun, 153
fastr.execution.noderun, 155
fastr.execution.sinknoderun, 158
fastr.execution.sourcenoderun, 160
fastr.helpers, 162
fastr.helpers.checksum, 162
fastr.helpers.classproperty, 164
fastr.helpers.clear_pycs, 164
fastr.helpers.configmanager, 164
fastr.helpers.events, 167
fastr.helpers.filesynchelper, 167

fastr.helpers.iohelpers, 168
fastr.helpers.jsonschemaparser, 168
fastr.helpers.lazy_module, 171
fastr.helpers.lockfile, 171
fastr.helpers.procutils, 172
fastr.helpers.report, 172
fastr.helpers.rest_generation, 172
fastr.helpers.schematatable, 172
fastr.helpers.shellescape, 173
fastr.helpers.sysinfo, 173
fastr.helpers.xmltodict, 174
fastr.planning, 175
fastr.planning.inputgroup, 175
fastr.planning.inputgroupcombiner, 176
fastr.planning.inputoutput, 178
fastr.planning.link, 192
fastr.planning.network, 194
fastr.planning.node, 198
fastr.plugins, 206
fastr.plugins.executionplugin, 232
fastr.plugins.managers, 236
fastr.plugins.managers.executionpluginmanager,
 236
fastr.plugins.managers.interfacemanager,
 236
fastr.plugins.managers.iopluginmanager,
 236
fastr.plugins.managers.networkmanager,
 238
fastr.plugins.managers.objectmanager,
 238
fastr.plugins.managers.pluginmanager,
 239
fastr.plugins.managers.targetmanager,
 241
fastr.plugins.managers.toolmanager, 241
fastr.plugins.reportingplugin, 235
fastr.test, 242
fastr.utils, 242
fastr.utils.cmd, 244
fastr.utils.cmd.cat, 244
fastr.utils.cmd.dump, 244

`fastr.utils.cmd.execute`, 245
`fastr.utils.cmd.extract_argparse`, 245
`fastr.utils.cmd.provenance`, 245
`fastr.utils.cmd pylint`, 245
`fastr.utils.cmd.report`, 245
`fastr.utils.cmd.run`, 245
`fastr.utils.cmd.sink`, 246
`fastr.utils.cmd.source`, 246
`fastr.utils.cmd.test`, 246
`fastr.utils.cmd.trace`, 246
`fastr.utils.cmd.upgrade`, 247
`fastr.utils.cmd.verify`, 247
`fastr.utils.cmd.webapp`, 247
`fastr.utils.compare`, 242
`fastr.utils.dicteq`, 243
`fastr.utils.gettools`, 243
`fastr.utils.multiprocesswrapper`, 244
`fastr.utils.verify`, 244
`fastr.version`, 87
`fastr.web`, 248
`fastr.web.api`, 248
`fastr.web.run`, 251
`fastr.web.views`, 251

INDEX

Symbols

—abstractmethods__
 (*fastr.core.dimension.ForwardsDimensions attribute*), 96

—abstractmethods__
 (*fastr.core.dimension.HasDimensions attribute*), 96

—abstractmethods__
 (*fastr.core.interface.Interface attribute*), 97

—abstractmethods__
 (*fastr.core.ioplugin.IOPlugin attribute*), 98

—abstractmethods__
 (*fastr.core.samples.ContainsSamples attribute*), 102

—abstractmethods__
 (*fastr.core.samples.HasSamples attribute*), 103

—abstractmethods__
 (*fastr.core.samples.SampleCollection attribute*), 104

—abstractmethods__
 (*fastr.core.samples.SampleValue attribute*), 108

—abstractmethods__
 (*fastr.core.target.ProcessUsageCollection attribute*), 109

—abstractmethods__
 (*fastr.core.target.SubprocessBasedTarget attribute*), 109

—abstractmethods__ (*fastr.core.target.Target attribute*), 110

—abstractmethods__ (*fastr.datatypes.AnyFile attribute*), 119

—abstractmethods__ (*fastr.datatypes.AnyType attribute*), 119

—abstractmethods__
 (*fastr.datatypes.BaseDataType attribute*), 120

—abstractmethods__ (*fastr.datatypes.DataType attribute*), 121

—abstractmethods__

 (*fastr.datatypes.DataTypeManager attribute*), 122

—abstractmethods__ (*fastr.datatypes.Deferred attribute*), 124

—abstractmethods__ (*fastr.datatypes.EnumType attribute*), 125

—abstractmethods__ (*fastr.datatypes.TypeGroup attribute*), 125

—abstractmethods__ (*fastr.datatypes.URLType attribute*), 126

—abstractmethods__ (*fastr.datatypes.ValueType attribute*), 127

—abstractmethods__
 (*fastr.execution.basenoderun.BaseNodeRun attribute*), 127

—abstractmethods__
 (*fastr.execution.flownoderun.AdvancedFlowNodeRun attribute*), 130

—abstractmethods__
 (*fastr.execution.flownoderun.FlowNodeRun attribute*), 130

—abstractmethods__
 (*fastr.execution.inputoutputrun.AdvancedFlowOutputRun attribute*), 130

—abstractmethods__
 (*fastr.execution.inputoutputrun.BaseInputRun attribute*), 131

—abstractmethods__
 (*fastr.execution.inputoutputrun.InputRun attribute*), 131

—abstractmethods__
 (*fastr.execution.inputoutputrun.MacroOutputRun attribute*), 133

—abstractmethods__
 (*fastr.execution.inputoutputrun.NamedSubinputRun attribute*), 133

—abstractmethods__
 (*fastr.execution.inputoutputrun.OutputRun attribute*), 134

—abstractmethods__
 (*fastr.execution.inputoutputrun.SourceOutputRun attribute*), 136

__abstractmethods__
(fastr.execution.inputoutputrun.SubInputRun
attribute), 137

__abstractmethods__
(fastr.execution.inputoutputrun.SubOutputRun
attribute), 139

__abstractmethods__
(fastr.execution.linkrun.LinkRun attribute),
149

__abstractmethods__
(fastr.execution.macronoderun.MacroNodeRun
attribute), 151

__abstractmethods__
(fastr.execution.noderun.NodeRun attribute),
156

__abstractmethods__
(fastr.execution.sinknoderun.SinkNodeRun
attribute), 158

__abstractmethods__
(fastr.execution.sourcenoderun.ConstantNodeRun
attribute), 161

__abstractmethods__
(fastr.execution.sourcenoderun.SourceNodeRun
attribute), 160

__abstractmethods__
(fastr.planning.inputgroup.InputGroup attribute), 175

__abstractmethods__
(fastr.planning.inputgroupcombiner.BaseInputGroupCombiner
attribute), 176

__abstractmethods__
(fastr.planning.inputgroupcombiner.DefaultInputGroupCombiner
attribute), 177

__abstractmethods__
(fastr.planning.inputgroupcombiner.MergingInputGroupCombiner
attribute), 178

__abstractmethods__
(fastr.planning.inputoutput.AdvancedFlowOutput
attribute), 179

__abstractmethods__
(fastr.planning.inputoutput.BaseInput attribute),
179

__abstractmethods__
(fastr.planning.inputoutput.BaseInputOutput
attribute), 180

__abstractmethods__
(fastr.planning.inputoutput.BaseOutput attribute),
181

__abstractmethods__
(fastr.planning.inputoutput.Input attribute),
182

__abstractmethods__
(fastr.planning.inputoutput_MACROinput
attribute), 184

__abstractmethods__
(fastr.planning.inputoutput.MacroOutput
attribute), 185

__abstractmethods__
(fastr.planning.inputoutput.NamedSubInput
attribute), 185

__abstractmethods__
(fastr.planning.inputoutput.Output attribute),
186

__abstractmethods__
(fastr.planning.inputoutput.SourceOutput
attribute), 187

__abstractmethods__
(fastr.planning.inputoutput.SubInput attribute),
188

__abstractmethods__
(fastr.planning.inputoutput.SubOutput attribute), 190

__abstractmethods__ (fastr.planning.link.Link attribute), 192

__abstractmethods__
(fastr.planning.node.AdvancedFlowNode
attribute), 198

__abstractmethods__
(fastr.planning.node.ConstantNode attribute),
199

__abstractmethods__
(fastr.planning.node.FlowNode attribute),
200

__abstractmethods__
(fastr.planning.node.MacroNode attribute),
201

__abstractmethods__
(fastr.planning.node.Node attribute), 201

__abstractmethods__
(fastr.planning.node.SinkNode attribute),
204

__abstractmethods__
(fastr.planning.node.SourceNode attribute),
205

__abstractmethods__
(fastr.plugins.BlockingExecution attribute),
206

__abstractmethods__
(fastr.plugins.CommaSeperatedValueFile
attribute), 207

__abstractmethods__
(fastr.plugins.CrossValidation attribute),
208

__abstractmethods__
(fastr.plugins.DRMAAExecution attribute),
209

208
`__abstractmethods__ (fastr.plugins.DockerTarget attribute), 210`
`__abstractmethods__ (fastr.plugins.ElasticsearchReporter attribute), 210`
`__abstractmethods__ (fastr.plugins.FastrInterface attribute), 212`
`__abstractmethods__ (fastr.plugins.FileSystem attribute), 214`
`__abstractmethods__ (fastr.plugins.FlowInterface attribute), 215`
`__abstractmethods__ (fastr.plugins.HTTPPlugin attribute), 217`
`__abstractmethods__ (fastr.plugins.LinearExecution attribute), 217`
`__abstractmethods__ (fastr.plugins.LocalBinaryTarget attribute), 219`
`__abstractmethods__ (fastr.plugins.MacroTarget attribute), 219`
`__abstractmethods__ (fastr.plugins.NipypeInterface attribute), 220`
`__abstractmethods__ (fastr.plugins.Null attribute), 221`
`__abstractmethods__ (fastr.plugins.PimReporter attribute), 221`
`__abstractmethods__ (fastr.plugins.ProcessPoolExecution attribute), 222`
`__abstractmethods__ (fastr.plugins.RQExecution attribute), 223`
`__abstractmethods__ (fastr.plugins.Reference attribute), 223`
`__abstractmethods__ (fastr.plugins.S3Filesystem attribute), 224`
`__abstractmethods__ (fastr.plugins.SimpleReport attribute), 225`
`__abstractmethods__ (fastr.plugins.SingularityTarget attribute), 225`
`__abstractmethods__ (fastr.plugins.SlurmExecution attribute), 226`
`__abstractmethods__ (fastr.plugins.StrongrExecution attribute), 227`
`__abstractmethods__ (fastr.plugins.VirtualFileSystem attribute), 228`
`__abstractmethods__ (fastr.plugins.VirtualFileSystemRegularExpression attribute), 229`
`__abstractmethods__ (fastr.plugins.VirtualFileSystemValueList attribute), 229`
`__abstractmethods__ (fastr.plugins.XNATStorage attribute), 231`
`__abstractmethods__ (fastr.plugins.executionplugin.ExecutionPlugin attribute), 234`
`__abstractmethods__ (fastr.plugins.managers.executionpluginmanager.ExecutionPlugin attribute), 236`
`__abstractmethods__ (fastr.plugins.managers.interfacemanager.InterfacePluginManager attribute), 236`
`__abstractmethods__ (fastr.plugins.managers.iopluginmanager.IOPluginManager attribute), 236`
`__abstractmethods__ (fastr.plugins.managers.networkmanager.NetworkManager attribute), 238`
`__abstractmethods__ (fastr.plugins.managers.objectmanager.ObjectManager attribute), 238`
`__abstractmethods__ (fastr.plugins.managers.pluginmanager.PluginManager attribute), 239`
`__abstractmethods__ (fastr.plugins.managers.pluginmanager.PluginSubManager attribute), 240`
`__abstractmethods__ (fastr.plugins.managers.pluginmanager.PluginsView attribute), 240`
`__abstractmethods__ (fastr.plugins.managers.targetmanager.TargetManager attribute), 241`
`__abstractmethods__ (fastr.plugins.managers.toolmanager.ToolManager attribute), 241`
`__abstractmethods__ (fastr.plugins.reportingplugin.ReportingPlugin attribute), 235`
`__add__() (fastr.core.samples.SampleBaseId method), 103`
`__add__() (fastr.core.samples.SampleItemBase method), 106`
`__add__() (fastr.core.samples.SamplePayload method), 107`
`__add__() (fastr.core.samples.SampleValue method), 108`
`__add__() (fastr.helpers.configmanager.EmptyDefault method), 166`
`__bool__() (fastr.execution.networkrun.NetworkRun method), 153`

—contains__() (fastr.core.samples.HasSamples method), 103
—contains__() (fastr.core.samples.SampleCollection method), 104
—contains__() (fastr.plugins.managers.objectmanager.ObjectManager method), 238
—dataschemafile__ (fastr.core.tool.Tool attribute), 111
—dataschemafile__ (fastr.execution.linkrun.LinkRun attribute), 149
—dataschemafile__ (fastr.execution.noderun.NodeRun attribute), 156
—dataschemafile__ (fastr.execution.sinknoderun.SinkNodeRun attribute), 158
—dataschemafile__ (fastr.execution.sourcenoderun.ConstantNodeRun attribute), 161
—dataschemafile__ (fastr.execution.sourcenoderun.SourceNodeRun attribute), 160
—dataschemafile__ (fastr.planning.link.Link attribute), 192
—dataschemafile__ (fastr.planning.network.Network attribute), 194
—dataschemafile__ (fastr.planning.node.ConstantNode attribute), 199
—dataschemafile__ (fastr.planning.node.Node attribute), 201
—dataschemafile__ (fastr.planning.node.SinkNode attribute), 204
—dataschemafile__ (fastr.planning.node.SourceNode attribute), 205
—dataschemafile__ (fastr.plugins.FastrInterface attribute), 212
—dataschemafile__ (fastr.plugins.FlowInterface attribute), 215
—del__() (fastr.helpers.lockfile.DirectoryLock method), 171
—del__() (fastr.plugins.executionplugin.ExecutionPlugin method), 234
—delitem__() (fastr.core.samples.SampleCollection method), 104
—delitem__() (fastr.core.samples.SampleValue method), 108
—delitem__() (fastr.helpers.configmanager.EmptyDefault enter() (fastr.core.target.Target method), 110
—delitem__() (fastr.helpers.configmanager.EmptyDefault enter() (fastr.helpers.lockfile.DirectoryLock method), 171
—delitem__() (fastr.plugins.managers.pluginmanager.PluginsView () (fastr.plugins.DockerTarget method),
method), 240
—dict__ (fastr.core.cardinality.CardinalitySpec attribute), 91
—dict__ (fastr.core.dimension.HasDimensions attribute), 96
—dict__ (fastr.core.interface.InputSpec attribute), 97
—dict__ (fastr.core.interface.InterfaceResult attribute), 98
—dict__ (fastr.core.interface.OutputSpec attribute), 98
—dict__ (fastr.core.provenance.Provenance attribute), 100
—dict__ (fastr.core.samples.SampleBaseId attribute), 103
—dict__ (fastr.core.samples.SampleCollection attribute), 104
—dict__ (fastr.core.samples.SampleItemBase attribute), 106
—dict__ (fastr.core.samples.SampleValue attribute), 108
—dict__ (fastr.core.target.ProcessUsageCollection attribute), 109
—dict__ (fastr.core.target.TargetResult attribute), 110
—dict__ (fastr.core.version.Version attribute), 113
—dict__ (fastr.core.vfs.VirtualFileSystem attribute), 115
—dict__ (fastr.execution.environmentmodules.EnvironmentModules attribute), 128
—dict__ (fastr.execution.networkanalyzer.NetworkAnalyzer attribute), 152
—dict__ (fastr.execution.networkchunker.NetworkChunker attribute), 153
—dict__ (fastr.helpers.classproperty.ClassPropertyDescriptor attribute), 164
—dict__ (fastr.helpers.configmanager.Config attribute), 164
—dict__ (fastr.helpers.configmanager.EmptyDefault attribute), 166
—dict__ (fastr.helpers.filesynchelperFileSyncHelper attribute), 167
—dict__ (fastr.helpers.lockfile.DirectoryLock attribute), 171
—dict__ (fastr.helpers.schematatable.SchemaPrinter attribute), 172
—dict__ (fastr.plugins.managers.pluginmanager.PluginsView attribute), 240
—dict__ (fastr.utils.cmd.upgrade.dummy_container attribute), 247
—dict__ (fastr.web.api.Run attribute), 249
—dir__() (in module fastr.__init__), 79
—enter__() (fastr.core.target.Target method), 110
—enter__() (fastr.helpers.lockfile.DirectoryLock method), 171

__enter__() (fastr.plugins.LocalBinaryTarget method), 219
 __enter__() (fastr.plugins.SingularityTarget method), 225
 __enter__() (fastr.plugins.executionplugin.ExecutionPlugin method), 234
 __eq__() (fastr.api.ResourceLimit method), 89
 __eq__() (fastr.core.cardinality.AnyCardinalitySpec method), 90
 __eq__() (fastr.core.cardinality.AsCardinalitySpec method), 90
 __eq__() (fastr.core.cardinality.CardinalitySpec method), 91
 __eq__() (fastr.core.cardinality.ChoiceCardinalitySpec method), 92
 __eq__() (fastr.core.cardinality.IntCardinalitySpec method), 92
 __eq__() (fastr.core.cardinality.MaxCardinalitySpec method), 93
 __eq__() (fastr.core.cardinality.MinCardinalitySpec method), 93
 __eq__() (fastr.core.cardinality.RangeCardinalitySpec method), 93
 __eq__() (fastr.core.cardinality.ValueCardinalitySpec method), 94
 __eq__() (fastr.core.dimension.Dimension method), 95
 __eq__() (fastr.core.resourcelimit.ResourceLimit method), 101
 __eq__() (fastr.core.tool.Tool method), 111
 __eq__() (fastr.datatypes.BaseDataType method), 120
 __eq__() (fastr.datatypes.URLType method), 126
 __eq__() (fastr.execution.linkrun.LinkRun method), 149
 __eq__() (fastr.execution.networkrun.NetworkRun method), 154
 __eq__() (fastr.execution.noderun.NodeRun method), 156
 __eq__() (fastr.execution.sourcenoderun.SourceNodeRun method), 160
 __eq__() (fastr.planning.inputoutput.Input method), 182
 __eq__() (fastr.planning.inputoutput.Output method), 186
 __eq__() (fastr.planning.inputoutput.SubInput method), 188
 __eq__() (fastr.planning.inputoutput.SubOutput method), 190
 __eq__() (fastr.planning.link.Link method), 192
 __eq__() (fastr.planning.network.Network method), 194
 __eq__() (fastr.planning.node.MacroNode method), 200
 __eq__() (fastr.planning.node.Node method), 201
 __eq__() (fastr.plugins.FastrInterface method), 212
 __eq__() (fastr.plugins.FlowInterface method), 215
 __eq__() (fastr.plugins.NipypeInterface method), 220
 __exit__() (fastr.core.target.Target method), 110
 __exit__() (fastr.helpers.lockfile.DirectoryLock method), 171
 __exit__() (fastr.plugins.DockerTarget method), 210
 __exit__() (fastr.plugins.LocalBinaryTarget method), 219
 __exit__() (fastr.plugins.SingularityTarget method), 225
 __exit__() (fastr.plugins.executionplugin.ExecutionPlugin method), 234
 __format__() (in module fastr.__init__), 79
 __get__() (fastr.helpers.classproperty.ClassPropertyDescriptor method), 164
 __getattr__() (fastr.helpers.lazy_module.LazyModule method), 171
 __getitem__() (fastr.api.Output method), 77
 __getitem__() (fastr.core.samples.ContainsSamples method), 102
 __getitem__() (fastr.core.samples.HasSamples method), 103
 __getitem__() (fastr.core.samples.SampleCollection method), 104
 __getitem__() (fastr.core.samples.SampleValue method), 108
 __getitem__() (fastr.core.target.ProcessUsageCollection method), 109
 __getitem__() (fastr.execution.inputoutputrun.InputRun method), 131
 __getitem__() (fastr.execution.inputoutputrun.NamedSubinputRun method), 133
 __getitem__() (fastr.execution.inputoutputrun.OutputRun method), 134
 __getitem__() (fastr.execution.inputoutputrun.SourceOutputRun method), 136
 __getitem__() (fastr.execution.inputoutputrun.SubInputRun method), 137
 __getitem__() (fastr.execution.inputoutputrun.SubOutputRun method), 139
 __getitem__() (fastr.execution.linkrun.LinkRun method), 149
 __getitem__() (fastr.execution.networkrun.NetworkRun method), 154
 __getitem__() (fastr.helpers.configmanager.EmptyDefault method), 166
 __getitem__() (fastr.planning.inputgroup.InputGroup method), 175
 __getitem__() (fastr.planning.inputoutput.Input method), 182
 __getitem__() (fastr.planning.inputoutput.NamedSubInput method), 185
 __getitem__() (fastr.planning.inputoutput.Output

```
        method), 186
__getitem__() (fastr.planning.inputoutput.SubInput
    method), 188
__getitem__() (fastr.planning.network.Network
    method), 195
__getitem__() (fastr.plugins.managers.objectmanager.ObjectManager
    method), 238
__getitem__() (fastr.plugins.managers.pluginmanager.PluginManager
    method), 240
__getitem__() (fastr.utils.cmd.upgrade.dummy_container
    method), 247
__getnewargs__() (fastr.core.samples.SampleItemBase
    method), 106
__getnewargs__() (fastr.core.target.SystemUsageInfo
    method), 109
__getnewargs__() (fastr.utils.cmd.upgrade.FastrNamespaceType
    method), 199
    247
__getstate__() (fastr.api.ResourceLimit method),
    89
__getstate__() (fastr.core.interface.Interface
    method), 97
__getstate__() (fastr.core.resourcelimit.ResourceLimit
    method), 101
__getstate__() (fastr.core.samples.SampleValue
    method), 108
__getstate__() (fastr.core.tool.Tool method), 111
__getstate__() (fastr.datatypes.BaseDataType
    method), 120
__getstate__() (fastr.datatypes.Deferred method),
    124
__getstate__() (fastr.execution.inputoutputrun.InputRun
    hash_(fastr.api.ResourceLimit attribute), 89
    method), 131
                hash_(fastr.core.cardinality.AnyCardinalitySpec
__getstate__() (fastr.execution.inputoutputrun.OutputRun
    method), 134
                hash_(fastr.core.cardinality.AsCardinalitySpec
__getstate__() (fastr.execution.inputoutputrun.SubInputRun
    method), 138
                hash_(fastr.core.cardinality.CardinalitySpec
__getstate__() (fastr.execution.inputoutputrun.SubOutputRun
    method), 139
                hash_(fastr.core.cardinality.ChoiceCardinalitySpec
__getstate__() (fastr.execution.job.Job method),
    142
                hash_(fastr.core.cardinality.IntCardinalitySpec
__getstate__() (fastr.execution.linkrun.LinkRun
    method), 149
                hash_(fastr.core.cardinality.MaxCardinalitySpec
__getstate__() (fastr.execution.macronoderun.MacroNodeRun
    method), 151
                hash_(fastr.core.cardinality.MinCardinalitySpec
__getstate__() (fastr.execution.networkrun.NetworkRun
    method), 154
                hash_(fastr.core.cardinality.RangeCardinalitySpec
__getstate__() (fastr.execution.noderun.NodeRun
    method), 156
                hash_(fastr.core.cardinality.ValueCardinalitySpec
__getstate__() (fastr.execution.sinknoderun.SinkNodeRun
    method), 158
                hash_(fastr.core.dimension.Dimension attribute),
__getstate__() (fastr.execution.sourcenoderun.ConstantNodeRun
    method), 161
                hash_(fastr.core.resourcelimit.ResourceLimit at-
__getstate__() (fastr.execution.sourcenoderun.SourceNodeRun
    method), 160
                hash_(fastr.core.tool.Tool attribute), 111
                hash_(fastr.planning.inputoutput.BaseInputOutput
                    method), 180
                hash_(fastr.planning.inputoutput.Input
                    method), 182
                hash_(fastr.planning.inputoutput.Output
                    method), 186
                hash_(fastr.planning.inputoutput.SubInput
                    method), 188
                hash_(fastr.planning.inputoutput.SubOutput
                    method), 190
                hash_(fastr.planning.link.Link method),
                    192
                hash_(fastr.planning.network.Network
                    method), 195
                hash_(fastr.planning.node.ConstantNode
                    method), 199
                hash_(fastr.planning.node.MacroNode
                    method), 201
                hash_(fastr.planning.node.Node method),
                    201
                hash_(fastr.planning.node.SinkNode
                    method), 204
                hash_(fastr.planning.node.SourceNode
                    method), 205
                hash_(fastr.plugins.FastrInterface
                    method), 212
                hash_(fastr.plugins.FlowInterface
                    method), 215
                hash_(fastr.plugins.NipypeInterface
                    method), 220
                hash_(fastr.core.cardinality.AnyCardinalitySpec
__getstate__() (fastr.core.cardinality.AsCardinalitySpec
    method), 90
                hash_(fastr.core.cardinality.CardinalitySpec
__getstate__() (fastr.core.cardinality.ChoiceCardinalitySpec
    method), 91
                hash_(fastr.core.cardinality.ChoiceCardinalitySpec
__getstate__() (fastr.core.cardinality.IntCardinalitySpec
    attribute), 92
                hash_(fastr.core.cardinality.IntCardinalitySpec
__getstate__() (fastr.core.cardinality.MaxCardinalitySpec
    attribute), 92
                hash_(fastr.core.cardinality.MaxCardinalitySpec
__getstate__() (fastr.core.cardinality.MinCardinalitySpec
    attribute), 93
                hash_(fastr.core.cardinality.MinCardinalitySpec
__getstate__() (fastr.core.cardinality.RangeCardinalitySpec
    attribute), 93
                hash_(fastr.core.cardinality.RangeCardinalitySpec
__getstate__() (fastr.core.cardinality.ValueCardinalitySpec
    attribute), 94
                hash_(fastr.core.dimension.Dimension attribute),
__getstate__() (fastr.core.resourcelimit.ResourceLimit at-
    method), 105
                hash_(fastr.core.resourcelimit.ResourceLimit
                    attribute), 101
                hash_(fastr.core.resourcelimit.ResourceLimit
                    attribute), 101
                hash_(fastr.core.resourcelimit.ResourceLimit
                    attribute), 101
                hash_(fastr.core.resourcelimit.ResourceLimit
                    attribute), 101
```

```

__hash__(fastr.datatypes.BaseDataType attribute), 120
__hash__(fastr.datatypes.URLType attribute), 126
__hash__(fastr.execution.linkrun.LinkRun attribute), 149
__hash__(fastr.execution.networkrun.NetworkRun attribute), 154
__hash__(fastr.execution.noderun.NodeRun attribute), 156
__hash__(fastr.execution.sourcenoderun.SourceNodeRun attribute), 160
__hash__(fastr.planning.inputoutput.Input attribute), 182
__hash__(fastr.planning.inputoutput.Output attribute), 186
__hash__(fastr.planning.inputoutput.SubInput attribute), 188
__hash__(fastr.planning.inputoutput.SubOutput attribute), 190
__hash__(fastr.planning.link.Link attribute), 192
__hash__(fastr.planning.network.Network attribute), 195
__hash__(fastr.planning.node.MacroNode attribute), 201
__hash__(fastr.planning.node.Node attribute), 202
__hash__(fastr.plugins.FastrInterface attribute), 212
__hash__(fastr.plugins.FlowInterface attribute), 215
__hash__(fastr.plugins.NipypeInterface attribute), 220
_iadd__() (fastr.helpers.configmanager.EmptyDefault method), 166
_init__() (fastr.api.ResourceLimit method), 89
_init__() (fastr.core.cardinality.AsCardinalitySpec method), 90
_init__() (fastr.core.cardinality.CardinalitySpec method), 91
_init__() (fastr.core.cardinality.ChoiceCardinalitySpec method), 92
_init__() (fastr.core.cardinality.IntCardinalitySpec method), 92
_init__() (fastr.core.cardinality.MaxCardinalitySpec method), 93
_init__() (fastr.core.cardinality.MinCardinalitySpec method), 93
_init__() (fastr.core.cardinality.RangeCardinalitySpec method), 94
_init__() (fastr.core.cardinality.ValueCardinalitySpec method), 94
_init__() (fastr.core.dimension.Dimension method), 95
_init__() (fastr.core.interface.InterfaceResult method), 98
_init__() (fastr.core.ioplugin.IOPlugin method), 98
_init__() (fastr.core.provenance.Provenance method), 100
__init__() (fastr.core.resourcelimit.ResourceLimit method), 101
__init__() (fastr.core.samples.SampleCollection method), 104
__init__() (fastr.core.samples.SampleValue method), 108
__init__() (fastr.core.target.ProcessUsageCollection method), 109
__init__() (fastr.core.target.TargetResult method), 110
__init__() (fastr.core.tool.Tool method), 111
__init__() (fastr.core.vfs.VirtualFileSystem method), 115
__init__() (fastr.datatypes.BaseDataType method), 120
__init__() (fastr.datatypes.DataType method), 121
__init__() (fastr.datatypes.DataTypeManager method), 122
__init__() (fastr.datatypes.Deferred method), 124
__init__() (fastr.datatypes.EnumType method), 125
__init__() (fastr.datatypes.TypeGroup method), 125
__init__() (fastr.datatypes.URLType method), 126
__init__() (fastr.datatypes.ValueType method), 127
__init__() (fastr.exceptions.FastrError method), 80
__init__() (fastr.exceptions.FastrExecutableNotFoundError method), 81
__init__() (fastr.exceptions.FastrFileNotFoundException method), 81
__init__() (fastr.exceptions.FastrLockNotAcquired method), 82
__init__() (fastr.exceptions.FastrScriptNotFoundError method), 85
__init__() (fastr.exceptions.FastrSerializationError method), 85
__init__() (fastr.execution.environmentmodules.EnvironmentModules method), 128
__init__() (fastr.execution.inputoutputrun.BaseInputRun method), 131
__init__() (fastr.execution.inputoutputrun.InputRun method), 132
__init__() (fastr.execution.inputoutputrun.NamedSubinputRun method), 133
__init__() (fastr.execution.inputoutputrun.OutputRun method), 134
__init__() (fastr.execution.inputoutputrun.SourceOutputRun method), 136
__init__() (fastr.execution.inputoutputrun.SubInputRun method), 138
__init__() (fastr.execution.inputoutputrun.SubOutputRun method), 139
__init__() (fastr.execution.job.InlineJob method), 141
__init__() (fastr.execution.job.Job method), 142
__init__() (fastr.execution.job.JobState method), 146

```

`__init__()` (*fastr.execution.job.SinkJob* method), 147
`__init__()` (*fastr.execution.linkrun.LinkRun* method), 149
`__init__()` (*fastr.execution.macronoderun.MacroNodeRun* method), 151
`__init__()` (*fastr.execution.networkchunker.DefaultNetworkChunk* method), 153
`__init__()` (*fastr.execution.networkrun.NetworkRun* method), 154
`__init__()` (*fastr.execution.noderun.NodeRun* method), 156
`__init__()` (*fastr.execution.sinknoderun.SinkNodeRun* method), 158
`__init__()` (*fastr.execution.sourcenoderun.ConstantNodeRun* method), 161
`__init__()` (*fastr.execution.sourcenoderun.SourceNodeRun* method), 160
`__init__()` (*fastr.helpers.classproperty.ClassPropertyDescriptor* method), 164
`__init__()` (*fastr.helpers.configmanager.Config* method), 164
`__init__()` (*fastr.helpers.configmanager.EmptyDefault* method), 166
`__init__()` (*fastr.helpers.filesynchelperFileSyncHelper* method), 168
`__init__()` (*fastr.helpers.jsonschema.parser.FastrRefResolver* method), 168
`__init__()` (*fastr.helpers.lazy_module.LazyModule* method), 171
`__init__()` (*fastr.helpers.lockfile.DirectoryLock* method), 171
`__init__()` (*fastr.helpers.schematatable.SchemaPrinter* method), 172
`__init__()` (*fastr.planning.inputgroup.InputGroup* method), 175
`__init__()` (*fastr.planning.inputgroupcombiner.BaseInputGroupCombine* method), 176
`__init__()` (*fastr.planning.inputgroupcombiner.MergingInputGroupCombiner* method), 178
`__init__()` (*fastr.planning.inputoutput.BaseInput* method), 179
`__init__()` (*fastr.planning.inputoutput.BaseInputOutput* method), 180
`__init__()` (*fastr.planning.inputoutput.BaseOutput* method), 181
`__init__()` (*fastr.planning.inputoutput.Input* method), 182
`__init__()` (*fastr.planning.inputoutput.NamedSubInput* method), 185
`__init__()` (*fastr.planning.inputoutput.Output* method), 186
`__init__()` (*fastr.planning.inputoutput.SourceOutput* method), 187
`__init__()` (*fastr.planning.inputoutput.SubInput* method), 188
`__init__()` (*fastr.planning.inputoutput.SubOutput* method), 190
`__init__()` (*fastr.planning.link.Link* method), 192
`__init__()` (*fastr.planning.network.Network* method), 195
`__init__()` (*fastr.planning.node.ConstantNode* method), 199
`__init__()` (*fastr.planning.node.FlowNode* method), 200
`__init__()` (*fastr.planning.node.MacroNode* method), 201
`__init__()` (*fastr.planning.node.Node* method), 202
`__init__()` (*fastr.planning.node.SinkNode* method), 204
`__init__()` (*fastr.planning.node.SourceNode* method), 205
`__init__()` (*fastr.plugins.BlockingExecution* method), 206
`__init__()` (*fastr.plugins.CommaSepreatedValueFile* method), 207
`__init__()` (*fastr.plugins.DRMAAExecution* method), 208
`__init__()` (*fastr.plugins.DockerTarget* method), 210
`__init__()` (*fastr.plugins.ElasticsearchReporter* method), 210
`__init__()` (*fastr.plugins.FastrInterface* method), 212
`__init__()` (*fastr.plugins.FileSystem* method), 214
`__init__()` (*fastr.plugins.FlowInterface* method), 215
`__init__()` (*fastr.plugins.HTTPPlugin* method), 217
`__init__()` (*fastr.plugins.LinearExecution* method), 217
`__init__()` (*fastr.plugins.LocalBinaryTarget* method), 219
`__init__()` (*fastr.plugins.MacroTarget* method), 219
`__init__()` (*fastr.plugins.NipypeInterface* method), 220
`__init__()` (*fastr.plugins.Null* method), 221
`__init__()` (*fastr.plugins.PimReporter* method), 221
`__init__()` (*fastr.plugins.ProcessPoolExecution* method), 222
`__init__()` (*fastr.plugins.RQExecution* method), 223
`__init__()` (*fastr.plugins.Reference* method), 223
`__init__()` (*fastr.plugins.S3Filesystem* method), 224
`__init__()` (*fastr.plugins.SingularityTarget* method), 226
`__init__()` (*fastr.plugins.SlurmExecution* method), 226
`__init__()` (*fastr.plugins.StrongrExecution* method), 227
`__init__()` (*fastr.plugins.VirtualFileSystemRegularExpression* method), 229
`__init__()` (*fastr.plugins.VirtualFileSystemValueList* method), 229

```

__init__() (fastr.plugins.XNATStorage method), 231
__init__() (fastr.plugins.executionplugin.ExecutionPlugin len__() (fastr.core.samples.SampleValue method),
method), 234
__init__() (fastr.plugins.managers.executionpluginmanager.ExecutionPluginManager getProcessUsageCollection
method), 236
__init__() (fastr.plugins.managers.interfacemanager.InterfacePluginManager execution.inputoutputrun.SubOutputRun
method), 236
__init__() (fastr.plugins.managers.iopluginmanager.IOPPluginManager) (fastr.planning.inputoutput.SubOutput
method), 236
__init__() (fastr.plugins.managers.objectmanager.ObjectManager) (fastr.plugins.managers.pluginmanager.PluginsView
method), 239
__init__() (fastr.plugins.managers.pluginmanager.PluginManager __() (fastr.api.Input method), 76
method), 239
__lshift__() (fastr.planning.inputoutput.BaseInput
method), 239
__init__() (fastr.plugins.managers.pluginmanager.PluginSubManager __) (fastr.core.cardinality.AnyCardinalitySpec
method), 240
__module__ (fastr.api.ResourceLimit attribute), 89
__init__() (fastr.plugins.managers.pluginmanager.PluginsView __) (fastr.core.cardinality.AnyCardinalitySpec
attribute), 90
__init__() (fastr.plugins.managers.targetmanager.TargetManager __) (fastr.core.cardinality.AsCardinalitySpec
method), 241
__module__ (fastr.core.cardinality.CardinalitySpec attribute), 90
__init__() (fastr.web.api.ObjectUrl method), 249
__init__() (fastr.web.api.Run method), 249
__init__() (fastr.web.api.SubUrl method), 250
__init_subclass__() (fastr.execution.basenoderun.BaseNodeRun
class method), 127
__init_subclass__() (fastr.planning.node.BaseNode class method),
198
__init_subclass__() (in module fastr.__init__), 79
__iter__() (fastr.core.samples.HasSamples method),
103
__iter__() (fastr.core.samples.SampleCollection
method), 104
__iter__() (fastr.core.samples.SampleValue method),
108
__iter__() (fastr.planning.inputgroupcombiner.BaseInputGroupCombiner
method), 176
__iter__() (fastr.planning.inputoutput.BaseInputOutput
method), 180
__iter__() (fastr.plugins.managers.iopluginmanager.IOPPluginManager
method), 237
__iter__() (fastr.plugins.managers.pluginmanager.PluginsView
method), 241
__keytransform__() (fastr.datatypes.DataTypeManager method),
122
__keytransform__() (fastr.plugins.iopluginmanager.IOPPluginManager
method), 237
__keytransform__() (fastr.plugins.managers.objectmanager.ObjectManager
method), 239
__len__() (fastr.core.samples.SampleCollection
method), 104
__len__() (fastr.core.samples.SampleValue method),
108
__len__() (fastr.core.samples.SampleValue method), 109
__len__() (fastr.core.samples.SampleValue method), 140
__len__() (fastr.core.samples.SampleValue method), 190
__len__() (fastr.core.samples.SampleValue method), 241
__lshift__() (fastr.planning.inputoutput.BaseInput
method), 76
__module__ (fastr.core.cardinality.AnyCardinalitySpec
attribute), 90
__module__ (fastr.core.cardinality.CardinalitySpec attribute), 91
__module__ (fastr.core.cardinality.ChoiceCardinalitySpec
attribute), 92
__module__ (fastr.core.cardinality.IntCardinalitySpec
attribute), 92
__module__ (fastr.core.cardinality.MaxCardinalitySpec
attribute), 93
__module__ (fastr.core.cardinality.MinCardinalitySpec
attribute), 93
__module__ (fastr.core.cardinality.RangeCardinalitySpec
attribute), 94
__module__ (fastr.core.cardinality.ValueCardinalitySpec
attribute), 94
__module__ (fastr.core.dimension.Dimension
attribute), 95
__module__ (fastr.core.dimension.ForwardsDimensions
attribute), 95
__module__ (fastr.core.dimension.HasDimensions
attribute), 96
__module__ (fastr.core.interface.InputSpec
attribute), 96
__module__ (fastr.core.interface.Interface
attribute), 97
__module__ (fastr.core.interface.InterfaceResult
attribute), 98
__module__ (fastr.core.interface.OutputSpec
attribute), 98
__module__ (fastr.core.ioplugin.IOPPlugin
attribute), 98
__module__ (fastr.core.provenance.Provenance
attribute), 100
__module__ (fastr.core.resourcelimit.ResourceLimit
attribute), 102
__module__ (fastr.core.samples.ContainsSamples
attribute), 104

```

tribute), 102
__module__(fastr.core.samples.HasSamples attribute), 103
__module__(fastr.core.samples.SampleBaseId attribute), 103
__module__(fastr.core.samples.SampleCollection attribute), 104
__module__(fastr.core.samples.SampleId attribute), 105
__module__(fastr.core.samples.SampleIndex attribute), 105
__module__(fastr.core.samples.SampleItem attribute), 105
__module__(fastr.core.samples.SampleItemBase attribute), 106
__module__(fastr.core.samples.SamplePayload attribute), 107
__module__(fastr.core.samples.SampleValue attribute), 108
__module__(fastr.core.target.ProcessUsageCollection attribute), 109
__module__(fastr.core.target.SubprocessBasedTarget attribute), 109
__module__(fastr.core.target.SystemUsageInfo attribute), 109
__module__(fastr.core.target.Target attribute), 110
__module__(fastr.core.target.TargetResult attribute), 111
__module__(fastr.core.tool.Tool attribute), 111
__module__(fastr.core.version.Version attribute), 114
__module__(fastr.core.vfs.VirtualFileSystem attribute), 115
__module__(fastr.datatypes.AnyFile attribute), 119
__module__(fastr.datatypes.AnyType attribute), 119
__module__(fastr.datatypes.BaseDataType attribute), 120
__module__(fastr.datatypes.DataType attribute), 121
__module__(fastr.datatypes.DataTypeManager attribute), 122
__module__(fastr.datatypes.Deferred attribute), 124
__module__(fastr.datatypes.EnumType attribute), 125
__module__(fastr.datatypes.TypeGroup attribute), 125
__module__(fastr.datatypes.URLType attribute), 126
__module__(fastr.datatypes.ValueType attribute), 127
__module__(fastr.exceptions.FastrAttributeError attribute), 79
__module__(fastr.exceptions.FastrCannotChangeAttributeError attribute), 80
__module__(fastr.exceptions.FastrCardinalityError attribute), 80
__module__(fastr.exceptions.FastrCollectorError attribute), 80
__module__(fastr.exceptions.FastrDataTypeFileNotReadable attribute), 80
__module__(fastr.exceptions.FastrDataTypeMismatchError attribute), 80
__module__(fastr.exceptions.FastrDataTypeNotAvailableError attribute), 80
__module__(fastr.exceptions.FastrDataTypeNotInstantiableError attribute), 80
__module__(fastr.exceptions.FastrDataTypeValueError attribute), 80
__module__(fastr.exceptions.FastrError attribute), 81
__module__(fastr.exceptions.FastrErrorInSubprocess attribute), 81
__module__(fastr.exceptions.FastrExecutableNotFoundError attribute), 81
__module__(fastr.exceptions.FastrExecutionError attribute), 81
__module__(fastr.exceptions.FastrFileNotFoundException attribute), 81
__module__(fastr.exceptions.FastrIOError attribute), 82
__module__(fastr.exceptions.FastrImportError attribute), 82
__module__(fastr.exceptions.FastrIndexError attribute), 82
__module__(fastr.exceptions.FastrIndexNonexistent attribute), 82
__module__(fastr.exceptions.FastrKeyError attribute), 82
__module__(fastr.exceptions.FastrLockNotAcquired attribute), 82
__module__(fastr.exceptions.FastrLookupError attribute), 82
__module__(fastr.exceptions.FastrMountUnknownError attribute), 82
__module__(fastr.exceptions.FastrNetworkMismatchError attribute), 83
__module__(fastr.exceptions.FastrNetworkUnknownError attribute), 83
__module__(fastr.exceptions.FastrNoValidTargetException attribute), 83
__module__(fastr.exceptions.FastrNodeAlreadyPreparedError attribute), 83
__module__(fastr.exceptions.FastrNodeNotPreparedError attribute), 83
__module__(fastr.exceptions.FastrNodeNotValidError attribute), 83
__module__(fastr.exceptions.FastrNotExecutableError attribute), 83
__module__(fastr.exceptions.FastrNotImplementedError attribute), 83
__module__(fastr.exceptions.FastrOSError attribute), 83
__module__(fastr.exceptions.FastrObjectUnknownError attribute), 84
__module__(fastr.exceptions.FastrOptionalModuleNotAvailableError attribute), 84

```

        attribute), 84
__module__(fastr.exceptions.FastrOutputValidationError __module__(fastr.execution.basenoderun.BaseNodeRun
        attribute), 84                                         attribute), 128
__module__(fastr.exceptions.FastrParentMismatchError __module__(fastr.execution.environmentmodules.EnvironmentModules
        attribute), 84                                         attribute), 128
__module__(fastr.exceptions.FastrPluginCapabilityNotImplemented __module__(fastr.execution.environmentmodules.ModuleSystem
        attribute), 84                                         attribute), 129
__module__(fastr.exceptions.FastrPluginNotAvailable __module__(fastr.execution.flownoderun.AdvancedFlowNodeRun
        attribute), 84                                         attribute), 130
__module__(fastr.exceptions.FastrPluginNotLoaded __module__(fastr.execution.flownoderun.FlowNodeRun
        attribute), 84                                         attribute), 130
__module__(fastr.exceptions.FastrResultFileNotFoundException __module__(fastr.execution.inputoutputrun.AdvancedFlowOutputRun
        attribute), 84                                         attribute), 130
__module__(fastr.exceptions.FastrScriptNotFoundError __module__(fastr.execution.inputoutputrun.BaseInputRun
        attribute), 85                                         attribute), 131
__module__(fastr.exceptions.FastrSerializationError __module__(fastr.execution.inputoutputrun.InputRun
        attribute), 85                                         attribute), 132
__module__(fastr.exceptions.FastrSerializationIgnoreDefaultError __module__(fastr.execution.inputoutputrun.MacroOutputRun
        attribute), 85                                         attribute), 133
__module__(fastr.exceptions.FastrSerializationInvalidDataError __module__(fastr.execution.inputoutputrun.NamedSubinputRun
        attribute), 85                                         attribute), 133
__module__(fastr.exceptions.FastrSerializationMethodError __module__(fastr.execution.inputoutputrun.OutputRun
        attribute), 85                                         attribute), 135
__module__(fastr.exceptions.FastrSinkDataUnavailableError __module__(fastr.execution.inputoutputrun.SourceOutputRun
        attribute), 85                                         attribute), 137
__module__(fastr.exceptions.FastrSizeInvalidError at- __module__(fastr.execution.inputoutputrun.SubInputRun
        tribute), 86                                         attribute), 138
__module__(fastr.exceptions.FastrSizeMismatchError __module__(fastr.execution.inputoutputrun.SubOutputRun
        attribute), 86                                         attribute), 140
__module__(fastr.exceptions.FastrSizeUnknownError __module__(fastr.execution.job.InlineJob
        attribute), 86                                         attribute), 141
__module__(fastr.exceptions.FastrSourceDataUnavailableError __module__(fastr.execution.job.Job
        attribute), 86                                         attribute), 142
__module__(fastr.exceptions.FastrStateError at- __module__(fastr.execution.job.JobCleanupLevel
        tribute), 86                                         attribute), 145
__module__(fastr.exceptions.FastrSubprocessNotFinished __module__(fastr.execution.job.JobState
        attribute), 86                                         attribute), 147
__module__(fastr.exceptions.FastrToolNotFoundError __module__(fastr.execution.job.SinkJob
        attribute), 86                                         attribute), 147
__module__(fastr.exceptions.FastrToolTargetNotFound __module__(fastr.execution.job.SourceJob
        attribute), 86                                         attribute), 148
__module__(fastr.exceptions.FastrToolUnknownError __module__(fastr.execution.linkrun.LinkRun
        attribute), 86                                         attribute), 150
__module__(fastr.exceptions.FastrToolVersionError __module__(fastr.execution.macronoderun.MacroNodeRun
        attribute), 87                                         attribute), 152
__module__(fastr.exceptions.FastrTypeError at- __module__(fastr.execution.networkanalyzer.DefaultNetworkAnalyzer
        tribute), 87                                         attribute), 152
__module__(fastr.exceptions.FastrUnknownURLSchemeError __module__(fastr.execution.networkanalyzer.NetworkAnalyzer
        attribute), 87                                         attribute), 152
__module__(fastr.exceptions.FastrValueError at- __module__(fastr.execution.networkchunker.DefaultNetworkChunker
        tribute), 87                                         attribute), 153
__module__(fastr.exceptions.FastrVersionInvalidError __module__(fastr.execution.networkchunker.NetworkChunker
        attribute), 87                                         attribute), 153
__module__(fastr.exceptions.FastrVersionMismatchError __module__(fastr.execution.networkrun.NetworkRun
        attribute), 87                                         attribute), 154

```

```
__module__ (fastr.execution.noderun.NodeRun  at- __module__ (fastr.planning.inputoutput.SourceOutput
tribute), 156                                attribute), 188
__module__ (fastr.execution.sinknoderun.SinkNodeRun __module__ (fastr.planning.inputoutput.SubInput at-
attribute), 158                                tribute), 189
__module__ (fastr.execution.sourcenoderun.ConstantNodeRun __module__ (fastr.planning.inputoutput.SubOutput at-
attribute), 162                                tribute), 191
__module__ (fastr.execution.sourcenoderun.SourceNodeRun __module__ (fastr.planning.link.Link attribute), 193
attribute), 160                                __module__ (fastr.planning.network.Network at-
attribute), 195
__module__ (fastr.helpers.classproperty.ClassPropertyDescriptor __module__ (fastr.planning.node.AdvancedFlowNode
attribute), 164                                attribute), 198
__module__ (fastr.helpers.configmanager.Config at- __module__ (fastr.planning.node.BaseNode attribute),
tribute), 164                                198
__module__ (fastr.helpers.configmanager.EmptyDefault __module__ (fastr.planning.node.ConstantNode
attribute), 166                                attribute), 199
__module__ (fastr.helpers.events.EventType attribute), __module__ (fastr.planning.node.FlowNode attribute),
167                                200
__module__ (fastr.helpers.events.FastrLogEventHandler __module__ (fastr.planning.node.InputDict attribute),
attribute), 167                                200
__module__ (fastr.helpers.filesynchelperFileSyncHelper __module__ (fastr.planning.node.MacroNode attribute),
attribute), 168                                201
__module__ (fastr.helpers.jsonschemasparser.FastrRefResolver __module__ (fastr.planning.node.Node attribute),
attribute), 169                                202
__module__ (fastr.helpers.lazy_module.LazyModule __module__ (fastr.planning.node.OutputDict attribute),
attribute), 171                                204
__module__ (fastr.helpers.lockfile.DirectoryLock at- __module__ (fastr.planning.node.SinkNode attribute),
tribute), 171                                204
__module__ (fastr.helpers.schematatable.SchemaPrinter __module__ (fastr.planning.node.SourceNode attribute),
attribute), 172                                205
__module__ (fastr.planning.inputgroup.InputGroup at- __module__ (fastr.plugins.BlockingExecution attribute),
tribute), 175                                206
__module__ (fastr.planning.inputgroupcombiner.BaseInputGroupCombi __module__ (fastr.plugins.CommaSeperatedValueFile
attribute), 176                                attribute), 207
__module__ (fastr.planning.inputgroupcombiner.DefaultInputGroupCombi __module__ (fastr.plugins.CrossValidation attribute),
attribute), 177                                208
__module__ (fastr.planning.inputgroupcombiner.MergingInputGroupCombi __module__ (fastr.plugins.DRMAAExecution attribute),
attribute), 178                                209
__module__ (fastr.planning.inputoutput.AdvancedFlowOutput __module__ (fastr.plugins.DockerTarget attribute),
attribute), 179                                210
__module__ (fastr.planning.inputoutput.BaseInput at- __module__ (fastr.plugins.ElasticsearchReporter attribute),
tribute), 179                                210
__module__ (fastr.planning.inputoutput.BaseInputOutput __module__ (fastr.plugins.FastrInterface attribute),
attribute), 180                                213
__module__ (fastr.planning.inputoutput.BaseOutput __module__ (fastr.plugins.FileSystem attribute), 214
attribute), 182                                __module__ (fastr.plugins.FlowInterface attribute),
attribute), 182                                216
__module__ (fastr.planning.inputoutput.Input at- __module__ (fastr.plugins.HTTPPlugin attribute), 217
tribute), 183                                __module__ (fastr.plugins.LinearExecution attribute),
attribute), 183                                217
__module__ (fastr.planning.inputoutput.MacroInput __module__ (fastr.plugins.LocalBinaryTarget attribute),
attribute), 184                                219
__module__ (fastr.planning.inputoutput.MacroOutput __module__ (fastr.plugins.MacroTarget attribute), 219
attribute), 185                                __module__ (fastr.plugins.NipypeInterface attribute),
attribute), 185                                220
__module__ (fastr.planning.inputoutput.NamedSubInput __module__ (fastr.plugins.Null attribute), 221
attribute), 185
```

__module__(fastr.plugins.PimReporter attribute), 222
 __module__(fastr.plugins.ProcessPoolExecution attribute), 222
 __module__(fastr.plugins.RQExecution attribute), 223
 __module__(fastr.plugins.Reference attribute), 224
 __module__(fastr.plugins.S3Filesystem attribute), 224
 __module__(fastr.plugins.SimpleReport attribute), 225
 __module__(fastr.plugins.SingularityTarget attribute), 226
 __module__(fastr.plugins.SlurmExecution attribute), 226
 __module__(fastr.plugins.StrongrExecution attribute), 227
 __module__(fastr.plugins.VirtualFileSystem attribute), 228
 __module__(fastr.plugins.VirtualFileSystemRegularExpression attribute), 229
 __module__(fastr.plugins.VirtualFileSystemValueList attribute), 229
 __module__(fastr.plugins.XNATStorage attribute), 231
 __module__(fastr.plugins.executionplugin.ExecutionPlugin attribute), 234
 __module__(fastr.plugins.executionplugin.JobAction attribute), 235
 __module__(fastr.plugins.managers.executionpluginmanager.ExecutionPluginManager attribute), 236
 __module__(fastr.plugins.managers.interfacemanager.InterfacePluginManager attribute), 236
 __module__(fastr.plugins.managers.iopluginmanager.IOPluginManager attribute), 237
 __module__(fastr.plugins.managers.networkmanager.NetworkManager attribute), 238
 __module__(fastr.plugins.managers.objectmanager.ObjectManager attribute), 239
 __module__(fastr.plugins.managers.pluginmanager.PluginManager attribute), 240
 __module__(fastr.plugins.managers.pluginmanager.PluginSubManager attribute), 240
 __module__(fastr.plugins.managers.pluginmanager.PluginsView attribute), 241
 __module__(fastr.plugins.managers.targetmanager.TargetManager attribute), 241
 __module__(fastr.plugins.managers.toolmanager.ToolManager attribute), 241
 __module__(fastr.plugins.reportingplugin.ReportingPlugin attribute), 235
 __module__(fastr.utils.cmd.upgrade.FastrNamespaceType attribute), 247
 __module__(fastr.plugins.managers.targetmanager.TargetManager static method), 247
 __module__(fastr.plugins.managers.toolmanager.ToolManager add() method), 103
 __module__(fastr.plugins.reportingplugin.ReportingPlugin add() method), 108
 __module__(fastr.utils.cmd.upgrade.FastrNamespaceType add() method), 166
 __module__(fastr.utils.cmd.upgrade.dummy_container attribute), 247
 __module__(fastr.web.api.NetworkApi attribute), 248
 __module__(fastr.web.api.NetworkListApi attribute), 249
 __module__(fastr.web.api.ObjectUrl attribute), 249
 __module__(fastr.web.api.Run attribute), 249
 __module__(fastr.web.api.RunApi attribute), 249
 __module__(fastr.web.api.RunListApi attribute), 250
 __module__(fastr.web.api.StatusApi attribute), 250
 __module__(fastr.web.api.SubUrl attribute), 250
 __module__(fastr.web.api.ToolApi attribute), 251
 __module__(fastr.web.api.ToolListApi attribute), 251
 __ne__() (fastr.api.ResourceLimit method), 89
 __ne__() (fastr.core.cardinality.CardinalitySpec method), 91
 __ne__() (fastr.core.dimension.Dimension method), 95
 __ne__() (fastr.core.resourcelimit.ResourceLimit method), 102
 __ne__() (fastr.datatypes.BaseDataType method), 120
 __ne__() (fastr.execution.networkrun.NetworkRun method), 154
 __ne__() (fastr.planning.inputoutput.BaseInputOutput method), 180
 __ne__() (fastr.planning.network.Network method), 195
 __ne__() (fastr.planning.node.Node method), 202
 __new__() (fastr.core.interface.InputSpec static method), 97
 __new__() (fastr.core.interface.OutputSpec static method), 98
 __new__() (fastr.core.samples.SampleBaseId static method), 103
 __new__() (fastr.core.samples.SampleItem static method), 103
 __new__() (fastr.core.samples.SampleItemBase static method), 106
 __new__() (fastr.core.samples.SamplePayload static method), 106
 __new__() (fastr.core.target.SystemUsageInfo static method), 107
 __new__() (fastr.core.version.Version static method), 109
 __new__() (fastr.core.version.Version static method), 109
 __new__() (fastr.datatypes.TypeGroup static method), 125
 __new__() (fastr.utils.cmd.upgrade.FastrNamespaceType static method), 125
 __new__() (in module fastr.__init__), 79
 __new__() (fastr.core.samples.SampleBaseId static method), 103
 __new__() (fastr.core.samples.SampleValue static method), 108
 __new__() (fastr.helpers.configmanager.EmptyDefault method), 166
 __reduce__() (in module fastr.__init__), 79
 __reduce_ex__() (fastr.datatypes.BaseDataType static method), 120
 __reduce_ex__() (fastr.datatypes.EnumType static method), 120

```
        method), 125
__reduce_ex__(in module fastr.__init__), 79
__repr__() (fastr.core.cardinality.CardinalitySpec
            method), 91
__repr__() (fastr.core.dimension.Dimension method),
            95
__repr__() (fastr.core.samples.SampleBaseId
            method), 103
__repr__() (fastr.core.samples.SampleCollection
            method), 104
__repr__() (fastr.core.samples.SampleIndex method),
            105
__repr__() (fastr.core.samples.SampleItemBase
            method), 106
__repr__() (fastr.core.samples.SampleValue method),
            108
__repr__() (fastr.core.target.SystemUsageInfo
            method), 110
__repr__() (fastr.core.tool.Tool method), 112
__repr__() (fastr.core.version.Version method), 114
__repr__() (fastr.datatypes.BaseDataType method),
            120
__repr__() (fastr.datatypes.Deferred method), 124
__repr__() (fastr.exceptions.FastrError method), 81
__repr__() (fastr.exceptions.FastrSerializationError
            method), 85
__repr__() (fastr.execution.environmentmodules.Environment
            method), 128
__repr__() (fastr.execution.job.Job method), 142
__repr__() (fastr.execution.job.SinkJob method), 147
__repr__() (fastr.execution.job.SourceJob method),
            148
__repr__() (fastr.execution.linkrun.LinkRun method),
            150
__repr__() (fastr.execution.networkrun.NetworkRun
            method), 154
__repr__() (fastr.execution.noderun.NodeRun
            method), 156
__repr__() (fastr.helpers.configmanager.Config
            method), 165
__repr__() (fastr.helpers.lazy_module.LazyModule
            method), 171
__repr__() (fastr.planning.inputoutput.BaseInputOutput
            method), 180
__repr__() (fastr.planning.link.Link method), 193
__repr__() (fastr.planning.network.Network method),
            195
__repr__() (fastr.planning.node.Node method), 202
__repr__() (fastr.utils.cmd.upgrade.FastrNamespaceType
            method), 247
__rrshift__() (fastr.api.Input method), 76
__rrshift__() (fastr.planning.inputoutput.BaseInput
            method), 179
__schema_type__ (fastr.web.api.ObjectUrl at-
                    tribute), 249
__schema_type__ (fastr.web.api.SubUrl attribute),
            250
__setitem__() (fastr.core.samples.ContainsSamples
            method), 102
__setitem__() (fastr.core.samples.SampleCollection
            method), 104
__setitem__() (fastr.core.samples.SampleValue
            method), 108
__setitem__() (fastr.execution.inputoutputrun.OutputRun
            method), 135
__setitem__() (fastr.execution.inputoutputrun.SourceOutputRun
            method), 137
__setitem__() (fastr.execution.inputoutputrun.SubOutputRun
            method), 140
__setitem__() (fastr.helpers.configmanager.EmptyDefault
            method), 166
__setitem__() (fastr.planning.inputgroup.InputGroup
            method), 175
__setitem__() (fastr.planning.inputoutput.Input
            method), 183
__setitem__() (fastr.planning.node.InputDict
            method), 200
__setitem__() (fastr.planning.node.OutputDict
            method), 204
__setitem__() (fastr.plugins.managers.pluginmanager.PluginManager
            method), 240
__setitem__() (fastr.plugins.managers.pluginmanager.PluginsView
            method), 241
__setstate__() (fastr.api.ResourceLimit method),
            89
__setstate__() (fastr.core.interface.Interface
            method), 97
__setstate__() (fastr.core.resourcelimit.ResourceLimit
            method), 102
__setstate__() (fastr.core.samples.SampleValue
            method), 108
__setstate__() (fastr.core.tool.Tool method), 112
__setstate__() (fastr.datatypes.BaseDataType
            method), 120
__setstate__() (fastr.datatypes.Deferred method),
            124
__setstate__() (fastr.execution.inputoutputrun.InputRun
            method), 132
__setstate__() (fastr.execution.inputoutputrun.OutputRun
            method), 135
__setstate__() (fastr.execution.inputoutputrun.SubInputRun
            method), 138
__setstate__() (fastr.execution.inputoutputrun.SubOutputRun
            method), 140
__setstate__() (fastr.execution.job.Job method),
            142
__setstate__() (fastr.execution.linkrun.LinkRun
            method), 150
```

__setstate__(*fastr.execution.macronoderun.MacroNodeRun*) (*fastr.core.cardinality.AnyCardinalitySpec method*), 152
 __setstate__(*fastr.execution.networkrun.NetworkRun*) (*fastr.core.cardinality.AsCardinalitySpec method*), 154
 __setstate__(*fastr.execution.noderun.NodeRun*) (*fastr.core.cardinality.CardinalitySpec method*), 156
 __setstate__(*fastr.execution.sinknoderun.SinkNodeRun*) (*fastr.core.cardinality.ChoiceCardinalitySpec method*), 158
 __setstate__(*fastr.execution.sourcenoderun.ConstantNodeRun*) (*fastr.core.cardinality.IntCardinalitySpec method*), 162
 __setstate__(*fastr.execution.sourcenoderun.SourceNodeRun*) (*fastr.core.cardinality.MaxCardinalitySpec method*), 160
 __setstate__(*fastr.planning.inputoutput.BaseInputOutput*) (*fastr.core.cardinality.MinCardinalitySpec method*), 180
 __setstate__(*fastr.planning.inputoutput.Input*) (*fastr.core.cardinality.RangeCardinalitySpec method*), 183
 __setstate__(*fastr.planning.inputoutput.Output*) (*fastr.core.cardinality.ValueCardinalitySpec method*), 186
 __setstate__(*fastr.planning.inputoutput.SubInput*) (*fastr.core.samples.SampleBaseId method*), 189
 __setstate__(*fastr.planning.inputoutput.SubOutput*) (*fastr.core.samples.SampleIndex method*), 191
 __setstate__(*fastr.planning.link.Link*) (*fastr.core.tool.Tool method*), 193
 __setstate__(*fastr.planning.network.Network*) (*fastr.core.version.Version method*), 195
 __setstate__(*fastr.planning.node.ConstantNode*) (*fastr.datatypes.BaseDataType method*), 199
 __setstate__(*fastr.planning.node.MacroNode*) (*fastr.exceptions.FastrError method*), 201
 __setstate__(*fastr.planning.node.Node*) (*fastr.exceptions.FastrExecutableNotFoundError method*), 202
 __setstate__(*fastr.planning.node.SinkNode*) (*fastr.exceptions.FastrScriptNotFoundError method*), 204
 __setstate__(*fastr.planning.node.SourceNode*) (*fastr.exceptions.FastrSerializationError method*), 205
 __setstate__(*fastr.plugins.FastrInterface*) (*fastr.execution.inputoutputrun.InputRun method*), 213
 __setstate__(*fastr.plugins.FlowInterface*) (*fastr.execution.inputoutputrun.NamedSubinputRun method*), 216
 __setstate__(*fastr.plugins.NipypeInterface*) (*fastr.execution.inputoutputrun.OutputRun method*), 220
 sizeof(*in module fastr.__init__*), 79
 slotnames(*fastr.web.api.ObjectUrl attribute*), 249
 slots(*fastr.api.ResourceLimit attribute*), 89
 slots(*fastr.core.dimension.Dimension attribute*), 95
 slots(*fastr.core.resourcelimit.ResourceLimit attribute*), 102
 slots(*fastr.core.target.SystemUsageInfo attribute*), 110
 slots(*fastr.utils.cmd.upgrade.FastrNamespaceType attribute*), 247
 str(*fastr.core.cardinality.AnyCardinalitySpec method*), 90
 str(*fastr.core.cardinality.AsCardinalitySpec method*), 90
 str(*fastr.core.cardinality.CardinalitySpec method*), 91
 str(*fastr.core.cardinality.ChoiceCardinalitySpec method*), 92
 str(*fastr.core.cardinality.IntCardinalitySpec method*), 92
 str(*fastr.core.cardinality.MaxCardinalitySpec method*), 93
 str(*fastr.core.cardinality.MinCardinalitySpec method*), 93
 str(*fastr.core.cardinality.RangeCardinalitySpec method*), 94
 str(*fastr.core.cardinality.ValueCardinalitySpec method*), 94
 str(*fastr.core.samples.SampleBaseId method*), 103
 str(*fastr.core.samples.SampleIndex method*), 105
 str(*fastr.core.tool.Tool method*), 112
 str(*fastr.core.version.Version method*), 114
 str(*fastr.datatypes.BaseDataType method*), 120
 str(*fastr.exceptions.FastrError method*), 81
 str(*fastr.exceptions.FastrExecutableNotFoundError method*), 81
 str(*fastr.exceptions.FastrScriptNotFoundError method*), 85
 str(*fastr.exceptions.FastrSerializationError method*), 85
 str(*fastr.execution.inputoutputrun.InputRun method*), 132
 str(*fastr.execution.inputoutputrun.NamedSubinputRun method*), 134
 str(*fastr.execution.inputoutputrun.OutputRun method*), 135
 str(*fastr.execution.inputoutputrun.SubinputRun method*), 138
 str(*fastr.execution.inputoutputrun.SuboutputRun method*), 140
 str(*fastr.execution.noderun.NodeRun method*), 156
 str(*fastr.helpers.schematatable.SchemaPrinter method*), 172
 str(*fastr.planning.inputoutput.Input method*), 183
 str(*fastr.planning.inputoutput.NamedSubinput method*), 185
 str(*fastr.planning.inputoutput.Output method*), 187
 str(*fastr.planning.inputoutput.Subinput method*)

method), 189
__str__() (fastr.planning.inputoutput.SubOutput
 method), 191
__str__() (fastr.planning.node.Node method), 202
__subclasshook__() (in module fastr.__init__), 79
__updatefunc__() (fastr.planning.inputgroup.InputGroup
 method), 175
__updatetriggers__
 (fastr.planning.inputgroup.InputGroup
 attribute), 176
__weakref__ (fastr.core.cardinality.CardinalitySpec
 attribute), 91
__weakref__ (fastr.core.dimension.HasDimensions
 attribute), 96
__weakref__ (fastr.core.interface.InterfaceResult
 attribute), 98
__weakref__ (fastr.core.provenance.Provenance
 attribute), 101
__weakref__ (fastr.core.samples.SampleCollection
 attribute), 105
__weakref__ (fastr.core.samples.SampleValue
 attribute), 108
__weakref__ (fastr.core.target.ProcessUsageCollection
 attribute), 109
__weakref__ (fastr.core.target.TargetResult attribute),
 111
__weakref__ (fastr.core.vfs.VirtualFileSystem
 attribute), 115
__weakref__ (fastr.exceptions.FastrError attribute),
 81
__weakref__ (fastr.exceptions.FastrIOError
 attribute), 82
__weakref__ (fastr.exceptions.FastrImportError
 attribute), 82
__weakref__ (fastr.exceptions.FastrOSError
 attribute), 83
__weakref__ (fastr.execution.environmentmodules.Environment
 attribute), 128
__weakref__ (fastr.execution.networkanalyzer.NetworkAnalyzer
 attribute), 152
__weakref__ (fastr.execution.networkchunker.NetworkChunker
 attribute), 153
__weakref__ (fastr.helpers.classproperty.ClassPropertyDescriptor
 attribute), 164
__weakref__ (fastr.helpers.configmanager.Config
 attribute), 165
__weakref__ (fastr.helpers.configmanager.EmptyDefault
 attribute), 166
__weakref__ (fastr.helpers.filesynchelperFileSyncHelper
 attribute), 168
__weakref__ (fastr.helpers.lockfile.DirectoryLock
 attribute), 171
__weakref__ (fastr.helpers.schematotable.SchemaPrinter
 attribute), 172
 __weakref__ (fastr.plugins.managers.pluginmanager.PluginsView
 attribute), 241
 __weakref__ (fastr.utils.cmd.upgrade.dummy_container
 attribute), 247
 __weakref__ (fastr.web.api.Run attribute), 249

A

abort () (fastr.execution.networkrun.NetworkRun
 method), 154
abort () (fastr.web.api.Run method), 249
abstract (fastr.core.vfs.VirtualFileSystem attribute),
 115
acquire () (fastr.helpers.lockfile.DirectoryLock
 method), 171
action () (fastr.datatypes.DataType method), 121
activate () (fastr.plugins.ElasticsearchReporter
 method), 210
activate () (fastr.plugins.PimReporter method), 222
activate () (fastr.plugins.reportingplugin.ReportingPlugin
 method), 235
activity () (fastr.core.provenance.Provenance
 method), 101
add_link () (fastr.planning.network.Network method),
 195
add_node () (fastr.planning.network.Network method),
 195
add_parser_doc_link () (in module
 fastr.utils.cmd), 244
add_stepid() (fastr.planning.network.Network
 method), 195
AdvancedFlowNode (class in fastr.planning.node),
 198
AdvancedFlowNodeRun (class in
 fastr.execution.flownoderun), 130
AdvancedFlowOutput (class in
 fastr.planning.inputoutput), 178
AdvancedFlowOutputRun (class in
 fastr.execution.inputoutputrun), 130
AdvancedFlowNodes (class in
 fastr.execution.environmentmodules.Environment
 attribute), 128
AdvancedFlowOutputRun (class in
 fastr.execution.inputoutputrun), 130
aggregate () (fastr.core.target.ProcessUsageCollection
 method), 109
any_of_draft4 () (in module
 fastr.helpers.jsonschemasmaparser), 169
AnyCardinalitySpec (class in
 fastr.core.cardinality), 90
AnyFile (class in fastr.datatypes), 119

AnyType (*class in fastr.datatypes*), 119
append() (*fastr.api.Input method*), 76
append() (*fastr.core.target.ProcessUsageCollection method*), 109
append() (*fastr.helpers.configmanager.EmptyDefault method*), 166
append() (*fastr.planning.inputoutput.Input method*), 183
as_dict() (*fastr.core.target.TargetResult method*), 111
AsCardinalitySpec (*class in fastr.core.cardinality*), 90
asdict() (*fastr.core.interface.InputSpec method*), 97
asdict() (*fastr.core.interface.OutputSpec method*), 98
asdict() (*fastr.helpers.configmanager.EmptyDefault method*), 166
aslist() (*fastr.helpers.configmanager.EmptyDefault method*), 166
authors (*fastr.core.tool.Tool attribute*), 112
automatic() (*fastr.execution.inputoutputrun.OutputRun property*), 135
automatic() (*fastr.planning.inputoutput.BaseOutput property*), 182
avail() (*fastr.execution.environmentmodules.EnvironmentModules method*), 128
avail_modules() (*fastr.execution.environmentmodules.EnvironmentModules property*), 128

B

BaseDataType (*class in fastr.datatypes*), 119
BaseInput (*class in fastr.planning.inputoutput*), 179
BaseInputGroupCombiner (*class in fastr.planning.inputgroupcombiner*), 176
BaseInputOutput (*class in fastr.planning.inputoutput*), 180
BaseInputRun (*class in fastr.execution.inputoutputrun*), 130
basename() (*in module fastr.data.url*), 118
BaseNode (*class in fastr.planning.node*), 198
BaseNodeRun (*class in fastr.execution.basenoderun*), 127
BaseOutput (*class in fastr.planning.inputoutput*), 181
blocking() (*fastr.execution.flownoderun.FlowNodeRun property*), 130
blocking() (*fastr.execution.noderun.NodeRun property*), 156
blocking() (*fastr.planning.inputoutput.BaseOutput property*), 182
blocking() (*fastr.planning.node.FlowNode property*), 200
blocking() (*fastr.planning.node.Node property*), 202
BlockingExecution (*class in fastr.plugins*), 206
build() (*fastr.core.version.Version property*), 114

C

calculate_execution_cardinality()
(fastr.core.cardinality.AsCardinalitySpec method), 90
calculate_execution_cardinality()
(fastr.core.cardinality.CardinalitySpec method), 91
calculate_execution_cardinality()
(fastr.core.cardinality.IntCardinalitySpec method), 92
calculate_execution_cardinality()
(fastr.core.cardinality.ValueCardinalitySpec method), 94
calculate_job_cardinality()
(fastr.core.cardinality.AsCardinalitySpec method), 90
calculate_job_cardinality()
(fastr.core.cardinality.CardinalitySpec method), 91
calculate_job_cardinality()
(fastr.core.cardinality.IntCardinalitySpec method), 93
calculate_job_cardinality()
(fastr.core.cardinality.ValueCardinalitySpec method), 94
calculate_planning_cardinality()
(fastr.core.cardinality.AsCardinalitySpec method), 91
calculate_planning_cardinality()
(fastr.core.cardinality.CardinalitySpec method), 92
calculate_planning_cardinality()
(fastr.core.cardinality.IntCardinalitySpec method), 93
call_subprocess()
(fastr.core.target.SubprocessBasedTarget method), 109
cancel (*fastr.plugins.executionplugin.JobAction attribute*), 235
cancel_job() (*fastr.plugins.executionplugin.ExecutionPlugin method*), 234
cancelled (*fastr.execution.job.JobState attribute*), 147
CANCELS_DEPENDENCIES
(fastr.plugins.DRMAAExecution attribute), 208
CANCELS_DEPENDENCIES
(fastr.plugins.executionplugin.ExecutionPlugin attribute), 233
cardinality() (*fastr.core.samples.SampleItemBase property*), 106
cardinality() (*fastr.execution.inputoutputrun.InputRun method*), 132
cardinality() (*fastr.execution.inputoutputrun.OutputRun method*), 135

cardinality() (*fastr.execution.inputoutputrun.SourceOutput*) (*fastr.plugins.FastrInterface method*), 137
cardinality() (*fastr.execution.inputoutputrun.SubInputRun*) (*fastr.tools.CheckTool*), 246
cardinality() (*fastr.execution.inputoutputrun.SubOutputRun*) (*fastr.datatypes.BaseDataType method*), 120
cardinality() (*fastr.execution.linkrun.LinkRun*) (*fastr.datatypes.Deferred method*), 124
cardinality() (*fastr.execution.linkrun.LinkRun*) (*fastr.datatypes.URLType method*), 126
cardinality() (*fastr.planning.inputoutput.BaseInputOutput*) (*fastr.helpers.checksum*), 162
cardinality() (*fastr.planning.inputoutput.Input*) (*fastr.helpers.checksum_directory*), 163
cardinality() (*fastr.planning.inputoutput.Output*) (*fastr.core.cardinality*), 92
cardinality() (*fastr.planning.inputoutput.SourceOutput*) (*fastr.core.networkchunker.DefaultNetworkChunker method*), 153
cardinality() (*fastr.planning.inputoutput.SubInput*) (*fastr.core.networkchunker.NetworkChunker method*), 153
cardinality() (*fastr.planning.inputoutput.SubOutput*) (*fastr.core.tool.Tool attribute*), 112
cardinality() (*fastr.planning.link.Link*) (*fastr.helpers.classproperty*), 164
cardinality_from_nargs() (*fastr.helpers.classproperty*), 164
CardinalitySpec (class in *fastr.core.cardinality*), 91
cast() (*fastr.core.samples.SampleValue method*), 108
cast_to_type() (*fastr.execution.job.Job static method*), 142
check_cardinality() (*fastr.execution.job.Job method*), 206
check_cardinality() (*fastr.planning.inputoutput.BaseInput method*), 179
check_cardinality() (*fastr.planning.inputoutput.BaseInputOutput method*), 234
check_finished() (*fastr.plugins.RQExecution method*), 223
check_finished() (*fastr.plugins.StrongrExecution method*), 227
check_id() (*fastr.execution.networkrun.NetworkRun method*), 154
check_id() (*fastr.planning.network.Network method*), 196
check_input_id() (*fastr.plugins.FastrInterface method*), 213
check_job_requirements() (*fastr.plugins.executionplugin.ExecutionPlugin method*), 234
check_job_status() (*fastr.plugins.executionplugin.ExecutionPlugin method*), 234
check_network() (*in module fastr.utils.cmd.test*), 246
check_networks() (*in module fastr.utils.cmd.test*), 246
checksum() (*fastr.datatypes.Defered method*), 124
checksum() (*fastr.datatypes.URLType method*), 126
checksum() (*fastr.helpers.checksum*), 162
checksum_directory() (*in module fastr.helpers.checksum*), 163
ChoiceCardinalitySpec (class in *fastr.core.cardinality*), 92
chunck_network() (*fastr.execution.networkchunker.DefaultNetworkChunker method*), 153
chunck_network() (*fastr.execution.networkchunker.NetworkChunker method*), 153
cite (*fastr.core.tool.Tool attribute*), 112
classproperty() (*in module fastr.helpers.classproperty*), 164
ClassPropertyDescriptor (class in *fastr.helpers.classproperty*), 164
clean() (*fastr.execution.job.Job method*), 142
clean_free_jobs() (*fastr.plugins.executionplugin.ExecutionPlugin method*), 234
cleanup() (*fastr.core.ioplugin.IOPPlugin method*), 98
cleanup() (*fastr.plugins.BlockingExecution method*), 206
cleanup() (*fastr.plugins.DRMAAExecution method*), 209
cleanup() (*fastr.plugins.executionplugin.ExecutionPlugin method*), 234
cleanup() (*fastr.plugins.LinearExecution method*), 217
cleanup() (*fastr.plugins.managers.iopluginmanager.IOPluginManager method*), 237
cleanup() (*fastr.plugins.ProcessPoolExecution method*), 222
cleanup() (*fastr.plugins.RQExecution method*), 223
cleanup() (*fastr.plugins.S3Filesystem method*), 224
cleanup() (*fastr.plugins.SlurmExecution method*), 226
cleanup() (*fastr.plugins.StrongrExecution method*), 227
cleanup() (*fastr.plugins.XNATStorage method*), 231
clear() (*fastr.execution.environmentmodules.EnvironmentModules method*), 128
clear() (*fastr.planning.inputoutput.Input method*), 183
clear_version() (*in module fastr.version*), 87
collapse() (*fastr.api.Link property*), 75
collapse() (*fastr.execution.linkrun.LinkRun property*), 150
collapse() (*fastr.planning.link.Link property*), 193
collapse_indexes()

(*fastr.execution.linkrun.LinkRun* *property*), 150
collapse_indexes() (*fastr.planning.link.Link property*), 193
collect_errors() (*fastr.plugins.FastrInterface static method*), 213
collect_input_argument_provenance() (*fastr.core.provenance.Provenance method*), 101
collect_jobs() (*fastr.plugins.DRMAAExecution method*), 209
collect_provenance() (*fastr.core.provenance.Provenance method*), 101
collect_provenance() (*fastr.execution.job.InlineJob method*), 141
collect_provenance() (*fastr.execution.job.Job method*), 142
collect_provenance() (*fastr.execution.job.SourceJob method*), 148
collect_results() (*fastr.plugins.FastrInterface method*), 213
collector_plugin_type (*fastr.plugins.FastrInterface attribute*), 213
collectors (*fastr.plugins.FastrInterface attribute*), 213
combine() (*fastr.core.samples.SampleItemBase static method*), 106
combine_dimensions() (*fastr.core.dimension.ForwardsDimensions method*), 96
command (*fastr.core.tool.Tool attribute*), 112
COMMAND_DUMP (*fastr.execution.job.Job attribute*), 142
command_version() (*fastr.core.tool.Tool property*), 112
commandfile() (*fastr.execution.job.Job property*), 143
commandurl() (*fastr.execution.job.Job property*), 143
CommaSeperatedValueFile (*class in fastr.plugins*), 207
compare_execution_dir() (*in module fastr.utils.compare*), 242
compare_job_dirs() (*in module fastr.utils.compare*), 242
compare_job_output_data() (*in module fastr.utils.compare*), 242
compare_output_data() (*fastr.core.tool.Tool static method*), 112
compare_set() (*in module fastr.utils.compare*), 242
compare_value_dict_item() (*in module fastr.utils.compare*), 242
compare_value_list() (*in module fastr.utils.compare*), 242
Config (*class in fastr.helpers.configmanager*), 164
config (*in module fastr.helpers*), 162
configuration_fields (*fastr.plugins.DRMAAExecution attribute*), 209
configuration_fields (*fastr.plugins.ElasticsearchReporter attribute*), 210
configuration_fields (*fastr.plugins.PimReporter attribute*), 222
configuration_fields (*fastr.plugins.ProcessPoolExecution attribute*), 222
configuration_fields (*fastr.plugins.RQExecution attribute*), 223
configuration_fields (*fastr.plugins.SlurmExecution attribute*), 226
configuration_fields (*fastr.plugins.StrongrExecution attribute*), 227
connect() (*fastr.plugins.XNATStorage method*), 232
constant_id() (*fastr.planning.inputoutput.BaseInput method*), 179
constant_id() (*fastr.planning.inputoutput.Input property*), 183
constant_id() (*fastr.planning.inputoutput.NamedSubInput property*), 185
constant_id() (*fastr.planning.inputoutput.SubInput property*), 189
constantlist() (*fastr.execution.networkrun.NetworkRun property*), 154
ConstantNode (*class in fastr.planning.node*), 198
ConstantNodeRun (*class in fastr.execution.sourcenoderun*), 161
container() (*fastr.plugins.DockerTarget property*), 210
ContainsSamples (*class in fastr.core.samples*), 102
content() (*fastr.datatypes.URLType class method*), 126
copy() (*fastr.api.ResourceLimit method*), 89
copy() (*fastr.core.dimension.Dimension method*), 95
copy() (*fastr.core.resourcelimit.ResourceLimit method*), 102
copy_file_dir() (*fastr.core.vfs.VirtualFileSystem static method*), 115
cores() (*fastr.api.ResourceLimit property*), 89
cores() (*fastr.core.resourcelimit.ResourceLimit property*), 102
cpu_percent() (*fastr.core.target.SystemUsageInfo property*), 110
create_cardinality() (*in module fastr.core.cardinality*), 94
create_constant() (*fastr.api.Network method*), 72
create_constant()

(*fastr.planning.network.Network* method), 147
196
create_enumtype() (*fastr.datatypes.DataTypeManager* method), 150
122
create_ioplugin_tool() (*fastr.plugins.managers.iopluginmanager.IOPPluginManager* static method), 193
237
create_job() (*fastr.execution.noderun.NodeRun* method), 156
158
create_job() (*fastr.execution.sinknoderun.SinkNodeRun* method), 158
create_job() (*fastr.execution.sourcenoderun.SourceNodeRun* method), 160
160
create_link() (*fastr.api.Network* method), 72
create_link() (*fastr.planning.network.Network* method), 196
create_link_from() (*fastr.planning.inputoutput.BaseInput* method), 179
179
create_macro() (*fastr.api.Network* method), 73
create_macro() (*fastr.planning.network.Network* method), 196
create_native_spec() (*fastr.plugins.DRMAAExecution* method), 209
209
create_network() (*fastr.api* method), 72
create_network() (in module *fastr.api*), 88
create_network_copy() (*fastr.api* method), 72
create_network_copy() (in module *fastr.api*), 88
create_network_parser() (in module *fastr.utils.cmd.run*), 245
245
create_node() (*fastr.api.Network* method), 73
create_node() (*fastr.planning.network.Network* method), 196
create_payload() (*fastr.execution.job.Job* method), 143
143
create_payload() (*fastr.execution.job.SinkJob* method), 147
147
create_reference() (*fastr.core.tool.Tool* method), 112
112
create_reference() (*fastr.planning.network.Network* method), 197
197
create_rest_table() (in module *fastr.helpers.rest_generation*), 172
172
create_sink() (*fastr.api.Network* method), 73
create_sink() (*fastr.planning.network.Network* method), 197
197
create_source() (*fastr.api.Network* method), 73
create_source() (*fastr.planning.network.Network* method), 197
197
create vfs_url() (in module *fastr.data.url*), 118
create_zip() (in module *fastr.utils.cmd.dump*), 244
244
method), 147
196
createobj() (*fastr.execution.linkrun.LinkRun* class method), 150
150
createobj() (*fastr.execution.noderun.NodeRun* class method), 157
157
createobj() (*fastr.planning.link.Link* class method), 193
193
createobj() (*fastr.planning.node.Node* class method), 202
202
CrossValidation (class in *fastr.plugins*), 208
208
D
data() (*fastr.core.samples.SampleItemBase* property), 107
107
data() (*fastr.execution.sourcenoderun.ConstantNodeRun* property), 162
162
data() (*fastr.planning.node.ConstantNode* property), 199
199
data() (*fastr.plugins.managers.pluginmanager.PluginSubManager* property), 240
240
data_uri() (*fastr.core.provenance.Provenance* static method), 101
101
DataType (class in *fastr.datatypes*), 121
121
datatype() (*fastr.execution.inputoutputrun.InputRun* property), 132
132
datatype() (*fastr.execution.inputoutputrun.OutputRun* property), 135
135
datatype() (*fastr.execution.inputoutputrun.SubOutputRun* property), 140
140
datatype() (*fastr.execution.sinknoderun.SinkNodeRun* property), 159
159
datatype() (*fastr.execution.sourcenoderun.SourceNodeRun* property), 161
161
datatype() (*fastr.planning.inputoutput.BaseInputOutput* property), 181
181
datatype() (*fastr.planning.inputoutput.Input* property), 183
183
datatype() (*fastr.planning.inputoutput.Output* property), 187
187
datatype() (*fastr.planning.inputoutput.SubOutput* property), 191
191
datatype() (*fastr.planning.node.SinkNode* property), 204
204
datatype() (*fastr.planning.node.SourceNode* property), 205
205
datatype_from_type() (in module *fastr.utils.cmd.extract_argparse*), 245
245
DataTypeManager (class in *fastr.datatypes*), 122
122
date_version_matcher (*fastr.core.version.Version* attribute), 114
114
deactivate() (*fastr.plugins.reportingplugin.ReportingPlugin* method), 235
235

debug () (*fastr.helpers.configmanager.Config* property), 165
DEFAULT_FIELDS (*fastr.helpers.configmanager.Config attribute*), 164
DEFAULT_TARGET_CLASS (*fastr.core.tool.Tool attribute*), 111
DefaultInputGroupCombiner (class in *fastr.planning.inputgroupcombiner*), 177
DefaultNetworkAnalyzer (class in *fastr.execution.networkanalyzer*), 152
DefaultNetworkChunker (class in *fastr.execution.networkchunker*), 153
Deferred (class in *fastr.datatypes*), 124
delete() (*fastr.web.api.RunApi* method), 249
descend() (*fastr.helpers.schematotable.SchemaPrinter* method), 172
description (*fastr.core.tool.Tool* attribute), 112
description (*fastr.datatypes.AnyFile* attribute), 119
description (*fastr.datatypes.AnyType* attribute), 119
description (*fastr.datatypes.BaseDataType* attribute), 120
description (*fastr.datatypes.EnumType* attribute), 125
description() (*fastr.execution.inputoutputrun.SubInputRun* property), 138
description() (*fastr.planning.inputoutput.BaseInputOutput* property), 181
description() (*fastr.planning.inputoutput.SubInput* property), 189
description_type (*fastr.planning.inputoutput.BaseInput* attribute), 179
description_type (*fastr.planning.inputoutput.BaseInputOutput* attribute), 181
description_type (*fastr.planning.inputoutput.BaseOutput* attribute), 182
destroy() (*fastr.execution.linkrun.LinkRun* method), 151
destroy() (*fastr.planning.link.Link* method), 194
dicteq() (in module *fastr.utils.dicteq*), 243
diffdict() (in module *fastr.utils.dicteq*), 243
diffobj() (in module *fastr.utils.dicteq*), 243
diffobj_str() (in module *fastr.utils.dicteq*), 243
Dimension (class in *fastr.core.dimension*), 95
dimensionality() (*fastr.core.samples.SampleItemBasedirurl* property), 107
dimensions() (*fastr.core.dimension.ForwardsDimensions* property), 96
dimensions() (*fastr.core.dimension.HasDimensions* property), 96
dimensions() (*fastr.core.samples.ContainsSamples* property), 102
dimensions() (*fastr.core.samples.SampleCollection* property), 105
dimensions() (*fastr.execution.inputoutputrun.InputRun* property), 132
dimensions() (*fastr.execution.inputoutputrun.MacroOutputRun* property), 133
dimensions() (*fastr.execution.inputoutputrun.SourceOutputRun* property), 137
dimensions() (*fastr.execution.inputoutputrun.SubInputRun* property), 138
dimensions() (*fastr.execution.linkrun.LinkRun* property), 151
dimensions() (*fastr.planning.inputgroup.InputGroup* property), 176
dimensions() (*fastr.planning.inputgroupcombiner.BaseInputGroupCombiner* property), 176
dimensions() (*fastr.planning.inputoutput.AdvancedFlowOutput* property), 179
dimensions() (*fastr.planning.inputoutput.Input* property), 183
dimensions() (*fastr.planning.inputoutput.MacroOutput* property), 185
dimensions() (*fastr.planning.inputoutput.Output* property), 187
dimensions() (*fastr.planning.inputoutput.SubInput* property), 189
dimensions() (*fastr.planning.link.Link* property), 194
dimensions() (*fastr.planning.node.FlowNode* property), 200
dimensions() (*fastr.planning.node.Node* property), 203
dimensions() (*fastr.planning.node.SourceNode* property), 205
dimnames() (*fastr.core.dimension.HasDimensions* property), 96
dimnames() (*fastr.execution.flownoderun.FlowNodeRun* property), 130
dimnames() (*fastr.execution.noderun.NodeRun* property), 157
dimnames() (*fastr.execution.sourcenoderun.SourceNodeRun* property), 161
dimnames() (*fastr.planning.node.Node* property), 203
dir_list() (in module *fastr.helpers.clear_pycs*), 164
directory() (in module *fastr.utils.cmd.test*), 246
DirectoryLock (class in *fastr.helpers.lockfile*), 171
dirname() (in module *fastr.data.url*), 118
dirurl() (in module *fastr.data.url*), 118
dispatch_callbacks() (*fastr.plugins.DRMAAExecution* method), 209
doc() (in module *fastr.web.views*), 251
DockerTarget (class in *fastr.plugins*), 209
done() (*fastr.execution.job.JobState* property), 147
dot_extension (*fastr.datatypes.BaseDataType* attribute), 121
draw() (*fastr.api.Network* method), 74
draw() (*fastr.execution.linkrun.Link* method), 194

```

draw() (fastr.planning.network.Network method), 197
draw() (fastr.planning.node.ConstantNode method), 199
draw() (fastr.planning.node.MacroNode method), 201
draw() (fastr.planning.node.Node method), 203
draw() (fastr.planning.node.SinkNode method), 205
draw() (fastr.planning.node.SourceNode method), 205
draw_id() (fastr.planning.node.Node method), 203
draw_link_target()
    (fastr.planning.node.MacroNode method), 201
draw_link_target() (fastr.planning.node.Node method), 203
draw_network() (fastr.planning.network.Network method), 197
DRMAAExecution (class in fastr.plugins), 208
dummy_container (class in fastr.utils.cmd.upgrade), 247
dump() (in module fastr.helpers.xmltodict), 174
dumps() (in module fastr.helpers.xmltodict), 174
DYNAMIC_LIBRARY_PATH_DICT
    (fastr.plugins.LocalBinaryTarget attribute), 219

E
elasticsearch_update_status()
    (fastr.plugins.ElasticsearchReporter method), 210
ElasticsearchReporter (class in fastr.plugins), 210
emit() (fastr.helpers.events.FastrLogEventHandler method), 167
emit_event() (in module fastr.helpers.events), 167
empty() (fastr.planning.inputgroup.InputGroup property), 176
EmptyDefault (class in fastr.helpers.configmanager), 166
endpoint (fastr.web.api.NetworkApi attribute), 248
endpoint (fastr.web.api.NetworkListApi attribute), 249
endpoint (fastr.web.api.RunApi attribute), 250
endpoint (fastr.web.api.RunListApi attribute), 250
endpoint (fastr.web.api.StatusApi attribute), 250
endpoint (fastr.web.api.ToolApi attribute), 251
endpoint (fastr.web.api.ToolListApi attribute), 251
ensure_tmp_dir() (fastr.execution.job.Job method), 143
entity() (fastr.core.provenance.Provenance method), 101
EnumType (class in fastr.datatypes), 125
EnvironmentModules (class in
    fastr.execution.environmentmodules), 128
envmod (fastr.execution.environmentmodules.ModuleSystem attribute), 129
EventType (class in fastr.helpers.events), 167
examplesdir() (fastr.helpers.configmanager.Config property), 165
excerpt() (fastr.exceptions.FastrError method), 81
exec_worker() (fastr.plugins.LinearExecution method), 217
execute() (fastr.api.Network method), 74
execute() (fastr.core.interface.Interface method), 97
execute() (fastr.core.tool.Tool method), 112
execute() (fastr.execution.flownoderun.AdvancedFlowNodeRun method), 130
execute() (fastr.execution.job.Job method), 143
execute() (fastr.execution.macronoderun.MacroNodeRun method), 152
execute() (fastr.execution.networkrun.NetworkRun method), 155
execute() (fastr.execution.noderun.NodeRun method), 157
execute() (fastr.execution.sinknoderun.SinkNodeRun method), 159
execute() (fastr.execution.sourcenoderun.ConstantNodeRun method), 162
execute() (fastr.execution.sourcenoderun.SourceNodeRun method), 161
execute() (fastr.planning.network.Network method), 197
execute() (fastr.plugins.CrossValidation static method), 208
execute() (fastr.plugins.FastrInterface method), 213
execute() (fastr.plugins.FlowInterface method), 216
execute() (fastr.plugins.NipypeInterface method), 220
execute_job() (in module
    fastr.execution.executionscript), 129
execution_done (fastr.execution.job.JobState attribute), 147
execution_failed (fastr.execution.job.JobState attribute), 147
execution_finished()
    (fastr.execution.networkrun.NetworkRun method), 155
execution_plugin()
    (fastr.helpers.configmanager.Config property), 165
ExecutionPlugin (class in
    fastr.plugins.executionplugin), 232
ExecutionPluginManager (class in
    fastr.plugins.managers.executionpluginmanager), 236
executionscript()
    (fastr.helpers.configmanager.Config property), 165
expand() (fastr.api.Link property), 75
expand() (fastr.core.samples.SampleIndex method), 105
expand() (fastr.execution.linkrun.LinkRun property),

```

151
`expand()` (*fastr.planning.link.Link* property), 194
`expand_url()` (*fastr.core.ioplugin.IOPlugin* method), 99
`expand_url()` (*fastr.core.vfs.VirtualFileSystem* method), 116
`expand_url()` (*fastr.plugins.CommaSeparatedValueFile* method), 207
`expand_url()` (*fastr.plugins.managers.iopluginmanager.IOPPluginManager* method), 237
`expand_url()` (*fastr.plugins.S3Filesystem* method), 224
`expand_url()` (*fastr.plugins.VirtualFileSystemRegularExpression* method), 229
`expand_url()` (*fastr.plugins.VirtualFileSystemValueList* method), 229
`expand_url()` (*fastr.plugins.XNATStorage* method), 232
`expanding()` (*fastr.core.interface.Interface* property), 97
`expanding()` (*fastr.plugins.FastrInterface* property), 213
`expanding()` (*fastr.plugins.FlowInterface* property), 216
`expanding()` (*fastr.plugins.NipypeInterface* property), 221
`extend()` (*fastr.helpers.configmanager.EmptyDefault* method), 166
`extend()` (in module *fastr.helpers.jsonschemaparser*), 169
`extension` (*fastr.datatypes.BaseDataType* attribute), 121
`extra()` (*fastr.core.version.Version* property), 114
`extra_string()` (*fastr.core.version.Version* property), 114
`extract_argparser()` (in module *fastr.utils.cmd.extract_argparse*), 245
`extrainfofile()` (*fastr.execution.job.Job* property), 143
`extrainfouri()` (*fastr.execution.job.Job* property), 143

F

`failed(fastr.execution.job.JobState` attribute), 147
`failed_annotations()` (*fastr.core.samples.SampleItemBase* property), 107
`fastr.__init__` (module), 79
`fastr.api` (module), 88
`fastr.core` (module), 90
`fastr.core.cardinality` (module), 90
`fastr.core.dimension` (module), 95
`fastr.core.interface` (module), 96
`fastr.core.ioplugin` (module), 98
`fastr.core.provenance` (*module*), 100
`fastr.core.resourcelimit` (*module*), 101
`fastr.core.samples` (*module*), 102
`fastr.core.target` (*module*), 109
`fastr.core.test` (*module*), 117
`fastr.core.tool` (*module*), 111
`fastr.core.version` (*module*), 113
`fastr.core.vfs` (*module*), 115
`fastr.data.url` (*module*), 117
`fastr.datatypes` (*module*), 119
`fastr.exceptions` (*module*), 79
`fastr.execution` (*module*), 127
`fastr.execution.basenoderun` (*module*), 127
`fastr.execution.environmentmodules` (*module*), 128
`fastr.execution.executionscript` (*module*), 129
`fastr.execution.flownoderun` (*module*), 129
`fastr.execution.inputoutputrun` (*module*), 130
`fastr.execution.job` (*module*), 141
`fastr.execution.linkrun` (*module*), 149
`fastr.execution.macronoderun` (*module*), 151
`fastr.execution.networkanalyzer` (*module*), 152
`fastr.execution.networkchunker` (*module*), 153
`fastr.execution.networkrun` (*module*), 153
`fastr.execution.noderun` (*module*), 155
`fastr.execution.sinknoderun` (*module*), 158
`fastr.execution.sourcenoderun` (*module*), 160
`fastr.helpers` (*module*), 162
`fastr.helpers.checksum` (*module*), 162
`fastr.helpers.classproperty` (*module*), 164
`fastr.helpers.clear_pycs` (*module*), 164
`fastr.helpers.configmanager` (*module*), 164
`fastr.helpers.events` (*module*), 167
`fastr.helpers.filesynchelper` (*module*), 167
`fastr.helpers.iohelpers` (*module*), 168
`fastr.helpers.jsonschemaparser` (*module*), 168
`fastr.helpers.lazy_module` (*module*), 171
`fastr.helpers.lockfile` (*module*), 171
`fastr.helpers.procutils` (*module*), 172
`fastr.helpers.report` (*module*), 172
`fastr.helpers.rest_generation` (*module*), 172
`fastr.helpers.schematotable` (*module*), 172
`fastr.helpers.shellescape` (*module*), 173
`fastr.helpers.sysinfo` (*module*), 173
`fastr.helpers.xmltodict` (*module*), 174
`fastr.planning` (*module*), 175

fastr.planning.inputgroup (*module*), 175
fastr.planning.inputgroupcombiner (*module*), 176
fastr.planning.inputoutput (*module*), 178
fastr.planning.link (*module*), 192
fastr.planning.network (*module*), 194
fastr.planning.node (*module*), 198
fastr.plugins (*module*), 206
fastr.plugins.executionplugin (*module*), 232
fastr.plugins.managers (*module*), 236
fastr.plugins.managers.executionpluginmanager (*module*), 236
fastr.plugins.managers.interfacemanager (*module*), 236
fastr.plugins.managers.iopluginmanager (*module*), 236
fastr.plugins.managers.networkmanager (*module*), 238
fastr.plugins.managers.objectmanager (*module*), 238
fastr.plugins.managers.pluginmanager (*module*), 239
fastr.plugins.managers.targetmanager (*module*), 241
fastr.plugins.managers.toolmanager (*module*), 241
fastr.plugins.reportingplugin (*module*), 235
fastr.test (*module*), 242
fastr.utils (*module*), 242
fastr.utils.cmd (*module*), 244
fastr.utils.cmd.cat (*module*), 244
fastr.utils.cmd.dump (*module*), 244
fastr.utils.cmd.execute (*module*), 245
fastr.utils.cmd.extract_argparse (*module*), 245
fastr.utils.cmd.provenance (*module*), 245
fastr.utils.cmd pylint (*module*), 245
fastr.utils.cmd.report (*module*), 245
fastr.utils.cmd.run (*module*), 245
fastr.utils.cmd.sink (*module*), 246
fastr.utils.cmd.source (*module*), 246
fastr.utils.cmd.test (*module*), 246
fastr.utils.cmd.trace (*module*), 246
fastr.utils.cmd.upgrade (*module*), 247
fastr.utils.cmd.verify (*module*), 247
fastr.utils.cmd.webapp (*module*), 247
fastr.utils.compare (*module*), 242
fastr.utils.dicteq (*module*), 243
fastr.utils.gettools (*module*), 243
fastr.utils.multiprocesswrapper (*module*), 244
fastr.utils.verify (*module*), 244

fastr.version (*module*), 87
fastr.web (*module*), 248
fastr.web.api (*module*), 248
fastr.web.run (*module*), 251
fastr.web.views (*module*), 251
fastr_cat () (*in module fastr.utils.cmd.cat*), 244
fastr_isinstance () (*in module fastr.datatypes*), 127
FastrAttributeError, 79
FastrCannotChangeAttributeError, 80
FastrCardinalityError, 80
FastrCollectorError, 80
FastrDataTypeFileNotReadable, 80
FastrDataTypeMismatchError, 80
FastrDataTypeNotAvailableError, 80
FastrDataTypeNotInstantiableError, 80
FastrDataTypeValueError, 80
FastrError, 80
FastrErrorInSubprocess, 81
FastrExecutableNotFoundError, 81
FastrExecutionError, 81
FastrFileNotFoundException, 81
FastrImportError, 82
FastrIndexError, 82
FastrIndexNonexistent, 82
FastrInterface (*class in fastr.plugins*), 211
FastrIOError, 81
FastrKeyError, 82
FastrLockNotAcquired, 82
FastrLogEventHandler (*class* *in fastr.helpers.events*), 167
FastrLookupError, 82
FastrMountUnknownError, 82
FastrNamespaceType (*class* *in fastr.utils.cmd.upgrade*), 247
FastrNetworkMismatchError, 82
FastrNetworkUnknownError, 83
FastrNodeAlreadyPreparedError, 83
FastrNodeNotPreparedError, 83
FastrNodeNotValidError, 83
FastrNotExecutableError, 83
FastrNotImplementedError, 83
FastrNoValidTargetException, 83
FastrObjectUnknownError, 84
FastrOptionalModuleNotFoundError, 84
FastrOSError, 83
FastrOutputValidationErrors, 84
FastrParentMismatchError, 84
FastrPluginCapabilityNotImplemented, 84
FastrPluginNotAvailable, 84
FastrPluginNotLoaded, 84
FastrRefResolver (*class* *in fastr.helpers.jsonschemaparser*), 168

FastrResultFileNotFoundException, 84
 FastrScriptNotFoundError, 84
 FastrSerializationError, 85
 FastrSerializationIgnoreDefaultError,
 85
 FastrSerializationInvalidDataError, 85
 FastrSerializationMethodError, 85
 FastrSinkDataUnavailableError, 85
 FastrSizeInvalidError, 85
 FastrSizeMismatchError, 86
 FastrSizeUnknownError, 86
 FastrSourceDataUnavailableError, 86
 FastrStateError, 86
 FastrSubprocessNotFinished, 86
 FastrToolNotFoundError, 86
 FastrToolTargetNotFound, 86
 FastrToolUnknownError, 86
 FastrToolVersionError, 86
 FastrTypeError, 87
 FastrUnknownURLSchemeError, 87
 FastrValueError, 87
 FastrVersionInvalidError, 87
 FastrVersionMismatchError, 87
`fetch_url()` (*fastr.core.ioplugin.IOPlugin method*),
 99
`fetch_url()` (*fastr.core.vfs.VirtualFileSystem
 method*), 116
`fetch_url()` (*fastr.plugins.FileSystem method*), 214
`fetch_url()` (*fastr.plugins.HTTPPlugin method*), 217
`fetch_url()` (*fastr.plugins.S3Filesystem method*), 224
`fetch_url()` (*fastr.plugins.XNATStorage method*),
 232
`fetch_value()` (*fastr.core.ioplugin.IOPlugin
 method*), 99
`fetch_value()` (*fastr.core.vfs.VirtualFileSystem
 method*), 116
`fetch_value()` (*fastr.plugins.FileSystem method*),
 214
`fetch_value()` (*fastr.plugins.S3Filesystem method*),
 224
`filename` (*fastr.datatypes.BaseDataType attribute*),
 121
`filename` (*fastr.plugins.BlockingExecution attribute*),
 206
`filename` (*fastr.plugins.CommaSeperatedValueFile attribute*), 208
`filename` (*fastr.plugins.CrossValidation attribute*), 208
`filename` (*fastr.plugins.DockerTarget attribute*), 210
`filename` (*fastr.plugins.DRMAAExecution attribute*),
 209
`filename` (*fastr.plugins.ElasticsearchReporter attribute*), 211
`filename` (*fastr.plugins.FastrInterface attribute*), 213
`filename` (*fastr.plugins.FileSystem attribute*), 214
`filename` (*fastr.plugins.FlowInterface attribute*), 216
`filename` (*fastr.plugins.HTTPPlugin attribute*), 217
`filename` (*fastr.plugins.LinearExecution attribute*),
 217
`filename` (*fastr.plugins.LocalBinaryTarget attribute*),
 219
`filename` (*fastr.plugins.MacroTarget attribute*), 219
`filename` (*fastr.plugins.NipypeInterface attribute*), 221
`filename` (*fastr.plugins.Null attribute*), 221
`filename` (*fastr.plugins.PimReporter attribute*), 222
`filename` (*fastr.plugins.ProcessPoolExecution attribute*), 222
`filename` (*fastr.plugins.Reference attribute*), 224
`filename` (*fastr.plugins.RQExecution attribute*), 223
`filename` (*fastr.plugins.S3Filesystem attribute*), 225
`filename` (*fastr.plugins.SimpleReport attribute*), 225
`filename` (*fastr.plugins.SingularityTarget attribute*),
 226
`filename` (*fastr.plugins.SlurmExecution attribute*), 226
`filename` (*fastr.plugins.StrongrExecution attribute*),
 227
`filename` (*fastr.plugins.VirtualFileSystem attribute*),
 228
`filename` (*fastr.plugins.VirtualFileSystemRegularExpression
 attribute*), 229
`filename` (*fastr.plugins.VirtualFileSystemValueList attribute*), 230
`filename` (*fastr.plugins.XNATStorage attribute*), 232
`FileSyncHelper` (class in
 fastr.helpers.filesynchelper), 167
`filesynchelper_enabled()` (in module
 fastr.helpers.filesynchelper), 168
`filesynchelper_url()`
 (*fastr.helpers.configmanager.Config property*), 165
`FileSystem` (class in *fastr.plugins*), 214
`fill_output_argument()` (*fastr.execution.job.Job class method*), 143
`filter_plugin()` (*fastr.plugins.managers.pluginmanager.PluginsView method*), 241
`find_argparser()` (in module
 fastr.utils.cmd.extract_argparse), 245
`find_commands()` (in module *fastr.utils.cmd*), 244
`find_source_index()`
 (*fastr.execution.noderun.NodeRun method*),
 157
`find_source_index()`
 (*fastr.planning.inputgroup.InputGroup method*), 176
`find_source_index()` (*fastr.planning.node.Node method*), 203
`find_tool()` (in module *fastr.utils.cmd.upgrade*), 247
`finished` (*fastr.execution.job.JobState attribute*), 147
`flow_plugin_type` (*fastr.plugins.FlowInterface attribute*), 216

tribute), 216
flow_plugins (*fastr.plugins.FlowInterface* attribute), 216
FlowInterface (*class in fastr.plugins*), 215
FlowNode (*class in fastr.planning.node*), 200
FlowNodeRun (*class in fastr.execution.flownoderun*), 129
format () (*fastr.web.api.ObjectUrl* method), 249
format () (*fastr.web.api.SubUrl* method), 250
ForwardsDimensions (*class in fastr.core.dimension*), 95
from_schema () (*fastr.helpers.jsonschema.parser.FastrRefResolver* class method), 169
full_split () (*in module fastr.data.url*), 118
fullid (*fastr.datatypes.BaseDataType* attribute), 121
fullid() (*fastr.core.samples.SampleCollection* property), 105
fullid() (*fastr.core.tool.Tool* property), 112
fullid() (*fastr.datatypes.DataTypeManager* property), 122
fullid() (*fastr.execution.inputoutputrun.InputRun* property), 132
fullid() (*fastr.execution.inputoutputrun.NamedSubInputRun* property), 134
fullid() (*fastr.execution.inputoutputrun.OutputRun* property), 135
fullid() (*fastr.execution.inputoutputrun.SubInputRun* property), 138
fullid() (*fastr.execution.inputoutputrun.SubOutputRun* property), 140
fullid() (*fastr.execution.job.Job* property), 143
fullid() (*fastr.execution.linkrun.LinkRun* property), 151
fullid() (*fastr.execution.networkrun.NetworkRun* property), 155
fullid() (*fastr.execution.noderun.NodeRun* property), 157
fullid() (*fastr.planning.inputgroup.InputGroup* property), 176
fullid() (*fastr.planning.inputgroupcombiner.BaseInputGroup* property), 176
fullid() (*fastr.planning.inputoutput.BaseInputOutput* property), 181
fullid() (*fastr.planning.inputoutput.Input* property), 183
fullid() (*fastr.planning.inputoutput.NamedSubInput* property), 185
fullid() (*fastr.planning.inputoutput.Output* property), 187
fullid() (*fastr.planning.inputoutput.SubInput* property), 189
fullid() (*fastr.planning.inputoutput.SubOutput* property), 191
fullid() (*fastr.planning.link.Link* property), 194
fullid() (*fastr.planning.network.Network* property), 197
fullid() (*fastr.planning.node.Node* property), 203
function_wrapper () (in module *fastr.utils.multiprocesswrapper*), 244

G

GE_NATIVE_SPEC (*fastr.plugins.DRMAAExecution* attribute), 208
generate_jobs () (*fastr.execution.networkrun.NetworkRun* method), 155
get () (*fastr.web.api.NetworkApi* method), 248
get () (*fastr.web.api.NetworkListApi* method), 249
get () (*fastr.web.api.RunApi* method), 250
get () (*fastr.web.api.RunListApi* method), 250
get () (*fastr.web.api.StatusApi* method), 250
get () (*fastr.web.api.ToolApi* method), 251
get () (*fastr.web.api.ToolListApi* method), 251
get_arguments () (*fastr.plugins.FastrInterface* method), 213
get_base_version () (*in module fastr.version*), 87
get_command () (*fastr.plugins.FastrInterface* method), 214
get_command_module () (*in module fastr.utils.cmd*), 244
get_cpu_usage () (*in module fastr.helpers.sysinfo*), 173
get_deferred () (*fastr.execution.job.Job* method), 143
get_drmaa_info () (*in module fastr.helpers.sysinfo*), 173
get_field () (*fastr.helpers.configmanager.Config* method), 165
get_hg_info () (*in module fastr.version*), 88
get_hostinfo () (*in module fastr.helpers.sysinfo*), 173
get_job () (*fastr.plugins.executionplugin.ExecutionPlugin* method), 234
get_memory_usage () (in module *fastr.helpers.sysinfo*), 173
get_message () (*in module fastr.exceptions*), 87
get_mounts () (*in module fastr.helpers.sysinfo*), 173
get_object_version () (*fastr.plugins.managers.networkmanager.NetworkManager* method), 238
get_object_version () (*fastr.plugins.managers.objectmanager.ObjectManager* method), 239
get_object_version () (*fastr.plugins.managers.toolmanager.ToolManager* method), 241
get_os () (*in module fastr.helpers.sysinfo*), 173
get_output_datatype () (*fastr.execution.job.Job* method), 143

```

get_output_datatype()
    (fastr.execution.job.SourceJob method), 148
get_output_info()
    (fastr.execution.macronoderun.MacroNodeRun
method), 152
get_output_info()
    (fastr.planning.node.MacroNode
method), 201
get_parent_provenance()
    (fastr.core.provenance.Provenance
method), 101
get_parser() (in module fastr.utils.cmd.cat), 244
get_parser() (in module fastr.utils.cmd.dump), 244
get_parser() (in module fastr.utils.cmd.execute), 245
get_parser() (in module
fastr.utils.cmd.extract_argparse), 245
get_parser() (in module fastr.utils.cmd.provenance),
    245
get_parser() (in module fastr.utils.cmd pylint), 245
get_parser() (in module fastr.utils.cmd.report), 245
get_parser() (in module fastr.utils.cmd.run), 245
get_parser() (in module fastr.utils.cmd.sink), 246
get_parser() (in module fastr.utils.cmd.source), 246
get_parser() (in module fastr.utils.cmd.test), 246
get_parser() (in module fastr.utils.cmd.trace), 246
get_parser() (in module fastrutils.cmd.upgrade),
    247
get_parser() (in module fastr.utils.cmd.verify), 247
get_parser() (in module fastr.utils.cmd.webapp),
    247
get_path_from_url() (in module fastr.data.url),
    118
get_processes() (in module fastr.helpers.sysinfo),
    174
get_prov_document() (in module
fastr.utils.cmd.provenance), 245
get_python() (in module fastr.helpers.sysinfo), 174
get_result() (fastr.execution.job.InlineJob method),
    141
get_result() (fastr.execution.job.Job method), 144
get_result() (fastr.execution.job.SinkJob method),
    148
get_saved_version() (in module fastr.version), 88
get_sourced_nodes()
    (fastr.execution.inputoutputrun.InputRun
method), 132
get_sourced_nodes()
    (fastr.execution.inputoutputrun.SubInputRun
method), 138
get_sourced_nodes()
    (fastr.execution.noderun.NodeRun
method), 157
get_sourced_nodes()
    (fastr.planning.inputoutput.Input
method), 184
get_sourced_nodes()
    (fastr.planning.inputoutput.SubInput
method), 189
get_sourced_nodes() (fastr.planning.node.Node
method), 203
get_sourced_outputs()
    (fastr.execution.inputoutputrun.InputRun
method), 132
get_sourced_outputs()
    (fastr.execution.inputoutputrun.SubInputRun
method), 138
get_sourced_outputs()
    (fastr.planning.inputoutput.Input
method), 184
get_sourced_outputs()
    (fastr.planning.inputoutput.SubInput
method), 189
get_specials() (fastr.plugins.FastrInterface
method), 214
get_status() (fastr.plugins.executionplugin.ExecutionPlugin
method), 234
get_sysinfo() (in module fastr.helpers.sysinfo), 174
get_type() (fastr.datatypes.DataTypeManager
method), 122
get_type() (fastr.plugins.NipypeInterface method),
    221
get_url_scheme() (in module fastr.data.url), 118
get_users() (in module fastr.helpers.sysinfo), 174
get_value() (fastr.execution.job.Job class method),
    144
getblueprinter() (in module
fastr.helpers.jsonschemasparser), 169
global_id() (fastr.execution.networkrun.NetworkRun
property), 155
global_id() (fastr.execution.noderun.NodeRun prop-
erty), 157
global_id() (fastr.planning.network.Network prop-
erty), 197
global_id() (fastr.planning.node.Node property),
    203
guess_type() (fastr.datatypes.DataTypeManager
method), 122

```

H

```

has_file_promise()
    (fastr.helpers.filesynchelper.FileSyncHelper
method), 168
has_type() (fastr.datatypes.DataTypeManager
method), 123
HasDimensions (class in fastr.core.dimension), 96
hash() (fastr.core.tool.Tool property), 112
hash_inputs() (fastr.execution.job.Job method), 144

```

hash_inputs() (*fastr.execution.job.SinkJob method*), 148
hash_inputs() (*fastr.execution.job.SourceJob method*), 148
hash_results() (*fastr.execution.job.Job method*), 144
hashsum() (*in module fastr.helpers.checksum*), 163
HasSamples (*class in fastr.core.samples*), 102
help (*fastr.core.tool.Tool attribute*), 112
hold (*fastr.execution.job.JobState attribute*), 147
hold (*fastr.plugins.executionplugin.JobAction attribute*), 235
hold_job() (*fastr.plugins.executionplugin.ExecutionPlugin method*), 234
HTTPPPlugin (*class in fastr.plugins*), 216

|

id (*fastr.datatypes.BaseDataType attribute*), 121
id() (*fastr.api.Input property*), 76
id() (*fastr.api.Link property*), 75
id() (*fastr.api.Network property*), 74
id() (*fastr.api.Node property*), 75
id() (*fastr.api.Output property*), 77
id() (*fastr.core.samples.SampleItemBase property*), 107
id() (*fastr.core.tool.Tool property*), 112
id() (*fastr.execution.job.Job property*), 144
id() (*fastr.execution.job.SinkJob property*), 148
id() (*fastr.execution.networkrun.NetworkRun property*), 155
id() (*fastr.execution.noderun.NodeRun property*), 157
id() (*fastr.planning.inputoutput.BaseInputOutput property*), 181
id() (*fastr.planning.inputoutput.Input property*), 184
id() (*fastr.planning.network.Network property*), 197
id() (*fastr.planning.node.Node property*), 203
idle() (*fastr.execution.job.JobState property*), 147
ids() (*fastr.core.samples.HasSamples method*), 103
in_progress() (*fastr.execution.job.JobState property*), 147
index() (*fastr.core.samples.SampleItemBase property*), 107
index() (*fastr.execution.inputoutputrun.InputRun method*), 132
index() (*fastr.planning.inputoutput.Input method*), 184
index() (*in module fastr.web.views*), 251
indexes() (*fastr.core.samples.HasSamples method*), 103
indexrep() (*fastr.execution.inputoutputrun.SubOutputRun property*), 140
indexrep() (*fastr.planning.inputoutput.SubOutput property*), 191
INFO_DUMP (*fastr.execution.job.Job attribute*), 142
init_provenance() (*fastr.core.provenance.Provenance method*), 101
InlineJob (*class in fastr.execution.job*), 141
Input (*class in fastr.api*), 76
Input (*class in fastr.planning.inputoutput*), 182
input() (*fastr.api.Node property*), 75
input() (*fastr.execution.sinknoderun.SinkNodeRun property*), 159
input() (*fastr.planning.node.SinkNode property*), 205
input_group() (*fastr.api.Input property*), 77
input_group() (*fastr.execution.inputoutputrun.InputRun property*), 132
input_group() (*fastr.execution.inputoutputrun.SubInputRun property*), 138
input_group() (*fastr.planning.inputoutput.Input property*), 184
input_group() (*fastr.planning.inputoutput.MacroInput property*), 184
input_group() (*fastr.planning.inputoutput.SubInput property*), 189
input_groups() (*fastr.execution.noderun.NodeRun property*), 157
input_groups() (*fastr.planning.inputgroupcombiner.BaseInputGroupC property*), 176
input_groups() (*fastr.planning.node.Node property*), 203
InputDict (*class in fastr.planning.node*), 200
InputGroup (*class in fastr.planning.inputgroup*), 175
InputRun (*class in fastr.execution.inputoutputrun*), 131
inputs (*fastr.planning.node.Node attribute*), 203
inputs() (*fastr.api.Node property*), 75
inputs() (*fastr.core.interface.Interface property*), 97
inputs() (*fastr.core.tool.Tool property*), 112
inputs() (*fastr.plugins.FastrInterface property*), 214
inputs() (*fastr.plugins.FlowInterface property*), 216
inputs() (*fastr.plugins.NipypeInterface property*), 221
InputSpec (*class in fastr.core.interface*), 96
InputSpecBase (*in module fastr.core.interface*), 97
insert() (*fastr.execution.inputoutputrun.InputRun method*), 132
insert() (*fastr.planning.inputoutput.Input method*), 184
IntCardinalitySpec (*class in fastr.core.cardinality*), 92
Interface (*class in fastr.core.interface*), 97
InterfacePluginManager (*class in fastr.plugins.managers.interfacemanager*), 236
InterfaceResult (*class in fastr.core.interface*), 98
IOPlugin (*class in fastr.core.ioplugin*), 98
IOPluginManager (*class in fastr.plugins.managers.iopluginmanager*), 236
is_mapping() (*fastr.core.samples.SampleValue property*), 108

i
 is_sequence() (*fastr.core.samples.SampleValue property*), 108
 is_valid() (*fastr.planning.network.Network method*), 198
 isdatatype() (*fastr.datatypes.DataTypeManager static method*), 123
 isinstance() (*fastr.datatypes.BaseDataType class method*), 121
 isinstance() (*fastr.datatypes.TypeGroup class method*), 126
 isloaded() (*fastr.execution.environmentmodules.EnvironmentModule method*), 128
 isslice() (*fastr.core.samples.SampleIndex property*), 105
 isurl() (*fastr.core.ioplugin.IOPPlugin static method*), 99
 isurl() (*in module fastr.data.url*), 119
 item_index() (*fastr.execution.inputoutputrun.NamedSubInputRun property*), 134
 item_index() (*fastr.execution.inputoutputrun.SubInputRun property*), 139
 item_index() (*fastr.planning.inputoutput.BaseInput property*), 179
 item_index() (*fastr.planning.inputoutput.NamedSubInput property*), 185
 item_index() (*fastr.planning.inputoutput.SubInput property*), 189
 items() (*fastr.core.samples.HasSamples method*), 103
 items_validate() (*in module fastr.helpers.jsonschema*), 169
 iter_input_groups() (*fastr.planning.inputgroupcombiner.BaseInputGroupCombiner method*), 176
 iter_input_groups() (*fastr.planning.inputgroupcombiner.DefaultInputGroupCombiner method*), 177
 iter_input_groups() (*fastr.planning.inputgroupcombiner.MergingInputGroupCombiner method*), 178
 iterconvergingindices() (*fastr.execution.inputoutputrun.OutputRun method*), 135
 iterelements() (*fastr.core.samples.SampleValue method*), 108
 iterinputvalues() (*fastr.planning.inputgroup.InputGroup property*), 176
 iteritems() (*fastr.core.samples.HasSamples method*), 103
 iteritems() (*fastr.execution.inputoutputrun.SubInputRun method*), 139
 iteritems() (*fastr.planning.inputoutput.SubInput method*), 189
 itersubinputs() (*fastr.execution.inputoutputrun.BaseInputRun method*), 131
 itersubinputs() (*fastr.execution.inputoutputrun.InputRun method*), 133
 itersubinputs() (*fastr.execution.inputoutputrun.SubInputRun method*), 139
 itersubinputs() (*fastr.planning.inputoutput.BaseInput method*), 179
 itersubinputs() (*fastr.planning.inputoutput.Input method*), 184
 itersubinputs() (*fastr.planning.inputoutput.SubInput method*), 189

J
 Job (*class in fastr.execution.job*), 141
 job() (*fastr.datatypes.Deferred property*), 124
 job_cleanup_level() (*fastr.helpers.configmanager.Config property*), 165
 job_finished() (*fastr.execution.networkrun.NetworkRun method*), 155
 job_finished() (*fastr.helpers.filesynchelperFileSyncHelper method*), 168
 job_finished() (*fastr.plugins.executionplugin.ExecutionPlugin method*), 234
 job_finished_callback() (*fastr.plugins.ProcessPoolExecution method*), 222
 job_regression_check() (*fastr.plugins.DRMAAExecution method*), 209
 job_status_check() (*fastr.plugins.SlurmExecution method*), 226
 job_updated (*fastr.helpers.events.EventType attribute*), 167
 job_updated() (*fastr.plugins.elasticsearchReporter method*), 211
 job_updated() (*fastr.plugins.PimReporter method*), 234
 job_updated() (*fastr.plugins.reportingplugin.ReportingPlugin method*), 235
 JobAction (*class in fastr.plugins.executionplugin*), 235
 JobCleanupLevel (*class in fastr.execution.job*), 145
 jobs() (*fastr.core.samples.SampleItemBase property*), 107
 JobState (*class in fastr.execution.job*), 145
 join() (*in module fastr.data.url*), 119
 json (*in module fastr.plugins*), 232

L
 LazyModule (*class in fastr.helpers.lazy_module*), 171
 LinearExecution (*class in fastr.plugins*), 217
 linearized() (*fastr.execution.inputoutputrun.SourceOutputRun property*), 137

linearized() (*fastr.planning.inputoutput.SourceOutput property*), 188
Link (*class in fastr.api*), 75
Link (*class in fastr.planning.link*), 192
link_or_copy() (*in module fastr.helpers.iohelpers*), 168
LinkRun (*class in fastr.execution.linkrun*), 149
listeners() (*fastr.execution.inputoutputrun.OutputRun property*), 136
listeners() (*fastr.execution.inputoutputrun.SubOutputRun property*), 141
listeners() (*fastr.execution.noderun.NodeRun property*), 157
listeners() (*fastr.planning.inputoutput.Output property*), 187
listeners() (*fastr.planning.inputoutput.SubOutput property*), 191
listeners() (*fastr.planning.node.Node property*), 203
lmod (*fastr.execution.environmentmodules.ModuleSystem attribute*), 129
load() (*fastr.api.Network class method*), 75
load() (*fastr.execution.environmentmodules.EnvironmentModule method*), 128
load() (*fastr.helpers.filesynchelperFileSyncHelper method*), 168
load() (*in module fastr.helpers.xmltodict*), 174
load_gpickle() (*in module fastr.helpers.iohelpers*), 168
load_json() (*in module fastr.helpers.iohelpers*), 168
loaded_modules() (*fastr.execution.environmentmodules.EnvironmentModule property*), 128
loads() (*in module fastr.helpers.xmltodict*), 175
LocalBinaryTarget (*class in fastr.plugins*), 217
lock_dir() (*fastr.helpers.lockfile.DirectoryLock property*), 171
lock_dir_name (*fastr.helpers.lockfile.DirectoryLock attribute*), 171
log_record_emitted
 (*fastr.helpers.events.EventType attribute*), 167
log_record_emitted() (*fastr.plugins.PimReporter method*), 222
log_record_emitted()
 (*fastr.plugins.reportingplugin.ReportingPlugin method*), 235
log_to_file() (*fastr.helpers.configmanager.Config property*), 165
logdir() (*fastr.helpers.configmanager.Config property*), 165
logfile() (*fastr.execution.job.Job property*), 144
logging_config() (*fastr.helpers.configmanager.Config property*), 165
loglevel() (*fastr.helpers.configmanager.Config prop-*erty), 165
logtype() (*fastr.helpers.configmanager.Config property*), 165
logurl() (*fastr.execution.job.Job property*), 144
long_id() (*fastr.execution.networkrun.NetworkRun property*), 155
lookup() (*fastr.datatypes.Deferred class method*), 124

M

MacroInput (*class in fastr.planning.inputoutput*), 184
MacroNode (*class in fastr.planning.node*), 200
MacroNodeRun
 (*class in fastr.execution.macronoderun*), 151
MacroOutput (*class in fastr.planning.inputoutput*), 185
MacroOutputRun
 (*class in fastr.execution.inputoutputrun*), 133
MacroTarget (*class in fastr.plugins*), 219
main() (*in module fastr.execution.executionscript*), 129
main() (*in module fastr.helpers.clear_pycs*), 164
main() (*in module fastr.utils.cmd*), 244
main() (*in module fastr.utils.cmd.cat*), 244
main() (*in module fastr.utils.cmd.dump*), 244
main() (*in module fastr.utils.cmd.execute*), 245
main() (*in module fastr.utils.cmd.extract_argparse*), 245
main() (*in module fastr.utils.cmd.provenance*), 245
main() (*in module fastr.utils.cmd pylint*), 245
main() (*in module fastr.utils.cmd.report*), 245
main() (*in module fastr.utils.cmd.run*), 245
main() (*in module fastr.utils.cmd.sink*), 246
main() (*in module fastr.utils.cmd.source*), 246
main() (*in module fastr.utils.cmd.test*), 246
main() (*in module fastr.utils.cmd.trace*), 246
main() (*in module fastr.utils.cmd.upgrade*), 247
main() (*in module fastr.utils.cmd.verify*), 247
main() (*in module fastr.utils.cmd.webapp*), 247
main() (*in module fastr.utils.gettools*), 243
main() (*in module fastr.web.run*), 251
major() (*fastr.core.version.Version property*), 114
make_file_promise()
 (*fastr.helpers.filesynchelperFileSyncHelper method*), 168
mapping_part() (*fastr.core.samples.SampleValue method*), 108
match_types() (*fastr.datatypes.DataTypeManager method*), 123
match_types_any()
 (*fastr.datatypes.DataTypeManager method*), 123
MaxCardinalitySpec
 (*class in fastr.core.cardinality*), 93
md5_checksum() (*in module fastr.helpers.checksum*), 163

mediatypes () (*fastr:web.api.NetworkApi method*), 248
 mediatypes () (*fastr:web.api.NetworkListApi method*), 249
 mediatypes () (*fastr:web.api.RunApi method*), 250
 mediatypes () (*fastr:web.api.RunListApi method*), 250
 mediatypes () (*fastr:web.api.StatusApi method*), 250
 mediatypes () (*fastr:web.api.ToolApi method*), 251
 mediatypes () (*fastr:web.api.ToolListApi method*), 251
 members (*fastr:datatype.TypeGroup attribute*), 126
 memory () (*fastr:api.ResourceLimit property*), 89
 memory () (*fastr:core.resourcelimit.ResourceLimit property*), 102
 merge () (*fastr:planning.inputgroupcombiner.BaseInputGroupCombinerBaseInputGroupCombiner* (*fastr:plugins.LinearExecution attribute*), 217
 method), 176
 merge () (*fastr:planning.inputgroupcombiner.DefaultInputGroupCombinerDefaultInputGroupCombiner* (*fastr:plugins.MacroTarget attribute*), 219
 method), 177
 merge () (*fastr:planning.inputgroupcombiner.MergingInputGroupCombinerMergingInputGroupCombiner* (*fastr:plugins.Null attribute*), 221
 method), 178
 merge_default () (*fastr:helpers.configmanager.EmptyDefault* (*fastr:plugins.ProcessPoolExecution attribute*), 223
 method), 166
 merge_dimensions ()
 (*fastr:execution.noderun.NodeRun property*), 157
 merge_dimensions () (*fastr:planning.node.Node property*), 203
 merge_failed_annotations ()
 (*fastr:planning.inputgroupcombiner.BaseInputGroupCombinerBaseInputGroupCombiner* (*fastr:plugins.StrongrExecution attribute*), 227
 method), 177
 merge_payloads () (*fastr:planning.inputgroupcombiner.BaseInputGroupCombinerBaseInputGroupCombiner* (*fastr:plugins.VirtualFileSystemRegularExpression attribute*), 229
 method), 177
 merge_sample_data ()
 (*fastr:planning.inputgroupcombiner.BaseInputGroupCombinerBaseInputGroupCombiner* (*fastr:plugins.VirtualFileSystemValueList attribute*), 230
 method), 177
 merge_sample_id ()
 (*fastr:planning.inputgroupcombiner.BaseInputGroupCombinerBaseInputGroupCombiner* (*fastr:execution.environmentmodules*), 129
 method), 177
 merge_sample_index ()
 (*fastr:planning.inputgroupcombiner.BaseInputGroupCombinerBaseInputGroupCombiner* (*fastr:core.target.SubprocessBasedTarget process* (),
 method), 177
 merge_sample_jobs ()
 (*fastr:planning.inputgroupcombiner.BaseInputGroupCombinerBaseInputGroupCombiner* (*fastr:helpers.configmanager.Config property*), 165
 MergingInputGroupCombiner (class in
 fastr:planning.inputgroupcombiner), 178
 methods (*fastr:web.api.NetworkApi attribute*), 248
 methods (*fastr:web.api.NetworkListApi attribute*), 249
 methods (*fastr:web.api.RunApi attribute*), 250
 methods (*fastr:web.api.RunListApi attribute*), 250
 methods (*fastr:web.api.StatusApi attribute*), 250
 methods (*fastr:web.api.ToolApi attribute*), 251
 methods (*fastr:web.api.ToolListApi attribute*), 251
 MinCardinalitySpec (class in
 fastr:core.cardinality), 93
 minor () (*fastr:core.version.Version property*), 115
 module (*fastr:plugins.BlockingExecution attribute*), 206
 module (*fastr:plugins.CommaSepreatedValueFile attribute*), 208
 module (*fastr:plugins.CrossValidation attribute*), 208
 module (*fastr:plugins.DockerTarget attribute*), 210
 module (*fastr:plugins.DRMAAExecution attribute*), 209
 module (*fastr:plugins.ElasticsearchReporter attribute*), 211
 module (*fastr:plugins.FastrInterface attribute*), 214
 module (*fastr:plugins.FileSystem attribute*), 214
 module (*fastr:plugins.FlowInterface attribute*), 216
 module (*fastr:plugins.HTTPPlugin attribute*), 217
 module (*fastr:plugins.LocalBinaryTarget attribute*), 219
 module (*fastr:plugins.NipypeInterface attribute*), 221
 module (*fastr:plugins.Null attribute*), 221
 module (*fastr:plugins.PimReporter attribute*), 222
 module (*fastr:plugins.Reference attribute*), 224
 module (*fastr:plugins.RQExecution attribute*), 223
 module (*fastr:plugins.S3Filesystem attribute*), 225
 module (*fastr:plugins.SimpleReport attribute*), 225
 module (*fastr:plugins.SingularityTarget attribute*), 226
 module (*fastr:plugins.SlurmExecution attribute*), 226
 module (*fastr:plugins.StrongrExecution attribute*), 227
 module (*fastr:plugins.VirtualFileSystem attribute*), 228
 module (*fastr:plugins.VirtualFileSystemValueList attribute*), 230
 module (*fastr:plugins.XNATStorage attribute*), 232
 ModuleSystem (class in
 fastr:execution.environmentmodules), 129
 monitor_docker () (*fastr:plugins.DockerTarget method*), 210
 N
 name (*fastr:core.tool.Tool attribute*), 112
 name (*fastr:datatype.BaseDataType attribute*), 121
 name () (*fastr:core.dimension.Dimension property*), 95
 name () (*fastr:execution.noderun.NodeRun property*), 157
 name () (*fastr:planning.node.Node property*), 203

```

NamedSubInput (class in fastr.planning.inputoutput), 185
NamedSubinputRun (class in fastr.execution.inputoutputrun), 133
namedtuple_to_dict () (in module fastr.helpers.sysinfo), 174
namespace (fastr.core.tool.Tool attribute), 113
namespace (fastr.planning.network.Network attribute), 198
NATIVE_SPEC (fastr.plugins.DRMAAExecution attribute), 208
ndims () (fastr.core.dimension.HasDimensions property), 96
ndims () (fastr.core.samples.SampleCollection property), 105
ndims () (fastr.execution.inputoutputrun.SourceOutputRun property), 137
Network (class in fastr.api), 72
Network (class in fastr.planning.network), 194
network () (fastr.execution.networkrun.NetworkRun property), 155
network () (fastr.planning.node.MacroNode property), 201
network () (in module fastr.web.views), 251
NETWORK_DUMP_FILE_NAME (fastr.execution.networkrun.NetworkRun attribute), 153
NETWORK_DUMP_FILE_NAME (fastr.planning.network.Network attribute), 194
network_lock_thread () (in module fastr.web.api), 251
network_run () (fastr.execution.macronoderun.MacroNodeReentrant property), 152
network_runner () (in module fastr.web.api), 251
NetworkAnalyzer (class in fastr.execution.networkanalyzer), 152
NetworkApi (class in fastr.web.api), 248
NetworkChunker (class in fastr.execution.networkchunker), 153
NetworkListApi (class in fastr.web.api), 249
NetworkManager (class in fastr.plugins.managers.networkmanager), 238
NetworkRun (class in fastr.execution.networkrun), 153
networks (fastr attribute), 72
networks () (in module fastr.web.views), 251
networks_path () (fastr.helpers.configmanager.Config property), 165
NipypeInterface (class in fastr.plugins), 220
no_cleanup (fastr.execution.job.JobCleanupLevel attribute), 145
Node (class in fastr.api), 75
Node (class in fastr.planning.node), 201
node () (fastr.core.cardinality.AsCardinalitySpec property), 91
node () (fastr.core.cardinality.ValueCardinalitySpec property), 94
node () (fastr.execution.inputoutputrun.SubInputRun property), 139
node () (fastr.execution.inputoutputrun.SubOutputRun property), 141
node () (fastr.planning.inputoutput.BaseInputOutput property), 181
node () (fastr.planning.inputoutput.SubInput property), 190
node () (fastr.planning.inputoutput.SubOutput property), 191
node_class (fastr.core.tool.Tool attribute), 113
NODE_RUN_MAP (fastr.execution.basenoderun.BaseNodeRun attribute), 127
NODE_RUN_TYPES (fastr.execution.basenoderun.BaseNodeRun attribute), 127
NODE_TYPES (fastr.planning.node.BaseNode attribute), 198
nodegroup () (fastr.planning.node.Node property), 203
nodegroup () (fastr.planning.node.SourceNode property), 205
nodegroups () (fastr.execution.networkrun.NetworkRun property), 155
nodegroups () (fastr.planning.network.Network property), 198
NodeRun (class in fastr.execution.noderun), 155
non_failed (fastr.execution.job.JobCleanupLevel attribute), 145
nodeexistent (fastr.execution.job.JobState attribute), 147
normurl () (in module fastr.data.url), 119
not_draft4 () (in module fastr.helpers.jsonschemasparser), 169
ns_id () (fastr.core.tool.Tool property), 113
ns_id () (fastr.planning.network.Network property), 198
Null (class in fastr.plugins), 221
O
object_class () (fastr.plugins.managers.networkmanager.NetworkManager property), 238
object_class () (fastr.plugins.managers.objectmanager.ObjectManager property), 239
object_class () (fastr.plugins.managers.toolmanager.ToolManager property), 241
ObjectManager (class in fastr.plugins.managers.objectmanager), 238
ObjectUrl (class in fastr.web.api), 249
objectversions () (fastr.plugins.managers.objectmanager.ObjectManager method), 239

```

one_of_draft4 () (in module `fastr.helpers.jsonschemaparser`), 170
open_url () (in module `fastr.utils.cmd.webapp`), 247
options (`fastr.datatypes.EnumType` attribute), 125
Output (class in `fastr.api`), 77
Output (class in `fastr.planning.inputoutput`), 185
output () (`fastr.api.Node` property), 75
output () (`fastr.execution.sourcenoderun.SourceNodeRun` property), 161
output () (`fastr.planning.node.SourceNode` property), 205
OutputDict (class in `fastr.planning.node`), 204
OutputRun (class in `fastr.execution.inputoutputrun`), 134
outputs (`fastr.planning.node.Node` attribute), 203
outputs () (`fastr.api.Node` property), 76
outputs () (`fastr.core.interface.Interface` property), 98
outputs () (`fastr.core.tool.Tool` property), 113
outputs () (`fastr.plugins.FastrInterface` property), 214
outputs () (`fastr.plugins.FlowInterface` property), 216
outputs () (`fastr.plugins.NipypeInterface` property), 221
outputsize () (`fastr.execution.flownoderun.FlowNodeRun` property), 130
outputsize () (`fastr.execution.noderun.NodeRun` property), 157
outputsize () (`fastr.execution.sourcenoderun.SourceNodeRun` property), 161
outputsize () (`fastr.planning.node.FlowNode` property), 200
outputsize () (`fastr.planning.node.Node` property), 203
OutputSpec (class in `fastr.core.interface`), 98
OutputSpecBase (in module `fastr.core.interface`), 98

P

parent (`fastr.datatypes.BaseDataType` attribute), 121
parent () (`fastr.core.samples.SampleCollection` property), 105
parent () (`fastr.execution.linkrun.LinkRun` property), 151
parent () (`fastr.execution.noderun.NodeRun` property), 158
parent () (`fastr.planning.inputgroup.InputGroup` property), 176
parent () (`fastr.planning.link.Link` property), 194
parent () (`fastr.planning.node.Node` property), 203
parse () (`fastr.helpers.schematotable.SchemaPrinter` method), 173
parse_uri () (`fastr.plugins.XNATStorage` method), 232
parsed_value () (`fastr.datatypes.BaseDataType` property), 121
parsed_value () (`fastr.datatypes.Deferred` property), 124
parsed_value () (`fastr.datatypes.URLType` property), 127
path (in module `fastr.plugins`), 232
path () (`fastr.core.tool.Tool` property), 113
path_to_url () (`fastr.core.ioplugin.IOPlugin` method), 99
path_to_url () (`fastr.core.vfs.VirtualFileSystem` method), 116
path_to_url () (`fastr.plugins.FileSystem` method), 215
paths () (`fastr.plugins.LocalBinaryTarget` property), 219
pattern_properties_prevvalid () (in module `fastr.helpers.jsonschemaparser`), 170
pid_file () (`fastr.helpers.lockfile.DirectoryLock` property), 171
pid_file_name (`fastr.helpers.lockfile.DirectoryLock` attribute), 171
pim_batch_size () (`fastr.helpers.configmanager.Config` property), 165
pim_debug () (`fastr.helpers.configmanager.Config` property), 165
pim_finished_timeout () (`fastr.helpers.configmanager.Config` property), 165
pim_host () (`fastr.helpers.configmanager.Config` property), 165
pim_update_interval () (`fastr.helpers.configmanager.Config` property), 165
pim_username () (`fastr.helpers.configmanager.Config` property), 165
PimReporter (class in `fastr.plugins`), 221
plugin_class () (`fastr.datatypes.DataTypeManager` property), 123
plugin_class () (`fastr.plugins.managers.pluginmanager.PluginManager` property), 240
plugin_class () (`fastr.plugins.managers.pluginmanager.PluginSubManager` property), 240
PluginManager (class in `fastr.plugins.managers.pluginmanager`), 239
plugins_path () (`fastr.helpers.configmanager.Config` property), 165
PluginSubManager (class in `fastr.plugins.managers.pluginmanager`), 240
PluginsView (class in `fastr.plugins.managers.pluginmanager`), 240
poll_datatype () (`fastr.datatypes.DataTypeManager` method), 124
populate () (`fastr.datatypes.DataTypeManager` method), 124
populate () (`fastr.plugins.managers.toolmanager.ToolManager`

method), 241
post() (fastr.web.api.RunListApi method), 250
predefined() (fastr.core.cardinality.AsCardinalitySpec property), 91
predefined() (fastr.core.cardinality.CardinalitySpec property), 92
predefined() (fastr.core.cardinality.IntCardinalitySpec property), 93
preference (fastr.datatypes.TypeGroup attribute), 126
preferred_types()
 (fastr.datatypes.DataTypeManager property), 124
preferred_types()
 (fastr.execution.inputoutputrun.OutputRun property), 136
preferred_types()
 (fastr.execution.inputoutputrun.SubOutputRun property), 141
preferred_types()
 (fastr.helpers.configmanager.Config property), 165
preferred_types()
 (fastr.planning.inputoutput.Output property), 187
preferred_types()
 (fastr.planning.inputoutput.SubOutput property), 191
prepend() (fastr.helpers.configmanager.EmptyDefault method), 166
primary() (fastr.planning.inputgroup.InputGroup property), 176
print_help() (in module fastr.utils.cmd), 244
print_job_result() (in module fastr.helpers.report), 172
print_result() (fastr.core.ioplugin.IOPlugin static method), 99
print_sample_sink() (in module fastr.utils.cmd.trace), 246
print_samples() (in module fastr.utils.cmd.trace), 246
print_sinks() (in module fastr.utils.cmd.trace), 246
print_value() (fastr.planning.node.ConstantNode property), 199
printlines() (fastr.helpers.schematatable.SchemaPrinter method), 173
process_callbacks()
 (fastr.plugins.executionplugin.ExecutionPlugin method), 235
process_pool_worker_number()
 (fastr.helpers.configmanager.Config property), 165
processing_callback (fastr.execution.job.JobState attribute), 147
ProcessPoolExecution (class in fastr.plugins), 222
ProcessUsageCollection (class in fastr.core.target), 109
properties_postvalidate() (in module fastr.helpers.jsonschemasparser), 170
properties_prevalidate() (in module fastr.helpers.jsonschemasparser), 170
protected_modules()
 (fastr.helpers.configmanager.Config property), 165
prov() (in module fastr.web.views), 251
PROV_DUMP (fastr.execution.job.Job attribute), 142
Provenance (class in fastr.core.provenance), 100
provenance() (fastr.datatypes.Deferred property), 125
provfile() (fastr.execution.job.Job property), 144
provurl() (fastr.execution.job.Job property), 144
pull_source_data() (fastr.core.ioplugin.IOPlugin method), 99
pull_source_data()
 (fastr.plugins.managers.iopluginmanager.IOPPluginManager method), 237
push_sink_data() (fastr.core.ioplugin.IOPlugin method), 100
push_sink_data() (fastr.plugins.managers.iopluginmanager.IOPPlugin method), 237
push_sink_data() (fastr.plugins.Reference method), 224
put_url() (fastr.core.ioplugin.IOPlugin method), 100
put_url() (fastr.core.vfs.VirtualFileSystem method), 116
put_url() (fastr.plugins.FileSystem method), 215
put_url() (fastr.plugins.managers.iopluginmanager.IOPPluginManager method), 237
put_url() (fastr.plugins.Null method), 221
put_url() (fastr.plugins.S3Filesystem method), 225
put_url() (fastr.plugins.XNATStorage method), 232
put_value() (fastr.core.ioplugin.IOPlugin method), 100
put_value() (fastr.core.vfs.VirtualFileSystem method), 116
put_value() (fastr.plugins.FileSystem method), 215
put_value() (fastr.plugins.Null method), 221
put_value() (fastr.plugins.S3Filesystem method), 225
Python Enhancement Proposals
 PEP 8#class-names, 28
 PEP 8#global-variable-names, 28
 PEP 8#method-names-and-instance-variables, 28
 PEP 8#package-and-module-names, 28
 PEP 8#prescriptive-naming-conventions, 28
Python Enhancement Proposals
 PEP 8, 27

Q

queue (*fastr.plugins.executionplugin.JobAction attribute*), 235
 queue_job () (*fastr.plugins.executionplugin.ExecutionPlugin method*), 235
 queued (*fastr.execution.job.JobState attribute*), 147
 quote_argument () (in module *fastr.helpers.shellescape*), 173

R

RangeCardinalitySpec (class in *fastr.core.cardinality*), 93
 raw_value () (*fastr.datatypes.BaseDataType property*), 121
 read_bytes () (*fastr.core.target.SystemUsageInfo property*), 110
 read_config () (*fastr.helpers.configmanager.Config method*), 165
 read_config_files (*fastr.helpers.configmanager.Config attribute*), 165
 read_config_string () (*fastr.helpers.configmanager.Config method*), 165
 read_sink_data () (in module *fastr.utils.cmd.trace*), 246
 readfastrschema () (*fastr.helpers.jsonschema.parser.FastrRefResolver static method*), 169
 readfile () (*fastr.helpers.jsonschema.parser.FastrRefResolver static method*), 169
 Reference (class in *fastr.plugins*), 223
 references (*fastr.core.tool.Tool attribute*), 113
 register_fields () (*fastr.helpers.configmanager.Config method*), 165
 register_job () (*fastr.plugins.executionplugin.ExecutionPlugin method*), 235
 register_listener () (in module *fastr.helpers.events*), 167
 register_signals () (*fastr.execution.networkrun.NetworkRun method*), 155
 register_url_scheme () (*fastr.plugins.managers.iopluginmanager.IOPPluginManager static method*), 238
 register_url_scheme () (in module *fastr.data.url*), 119
 release () (*fastr.helpers.lockfile.DirectoryLock method*), 171
 release_job () (*fastr.plugins.executionplugin.ExecutionPlugin method*), 235
 reload () (*fastr.execution.environmentmodules.EnvironmentModules method*), 128

remove () (*fastr.execution.inputoutputrun.InputRun method*), 133
 remove () (*fastr.planning.inputoutput.Input method*), 184
 remove () (*fastr.planning.inputoutput.SubInput method*), 190
 remove () (*fastr.planning.network.Network method*), 198
 remove_listener () (in module *fastr.helpers.events*), 167
 reporting_plugins () (*fastr.helpers.configmanager.Config property*), 165
 ReportingPlugin (class in *fastr.plugins.reportingplugin*), 235
 request_parser (*fastr.web.api.RunListApi attribute*), 250
 required () (*fastr.planning.inputoutput.BaseInputOutput property*), 181
 requirements (*fastr.core.tool.Tool attribute*), 113
 ResourceLimit (class in *fastr.api*), 88
 ResourceLimit (class in *fastr.core.resourcelimit*), 101
 resources () (*fastr.execution.job.Job property*), 144
 resources () (*fastr.execution.noderun.NodeRun property*), 158
 resourcesdir () (*fastr.helpers.configmanager.Config property*), 165
 RESULT_DUMP (*fastr.execution.job.Job attribute*), 142
 resulting_datatype () (*fastr.execution.inputoutputrun.OutputRun property*), 136
 resulting_datatype () (*fastr.execution.inputoutputrun.SubOutputRun property*), 141
 resulting_datatype () (*fastr.execution.inputoutput.Output property*), 187
 resulting_datatype () (*fastr.planning.inputoutput.SubOutput property*), 191
 rmem () (*fastr.core.target.SystemUsageInfo property*), 110
 RQExecution (class in *fastr.plugins*), 223
 Run (class in *fastr.web.api*), 249
 run_command () (*fastr.core.target.Target method*), 110
 run_command () (*fastr.plugins.DockerTarget method*), 210
 run_command () (*fastr.plugins.LocalBinaryTarget method*), 219
 run_command () (*fastr.plugins.MacroTarget method*), 219
 run_command () (*fastr.plugins.SingularityTarget method*), 226

```

run_finished (fastr.helpers.events.EventType attribute), 167
run_finished() (fastr.plugins.PimReporter method), 222
run_finished() (fastr.plugins.reportingplugin.Reporting method), 235
run_finished() (fastr.plugins.SimpleReport method), 225
run_job() (fastr.plugins.RQExecution class method), 223
run_network() (fastr.web.api.Run method), 249
run pylint() (in module fastr.utils.cmd pylint), 245
run_started (fastr.helpers.events.EventType attribute), 167
run_started() (fastr.plugins.PimReporter method), 222
run_started() (fastr.plugins.reportingplugin.Reporting method), 235
RunApi (class in fastr.web.api), 249
runapp() (in module fastr.web.run), 251
RunListApi (class in fastr.web.api), 250
running (fastr.execution.job.JobState attribute), 147

S
S3Filesystem (class in fastr.plugins), 224
SampleBaseId (class in fastr.core.samples), 103
SampleCollection (class in fastr.core.samples), 103
SampleId (class in fastr.core.samples), 105
SampleIndex (class in fastr.core.samples), 105
SampleItem (class in fastr.core.samples), 105
SampleItemBase (class in fastr.core.samples), 106
SamplePayload (class in fastr.core.samples), 107
samples() (fastr.core.samples.ContainsSamples property), 102
samples() (fastr.execution.inputoutputrun.OutputRun property), 136
samples() (fastr.execution.inputoutputrun.SubOutputRun property), 141
samples() (fastr.planning.inputoutput.SubOutput property), 191
SampleValue (class in fastr.core.samples), 108
save() (fastr.api.Network method), 75
save_gpickle() (in module fastr.helpers.iohelpers), 168
save_json() (in module fastr.helpers.iohelpers), 168
save_version() (in module fastr.version), 88
SBATCH (fastr.plugins.SlurmExecution attribute), 226
SCANCEL (fastr.plugins.SlurmExecution attribute), 226
schemadir() (fastr.helpers.configmanager.Config property), 166
SchemaPrinter (class in fastr.helpers.schematatable), 172
scheme (fastr.plugins.CommaSeperatedValueFile attribute), 208
scheme (fastr.plugins.FileSystem attribute), 215
scheme (fastr.plugins.HTTPPlugin attribute), 217
scheme (fastr.plugins.Null attribute), 221
scheme (fastr.plugins.Reference attribute), 224
scheme (fastr.plugins.S3Filesystem attribute), 225
scheme (fastr.plugins.VirtualFileSystem attribute), 228
scheme (fastr.plugins.VirtualFileSystemRegularExpression attribute), 229
scheme (fastr.plugins.VirtualFileSystemValueList attribute), 230
scheme (fastr.plugins.XNATStorage attribute), 232
scheme () (fastr.core.ioplugin.IOPlugin property), 100
scheme () (fastr.core.vfs.VirtualFileSystem property), 116
SCONTROL (fastr.plugins.SlurmExecution attribute), 226
send_job() (fastr.plugins.DRMAAExecution method), 209
sequence_part() (fastr.core.samples.SampleValue method), 108
serialize() (fastr.core.provenance.Provenance method), 101
server() (fastr.plugins.XNATStorage property), 232
set_data() (fastr.execution.networkrun.NetworkRun method), 155
set_data() (fastr.execution.sinknoderun.SinkNodeRun method), 159
set_data() (fastr.execution.sourcenoderun.ConstantNodeRun method), 162
set_data() (fastr.execution.sourcenoderun.SourceNodeRun method), 161
set_data() (fastr.planning.node.ConstantNode method), 199
set_data() (fastr.planning.node.SourceNode method), 205
set_field() (fastr.helpers.configmanager.Config method), 166
set_result() (fastr.execution.flownoderun.AdvancedFlowNodeRun method), 130
set_result() (fastr.execution.flownoderun.FlowNodeRun method), 130
set_result() (fastr.execution.noderun.NodeRun method), 158
set_result() (fastr.execution.sinknoderun.SinkNodeRun method), 159
setup() (fastr.core.ioplugin.IOPlugin method), 100
setup() (fastr.core.vfs.VirtualFileSystem method), 116
sha1_checksum() (in module fastr.helpers.checksum), 163
show_jobs() (fastr.plugins.executionplugin.ExecutionPlugin method), 235
shutdown() (in module fastr.web.views), 251
shutdown_server() (in module fastr.web.views), 251
signal_dependent_jobs()

```

(*fastr.plugins.executionplugin.ExecutionPlugin method*), 235
SimpleReport (*class in fastr.plugins*), 225
SINGULARITY_BIN (*fastr.plugins.SingularityTarget attribute*), 225
SingularityTarget (*class in fastr.plugins*), 225
sink () (*in module fastr.utils.cmd.sink*), 246
SINK_DUMP_FILE_NAME
 (*fastr.execution.networkrun.NetworkRun attribute*), 153
SINK_DUMP_FILE_NAME
 (*fastr.planning.network.Network attribute*), 194
SinkJob (*class in fastr.execution.job*), 147
sinklist () (*fastr.execution.networkrun.NetworkRun property*), 155
SinkNode (*class in fastr.planning.node*), 204
SinkNodeRun (*class in fastr.execution.sinknoderun*), 158
size () (*fastr.core.dimension.Dimension property*), 95
size () (*fastr.core.dimension.HasDimensions property*), 96
size () (*fastr.execution.inputoutputrun.SourceOutputRun property*), 137
size () (*fastr.execution.linkrun.LinkRun property*), 151
slurm_job_check_interval ()
 (*fastr.helpers.configmanager.Config property*), 166
slurm_partition ()
 (*fastr.helpers.configmanager.Config property*), 166
SlurmExecution (*class in fastr.plugins*), 226
solve_broadcast ()
 (*fastr.planning.inputgroup.InputGroup class method*), 176
source () (*fastr.core.dimension.ForwardsDimensions property*), 96
source () (*fastr.execution.inputoutputrun.InputRun property*), 133
source () (*fastr.execution.inputoutputrun.SubInputRun property*), 139
source () (*fastr.execution.linkrun.LinkRun property*), 151
source () (*fastr.planning.inputoutput.Input property*), 184
source () (*fastr.planning.inputoutput.SubInput property*), 190
source () (*fastr.planning.link.Link property*), 194
source () (*in module fastr.utils.cmd.source*), 246
SOURCE_DUMP_FILE_NAME
 (*fastr.execution.networkrun.NetworkRun attribute*), 153
SOURCE_DUMP_FILE_NAME
 (*fastr.planning.network.Network attribute*), 194
source_job_limit ()
 (*fastr.helpers.configmanager.Config property*), 166
source_output () (*fastr.execution.inputoutputrun.SubInputRun property*), 139
source_output () (*fastr.planning.inputoutput.SubInput property*), 190
sourcegroup () (*fastr.execution.sourcenoderun.SourceNodeRun property*), 161
sourcegroup () (*fastr.planning.node.SourceNode property*), 206
SourceJob (*class in fastr.execution.job*), 148
sourcelist () (*fastr.execution.networkrun.NetworkRun property*), 155
SourceNode (*class in fastr.planning.node*), 205
SourceNodeRun
 (*class in fastr.execution.sourcenoderun*), 160
SourceOutput (*class in fastr.planning.inputoutput*), 187
SourceOutputRun
 (*class in fastr.execution.inputoutputrun*), 136
spec_fields ()
 (*fastr.plugins.DRMAAExecution property*), 209
split () (*in module fastr.data.url*), 119
SQUEUE (*fastr.plugins.SlurmExecution attribute*), 226
SQUEUE_FORMAT (*fastr.plugins.SlurmExecution attribute*), 226
status () (*fastr.core.version.Version property*), 115
status () (*fastr.execution.job.Job property*), 144
status () (*fastr.execution.linkrun.LinkRun property*), 151
status () (*fastr.execution.noderun.NodeRun property*), 158
status () (*fastr.planning.link.Link property*), 194
status () (*fastr.planning.node.Node property*), 203
status () (*fastr.web.api.Run method*), 249
STATUS_MAPPING (*fastr.plugins.SlurmExecution attribute*), 226
StatusApi (*class in fastr.web.api*), 250
STDERR_DUMP (*fastr.execution.job.Job attribute*), 142
stderrfile () (*fastr.execution.job.Job property*), 144
stderrurl () (*fastr.execution.job.Job property*), 144
stdout (*in module fastr.plugins*), 232
STDOUT_DUMP (*fastr.execution.job.Job attribute*), 142
stdoutfile () (*fastr.execution.job.Job property*), 144
stdouturl () (*fastr.execution.job.Job property*), 144
store ()
 (*fastr.helpers.filesynchelperFileSyncHelper method*), 168
StrongrExecution (*class in fastr.plugins*), 227
SubInput (*class in fastr.planning.inputoutput*), 188
SubInputRun (*class in fastr.execution.inputoutputrun*), 137
submit_jobs ()
 (*fastr.plugins.DRMAAExecution*

method), 209
SubOutput (class in *fastr.planning.inputoutput*), 190
SubOutputRun (class in *fastr.execution.inputoutputrun*), 139
SubprocessBasedTarget (class in *fastr.core.target*), 109
substitute () (*fastr.execution.job.SinkJob* method), 148
SubUrl (class in *fastr.web.api*), 250
suffix () (*fastr.core.version.Version* property), 115
SUPPORTED_APIS (*fastr.plugins.PimReporter* attribute), 221
SUPPORTS_CANCEL (*fastr.plugins.DRMAAExecution* attribute), 208
SUPPORTS_CANCEL (*fastr.plugins.executionplugin.ExecutionPlugin* attribute), 233
SUPPORTS_CANCEL (*fastr.plugins.SlurmExecution* attribute), 226
SUPPORTS_DEPENDENCY (*fastr.plugins.DRMAAExecution* attribute), 208
SUPPORTS_DEPENDENCY (*fastr.plugins.executionplugin.ExecutionPlugin* attribute), 233
SUPPORTS_DEPENDENCY (*fastr.plugins.SlurmExecution* attribute), 226
SUPPORTS_HOLD_RELEASE (*fastr.plugins.DRMAAExecution* attribute), 208
SUPPORTS_HOLD_RELEASE (*fastr.plugins.executionplugin.ExecutionPlugin* attribute), 233
SUPPORTS_HOLD_RELEASE (*fastr.plugins.SlurmExecution* attribute), 226
swap () (*fastr.execution.environmentmodules.EnvironmentModule* method), 128
switch_sample_sink () (in module *fastr.utils.cmd.trace*), 246
sync () (*fastr.execution.environmentmodules.EnvironmentModule* method), 129
systemdir () (*fastr.helpers.configmanager.Config* property), 166
SystemUsageInfo (class in *fastr.core.target*), 109

T

tags (*fastr.core.tool.Tool* attribute), 113
Target (class in *fastr.core.target*), 110
target () (*fastr.core.tool.Tool* property), 113
target () (*fastr.datatypes.Deferred* property), 125
target () (*fastr.execution.linkrun.LinkRun* property), 151
target () (*fastr.planning.link.Link* property), 194

TargetManager (class in *fastr.plugins.managers.targetmanager*), 241
TargetResult (class in *fastr.core.target*), 110
test () (*fastr.core.interface.Interface* class method), 98
test () (*fastr.core.target.Target* class method), 110
test () (*fastr.core.tool.Tool* method), 113
test () (*fastr.datatypes.BaseDataType* class method), 121
test () (*fastr.planning.network.Network* class method), 198
test () (*fastr.plugins.BlockingExecution* class method), 206
test () (*fastr.plugins.DRMAAExecution* class method), 209
ExecutionPlugin (*fastr.plugins.ElasticsearchReporter* class method), 211
test () (*fastr.plugins.LinearExecution* class method), 217
test () (*fastr.plugins.MacroTarget* class method), 220
test () (*fastr.plugins.NipypeInterface* class method), 221
test () (*fastr.plugins.ProcessPoolExecution* class method), 223
test () (*fastr.plugins.RQExecution* class method), 223
test () (*fastr.plugins.S3Filesystem* class method), 225
test () (*fastr.plugins.SingularityTarget* class method), 226
test () (*fastr.plugins.SlurmExecution* class method), 226
test () (*fastr.plugins.StrongrExecution* class method), 227
test_spec (*fastr.core.tool.Tool* attribute), 113
test_tool () (*fastr.core.tool.Tool* class method), 113
time () (*fastr.api.ResourceLimit* property), 89
time () (*fastr.core.resourcelimit.ResourceLimit* property), 102

EnvironmentModule.stamp () (*fastr.core.target.SystemUsageInfo* property), 110
tmpurl () (*fastr.execution.job.Job* property), 144
tmpurl () (*fastr.execution.job.SinkJob* property), 148

ObjectManager.*Object* () (*fastr.plugins.managers.objectmanager.ObjectManager* method), 239

Tool (class in *fastr.core.tool*), 111
tool () (*fastr.execution.job.Job* property), 144
tool () (*fastr.execution.noderun.NodeRun* property), 158
tool () (*fastr.planning.node.Node* property), 204
tool () (in module *fastr.utils.cmd.test*), 246
tool () (in module *fastr.web.views*), 251
TOOL_REFERENCE_FILE_NAME (*fastr.core.tool.Tool* attribute), 111
TOOL_RESULT_FILE_NAME (*fastr.core.tool.Tool* attribute), 111
ToolApi (class in *fastr.web.api*), 251

T
 toolist () (*fastr.utils.cmd.upgrade.FastrNamespaceType* property), 247
 ToolListApi (*class in fastr.web.api*), 251
 ToolManager (*class in fastr.plugins.managers.toolmanager*), 241
 tools (*fastr attribute*), 71
 tools_path () (*fastr.helpers.configmanager.Config property*), 166
 toolversions () (*fastr.plugins.managers.toolmanager.ToolManager* method), 242
 TORQUE_NATIVE_SPEC
 (*fastr.plugins.DRMAAExecution attribute*), 208
 tostring_modvalue ()
 (*fastr.execution.environmentmodules.EnvironmentModules static method*), 129
 totuple_modvalue ()
 (*fastr.execution.environmentmodules.EnvironmentModules static method*), 129
 translate_argument () (*fastr.execution.job.Job class method*), 144
 translate_output_results ()
 (*fastr.execution.job.Job static method*), 145
 translate_results () (*fastr.execution.job.Job method*), 145
 TypeGroup (*class in fastr.datatypes*), 125
 typelist () (*fastr.utils.cmd.upgrade.FastrNamespaceType property*), 247
 types (*fastr attribute*), 71
 types_path () (*fastr.helpers.configmanager.Config property*), 166

U
 unload () (*fastr.execution.environmentmodules.EnvironmentModules* method), 129
 unmerge () (*fastr.planning.inputgroupcombiner.BaseInputGroupCombiner* method), 177
 unmerge () (*fastr.planning.inputgroupcombiner.DefaultInputGroupCombiner* method), 177
 unmerge () (*fastr.planning.inputgroupcombiner.MergingInputGroupCombiner* method), 178
 unregister_signals ()
 (*fastr.execution.networkrun.NetworkRun method*), 155
 update () (*fastr.helpers.configmanager.EmptyDefault method*), 167
 update () (*fastr.planning.inputgroupcombiner.BaseInputGroupCombiner* method), 177
 update () (*fastr.planning.inputgroupcombiner.MergingInputGroupCombiner* method), 178
 update_input_groups ()
 (*fastr.execution.noderun.NodeRun method*), 158

V
 update_input_groups ()
 (*fastr.planning.node.Node method*), 204
 update_job_result () (in module *fastr.web.api*), 251
 update_size () (*fastr.core.dimension.Dimension method*), 95
 update_status () (in module *fastr.web.api*), 251
 upgrade_network () (in module *fastr.utils.cmd.upgrade*), 247
 upgrade_tool () (in module *fastr.utils.cmd.upgrade*), 247
 upload () (*fastr.plugins.XNATStorage static method*), 232
 url (*fastr.core.tool.Tool attribute*), 113
 modules_path () (*fastr.core.ioplugin.IOPPlugin method*), 100
 url_to_path () (*fastr.core.vfs.VirtualFileSystem method*), 116
 url_to_path () (*fastr.plugins.FileSystem method*), 215
 url_to_path () (*fastr.plugins.iopluginmanager.IOPPluginManager method*), 238
 URLType (*class in fastr.datatypes*), 126
 usage_type (*fastr.core.target.ProcessUsageCollection attribute*), 109
 userdir () (*fastr.helpers.configmanager.Config property*), 166

ValueCardinalitySpec (*class in fastr.core.cardinality*), 94
ValueType (*class in fastr.datatypes*), 127

verify_resource_loading() (in module
fastr.utils.verify), 244
verify_tool() (in module fastr.utils.verify), 244
Version (class in fastr.core.version), 113
version (fastr.core.tool.Tool attribute), 113
version (fastr.datatypes.BaseDataType attribute), 121
version (fastr.datatypes.EnumType attribute), 125
version() (fastr.api.Network property), 75
version_matcher (fastr.core.version.Version attribute), 115
VirtualFileSystem (class in fastr.core.vfs), 115
VirtualFileSystem (class in fastr.plugins), 227
VirtualFileSystemRegularExpression (class
in fastr.plugins), 228
VirtualFileSystemValueList (class in
fastr.plugins), 229
vmem() (fastr.core.target.SystemUsageInfo property),
110

W

wait_for_file() (fastr.helpers.filesynchelperFileSyncHelper
method), 168
wait_for_job() (fastr.helpers.filesynchelperFileSyncHelper
method), 168
wait_for_pickle()
(fastr.helpers.filesynchelperFileSyncHelper
method), 168
wait_for_vfs_url()
(fastr.helpers.filesynchelperFileSyncHelper
method), 168
warn_develop() (fastr.helpers.configmanager.Config
property), 166
web_hostname() (fastr.helpers.configmanager.Config
property), 166
web_port() (fastr.helpers.configmanager.Config prop-
erty), 166
web_secret_key() (fastr.helpers.configmanager.Config
property), 166
web_url() (fastr.helpers.configmanager.Config
method), 166
websocket_client() (in module fastr.web.views),
252
which() (in module fastr.helpers.procutils), 172
write() (fastr.execution.job.Job method), 145
write_bytes() (fastr.core.target.SystemUsageInfo
property), 110

X

xnat() (fastr.plugins.XNATStorage property), 232
XNATStorage (class in fastr.plugins), 230