
gs.config Documentation

Release 2.3.0

GroupServer.org

April 28, 2016

1	gs.config API Reference	3
1.1	Configuration	3
1.2	Errors	5
2	Example	7
2.1	File	7
2.2	Parsing	7
3	Changelog	9
3.1	2.3.0 (2015-03-30)	9
3.2	2.2.0 (2015-03-17)	9
3.3	2.1.3 (2014-09-16)	9
3.4	2.1.2 (2014-06-24)	9
3.5	2.1.1 (2014-05-05)	9
3.6	2.1.0 (2014-04-25)	9
3.7	2.0.0 (2013-08-10)	10
3.8	1.0.0 (2012-07-13)	10
4	Resources	11
5	Indices and tables	13
	Python Module Index	15

This package provides some classes that are used to manage “sets” of configuration options.

Contents:

gs.config API Reference

The package exports the following API symbols.

1.1 Configuration

class `gs.config.Config(configset, configpath=None)`
The configuration.

Method `Config(configset, configpath=None)`

Parameters

- **configset** (`str`) – The name of the configuration set to read.
- **configpath** (`str`) – The path to the configuration file. If `None` and Zope is being used then some standard Zope configuration directories are checked (see `Config.get_zope_config()`).

Raises

- `gs.config.errors.ConfigPathError` – No path could be found.
- `gs.config.errors.ConfigFileError` – The configuration file could not be read.
- `gs.config.errors.ConfigSetError` – The configuration file lacks configset.

The actual parsing of the configuration file is done by the `ConfigParser` module.

get (`configtype, strict=True`)

Get the values defined in a section

Parameters

- **configtype** (`str`) – The ID for the section to retrieve.
- **strict** (`bool`) – If `True` (the default) then a `ConfigNoOption` error is raised when an option is present in the configuration file but absent from the schema. When `False` the option is ignored.

Returns The values for all options in the provided section.

Return type A dict containing `optionId: value` pairs. The values are coerced using the schema set by `set_schema()`.

Raises

- `gs.config.errors.ConfigNoSectionError` – No section for the ID in configType exists.
- `gs.config.errors.ConfigNoOptionError` – An option was present in the configuration file but absent from the section.
- `gs.config.errors.ConfigConvertError` – An option could not be coerced.

Example:

```
smtpConfig = config.get('smtp')
```

get_schema(configType)

Get the schema that is currently set for a section.

Parameters `configType (str)` – The identifier for the section.

Returns The schema that is currently set for the section.

Return type A dict, containing optionId: type pairs.

Raises `gs.config.errors.ConfigNoSchemaError` – No schema with the identifier configType found.

static get_zope_config()

Try and figure out where the groupserver config is, using Zope

Returns The location of the config file from Zope.

Return type str

Raises `gs.config.errors.ConfigFileError` – The configuration file failed to be read.

The location of the configuration file should either be the \$ZOPE_HOME/etc/gsconfig.ini or \$INSTANCE_HOME/etc/gsconfig.ini, with the latter preferred for backwards compatibility, but the former being more typical. This normally equates to etc/gsconfig.ini within what the installation documentation refers to as *the GroupServer directory*.

keys()

Get the list of sections that are currently defined.

Returns A list of sections for the configuration set.

Return type list

set_schema(configType, schema)

Set the schema that is used for parsing the options.

Parameters

- `configType (str)` – The identifier for the section of the configuration.
- `schema (dict)` – The schema for the section, as optionId: type pairs.

When the value for an option in a section is retrieved its type is coerced from a string to one of the types passed in as schema.

Example:

```
s = {'station': str,
      'frequency': int,}
conf.set_schema('radio', s)
```

`gs.config.getId()`

Get the ID of the current instance.

Returns The ID the of the instance, or `default`

Return type `str`

It can be useful to have multiple *instances* running on one server, but configured separately. The `getInstanceId` function gets the ID of the current instance by looking it up in the `HTTP_INSTANCEID` property of the current Zope HTTP request. If Zope (and HTTP) are not being used then `default` is returned.

This function is defined in `gs.config` mostly out of convenience, as GroupServer normally organises its configuration into *instances*.

1.2 Errors

The possible configuration errors.

exception `gs.config.errors.ConfigConvertError`

An error raised when the value cannot be converted.

exception `gs.config.errors.ConfigError`

A generic error with the configuration.

exception `gs.config.errors.ConfigFileError`

An error with reading the config file

exception `gs.config.errors.ConfigNoOptionError`

An error raised when an option is not defined in a schema

exception `gs.config.errors.ConfigNoSchemaError`

An error raised when there is no schema

exception `gs.config.errors.ConfigNoSectionError`

An error raised when there is no configuration section specified.

exception `gs.config.errors.ConfigPathError`

An error with the path to the config file.

exception `gs.config.errors.ConfigSetError`

An error with the structure of the config file.

Example

Below is an example of a *file* with configuration sets, and *parsing* the file.

2.1 File

In the following example the default configuration-set contains two items, `smtp` and `pop`. The the configuration for this set is provided by the `smtp-local` and `pop-local` sections. The `smtp-remote` section is currently unused by the configuration set.

```
[config-default]
smtp = local
pop = local

[smtp-local]
server = localhost
port = 2525

[pop-local]
server = localhost
port = 110

[smtp-remote]
server = smtp.example.com
port = 25
```

2.2 Parsing

A configuration class is initialised. The second parameter is optional, depending on the degree to which we want the environment to configure things automatically.

```
>>> from gs.config import Config
>>> config = Config('default', '/example/file.ini')
```

A schema must be provided before data is retrieved. For example, setting the server to be a string, and a port to be an integer.

```
>>> config.set_schema('smtp', {'server': str, 'port': int})
```

Then a specific configuration section, with all the options can be retrieved as a dict.

```
>>> config.get('smtp')
{'port': 2525, 'server': localhost}
```

If file fails to fit the schema then a ConfigError is raised:

```
>>> config.set_schema('smtp', {'someparam': int})
>>> config.get('smtp')
```

```
Traceback (most recent call last):
  File "<console>", line 1, in <module>
    File "config.py", line 201, in get
      raise ConfigNoOptionError(msg)
ConfigNoOptionError: No option "server" defined in schema for "smtp".
```

However, it is possible to parse the configuration in a lax way, by passing strict=False. This allows for hard-coded defaults:

```
>>> config.get('smtp', strict=False)
{}
```

Changelog

3.1 2.3.0 (2015-03-30)

- Checking both the instance home and the Zope-home for the configuration file

3.2 2.2.0 (2015-03-17)

- Allowing the parsing of the configuration file to be lax

3.3 2.1.3 (2014-09-16)

- Renaming the `*txt` files as `*rst` files, for [GitHub](#)

3.4 2.1.2 (2014-06-24)

- Fixing a coding error, where a `m` was used in an error, rather than a `msg`

3.5 2.1.1 (2014-05-05)

- Added Sphinx documentation

3.6 2.1.0 (2014-04-25)

- Adding Python 3 support
- Updating documentation
- Adding unit tests and tox support

3.7 2.0.0 (2013-08-10)

- Merge of some code from `gs.database`
- Reduced dependency on Zope (now an extra requirement)

3.8 1.0.0 (2012-07-13)

- Initial version

Resources

- Documentation: <http://groupserver.readthedocs.io/projects/gsconfig>
- Code repository: <https://github.com/groupserver/gs.config>
- Questions and comments to <http://groupserver.org/groups/development>
- Report bugs at <https://redmine.iopen.net/projects/groupserver>

Indices and tables

- genindex
- modindex
- search

g

gs.config.errors, 5

C

[Config](#) (class in `gs.config`), [3](#)
[ConfigConvertError](#), [5](#)
[ConfigError](#), [5](#)
[ConfigFileError](#), [5](#)
[ConfigNoOptionError](#), [5](#)
[ConfigNoSchemaError](#), [5](#)
[ConfigNoSectionError](#), [5](#)
[ConfigPathError](#), [5](#)
[ConfigSetError](#), [5](#)

G

[get\(\)](#) (`gs.config.Config` method), [3](#)
[get_schema\(\)](#) (`gs.config.Config` method), [4](#)
[get_zope_config\(\)](#) (`gs.config.Config` static method), [4](#)
[getInstanceId\(\)](#) (in module `gs.config`), [4](#)
[gs.config.errors](#) (module), [5](#)

K

[keys\(\)](#) (`gs.config.Config` method), [4](#)

S

[set_schema\(\)](#) (`gs.config.Config` method), [4](#)