Sark Documentation


Release 0.1.0

Tamir Bahar

Mar 18, 2022

Contents

1	Getti	ng Started	3		
2	2 Table of Contents				
	2.1	Introduction	5		
	2.2	Installation			
	2.3	API	7		
	2.4	Examples	17		
	2.5	Plugins	20		
		Debugging IDAPython Scripts			
		Support			
	2.8	How To Contribute	30		
	2.9	Credits	30		



Sark (named after the notorious Tron villain) is an object-oriented scripting layer written on top of IDAPython. Sark is easy to use and provides tools for writing advanced scripts and plugins.

Sark actively supports IDA7.4 and Python3. For older versions, see Support.

CHAPTER 1

Getting Started

Install Sark from the command line:

pip3 install -U git+https://github.com/tmr232/Sark.git#egg=Sark

Import inside IDA, and start having fun!

```
import sark
import idaapi
# Get the current function
func = sark.Function()
# Print all lines in the function
for line in func.lines:
    idaapi.msg("{}\n".format(line))
```

```
[00401336]
                                                                                                              \sim
                 mov
                            esi, eax
[00401338]
                            [esp+24h], al
                 MOV
[0040133C]
                            byte ptr [esp+30h], 1
                 MOV
[00401341]
                            edi, eax
                 mov
[00401343]
                 mov
                            ebx, eax
                           [esp+28h], eax
ds:__imp__HeapSetInformation@16; HeapSetInformation(x,x,x,x)
ds:__imp__GetConsoleOutputCP@0; GetConsoleOutputCP()
[00401345]
                 MOV
[00401349]
                 call
[0040134F]
                 call
[00401355]
                 push
                            eax
                            offset pszFormat; ".%u"
[00401356]
                 push
[0040135B]
                 lea
                            eax, [esp+1C4h]
                                                                                                              U,
```

Python

```
# Mark all the lines containing xrefs outside the function
for xref in func.xrefs_from:
    sark.Line(xref.frm).color = 0x8833FF
```

	MOV	[esp+ <mark>24h</mark>], al
	mov	byte ptr [esp+30h], 1
	mov	edi, eax
	mov	ebx, eax
	mov	[esp+28h], eax
	call	<pre>ds:impHeapSetInformation@16 ; HeapSetInformation(x,x,x,x)</pre>
	call	<pre>ds:impGetConsoleOutputCP@0 ; GetConsoleOutputCP()</pre>
	push	
	push	offset pszFormat ; ".%u"
	lea	eax, [esp+1C4h]
	push	ØCh
	push	eax
	call	_StringCchPrintfW
00.000	Lota Anon	ACD 40b
100.00\$	(917,400)	(728,185) 0000070C 0040130C: _main+3 (Synchronized with Hex View-1)

CHAPTER 2

Table of Contents

Contents:

2.1 Introduction

Even with books like Alexander Hanel's The Beginner's Guide to IDAPython, writing IDA scripts still remains a daunting task. The need to dive into the IDA SDK's header files (all 54 of them), read idaapi.py, idc.py and idautils.py, and preferably some existing plugins as well, wards off many researchers and keeps the script & plugin writing community small.

Being a researcher myself, I wanted to make scripting IDA a bit easier and more intuitive. I wanted to spend the majority of my (scripting) time writing code (be it in a code editor or an interactive shell) and not reading someone else's (I prefer spending my reading efforts on assembly.) So I created Sark.

Sark, (named after the notorious Tron villain,) is an object-oriented scripting layer written on top of IDAPython to provide ease of use, as well as additional tools for writing advanced scripts and plugins.

This tutorial will show you the basics of Sark, to get you started right away.



2.2 Installation

2.2.1 For Sark Users

To get the bleeding edge version, use:

pip3 install -U git+https://github.com/tmr232/Sark.git#egg=Sark

For older versions of IDA (7.3 or lower), use:

pip2 install -U git+https://github.com/tmr232/Sark.git@IDA-6.x#egg=Sark

And see Support

Alternatively, you can install Sark directly from PyPI. The Sark version will match the IDA versions, more or less. So for 7.4 or higher, you'll just want the latest:

pip3 install sark

But for 7.3 or earlier, you'll want a version smaller than 7.4:

pip2 install "sark<7.4"

That said, installing from the repo is the only way to be sure you get the latest version of Sark.

To install the IDA Plugins (optional) download the entire repository from GitHub and read Installing Plugins.

Updates

To update Sark to the latest version, just run the installation command again.

2.2.2 For Sark Developers

If you want to help in the development of Sark, follow this.

Clone the Sark repository to get the latest version

```
git clone https://github.com/tmr232/Sark.git && cd Sark pip3 install -e .
```

Updates

To update Sark to the latest version (including all *installed* codecs and plugins) simply pull the latest version from the repo

git pull

2.3 API

2.3.1 Tutorial Conventions

IDA IPython is used in the examples unless stated otherwise. For brevity, assume the following code precedes any example code.

import idaapi, idc, idautils
import sark

As Sark is a large, evolving library, the API documentation provided here will be partial and only include what is needed to get you started. However, the Sark code in itself is heavily documented.

2.3.2 Lines

Lines are the most basic and intuitive object in Sark. A line in the IDA-View is a line in Sark. Let's have a look.

```
>>> my_line = sark.Line() # Same as `sark.Line(ea=idc.here())`
>>> print(my_line)
[00417401] mov ebp, esp
>>> my_line.comments.regular = "The line at 0x{:08X}".format(my_line.ea)
>>> print(my_line)
[00417401] mov ebp, esp ; The line at 0x00417401
```

The sark.Line object encapsulates most of the line-relevant functions of IDAPython. Some examples include:

Member	Usage
ea	line's address
comments	line comments
name	the name of the line (if any)
insn	assembly instruction
xrefs_to	cross references to the line
xrefs_from	cross references from the line
bytes	the actual bytes in the line

For the rest, I suggest reading the highly documented code, or using the interactive shell to experiment with the sark.Line object.

The line object contains 4 notable members: comments, insn and the xrefs_* pair.

Line Comments

The comments member provides access to all comment types: - Regular comments - Repeating comments - Anterior lines - Posterior lines

It allows you to get, as well as set comments. Each change to the comments will cause the UI to refresh.

```
>>> anterior = my_line.comments.anterior
>>> my_line.comments.regular = "My Regular Comment"
```

Line Xrefs

Provide access to Xref objects describing the line's cross references. Xref objects will be discussed later under *Xrefs*.

Instructions

Provide access to the line's instructions, down to the single operand. Instruction objects will be discussed later under *Instructions*.

Getting Lines

There are several ways to get lines. Either directly or from other objects.

Method	Effect
A Single Line	
sark.Line()	Get the current line
<pre>sark.Line(ea=my_address)</pre>	Get the line at the given address
<pre>sark.Line(name=some_name)</pre>	Get the line with the given name
Multiple Lines	
<pre>sark.lines()</pre>	Iterate all lines in the IDB
<pre>sark.lines(start=start_ea, end=end_ea)</pre>	Iterate all lines between start_ea and end_ea
sark.lines(selection=True)	Iterate all lines in current selection
sark.lines(reverse=True)	Iterate lines in reverse order

Objects that contain lines, such as functions and code blocks, can return their own set of lines. See sark. Function().lines for an example.

2.3.3 Functions

Functions are another basic object in Sark. Each one provides access to a single function in IDA.

```
>>> my_func = sark.Function() # The same arguments as `sark.Line`
>>> print (my_func)
Function (name="sub_417400", addr=0x00417400)
>>> my_func.name = "my_func"
>>> print (my_func)
Function(name="my_func", addr=0x00417400)
>>> for line in my_func.lines:
        print(line.disasm)
. . .
        ebp
push
mov
        ebp, esp
sub
        esp, ODCh
        ebx
push
push
        esi
.
•
```

Like the sark.Line objects, they encapsulate relevant API into a single object. Some useful members are:

All similarly named members between sark.Line and sark.Function work similarly as well to avoid confusion.

Getting Functions

There are 2 ways to get functions:

- 1. Using the sark.Function class, which accepts the same arguments as sark.Line;
- 2. Using sark.functions to iterate over functions. It is the same as sark.lines, but does not accept a reverse argument.

2.3.4 Xrefs

Cross references are a core concept in IDA. They provide us with links between different objects and addresses throughout an IDB.

```
>>> for xref in sark.Line().xrefs_from:
... print(xref)
<Xref(frm=0x0041745B, to=0x0041745D, iscode=1, user=0, type='Ordinary_Flow')>
<Xref(frm=0x0041745B, to='loc_4174A4', iscode=1, user=0, type='Code_Near_Jump')>
>>> for xref in sark.Line().xrefs_from:
... if xref.type.is_jump:
... print(xref)
<Xref(frm=0x0041745B, to='loc_4174A4', iscode=1, user=0, type='Code_Near_Jump')>
```

Sark xrefs are pretty compact objects:

Member	Usage
frm	xref source address
to	xref destination address
iscode	is code xref
user	is user defined xref
type	XrefType object

XrefType

To make querying the type of the xref as easy as possible, the XrefType object was created:

Member	Usage
name	a string representing the type, mainly for display
type	the numeric type constant, as per IDA SDK
is_call	is the xref a call
is_jump	is the xref a jump
is_*	predicates to check if a specific type applies. Includes all xref types.

Usage is quite simple and looks like plain English (of sorts):

```
>>> if xref.type.is_jump:
... print("xref is jump.")
```

Getting Xrefs

Xrefs can be retrieved from lines or functions. Both objects have xrefs_from and xrefs_to properties that allow retrieval of the relevant xrefs.

2.3.5 Instructions

As promised - we arrive to discuss the instruction objects. Instruction objects represent the actual assembly code of each line.

```
>>> line = sark.Line()
>>> insn = line.insn
>>> print(line)
[00417555] mov ecx, [eax+8]
>>> print(insn.mnem)
mov
>>> print(insn.operands)
[<Operand(n=0, text='ecx')>, <Operand(n=1, text='[eax+8]')>]
```

Out of their members,

Member	Usage
operands	list of operands
mnem	opcode mnemonic
has_reg	is a reg used in the instruction
regs	the registers used in the instruction

Instruction.operands is the most interesting one.

Operands

Each operand provides the means to analyze individual operands in the code.

```
>>> print(insn.operands[1])
<Operand(n=1, text='[eax+8]')>
>>> print("{0.reg} + {0.offset}".format(insn.operands[1]))
eax + 8
```

Member	Usage		
n	operand index in instruction		
type	numeric type a-la IDA SDK		
size	data size of the operand		
is_read	is the operand read from		
is_write	is the operand written to		
reg	the register used in the operand		
text	the operand text, as displayed in IDA		
base	<pre>the base register in an address-phrase of the form [base + index * scale + offset]</pre>		
index	the index register in a phrase		
scale	the scale in a phrase		
offset	the offset in a phrase		

Getting Instructions

The best way to retrieve instruction objects is using the .insn member of sark.Line.

2.3.6 Code Blocks

If you ever looked at a function in the Graph-View, you know what code blocks are. They are the nodes in the function graph, sometimes referred to as a flowchart.

```
>>> block = sark.CodeBlock()
>>> print(list(block.next))
[<CodeBlock(start_ea=0x00417567, end_ea=0x00417570)>,
      <CodeBlock(start_ea=0x0041759E, end_ea=0x004175D4)>]
```

Sark's CodeBlock object inherits from the idaapi.BasicBlock objects, and adds a few handy members.

Member	Usage
lines	the lines in the block, as a generator
next	successor nodes, as a generator
prev	predecessor nodes, as a generator
color	the background color of the node

These members allow for easy traversal and analysis of nodes in a graph.

FlowChart

Sark's flowchart, inheriting from idaapi.FlowChart, is in every way the same except for returning Sark CodeBlock objects instead of idaapi.BasicBlock ones. It can be used to quickly fetch all the blocks in a function graph.

Getting Codeblocks

Codeblocks are created using the sark.CodeBlock(ea) class. Flowcharts can be retrieved using the sark. FlowChart(ea) class accordingly.

In some cases, you may want to go over more than one function. In those cases, you can use the sark. codeblocks(start=None, end=None, full=True) function. The full parameter controls the way the blocks are generated. With full=True, FlowChart objects are generated per function, yielding fully capable CodeBlock objects. With full=False, a single FlowChart is generated for the entire address range. This results in faster iteration, but since the blocks are not associated to their containing functions, it is not possible to get or set block colors (line color will change, though.)

Advanced Usage

Since the function flowchart is actually a graph, it makes sense to use it as one. To ease you into it, the sark. get_nx_graph (ea) function was added.

```
>>> sark.get_nx_graph(idc.here())
<networkx.classes.digraph.DiGraph at 0x85d6570>
```

The function returns a NetworkX DiGraph object representing the flowchart, with each node being the start_ea of a matching block. Using NetworkX's functionality, it is easy to trace routes in the graph.

```
>>> import networkx as nx
>>> func = sark.Function()
>>> graph = sark.get_nx_graph(func.ea)
>>> start_address = sark.get_block_start(func.start_ea) # The `get_block_start(ea)`_
\dis short for `get_codeblock(ea).start_ea`
>>> end_address = sark.get_block_start(func.end_ea - 1) # Remember, `end_ea` is_
\dis outside the function!
>>> path = nx.shortest_path(graph, start_address, end_address)
>>> print("From {} to {}".format(hex(start_address), hex(end_address)))
From 0x417400L to 0x4176a6L
>>>print " -> ".join(map(hex, nx.shortest_path(graph, start, end)))
0x417400L -> 0x41745dL -> 0x417483L -> 0x417499L -> 0x4176a6L
```

2.3.7 Segments

Though not as popular as functions and lines, IDA segments include both. In Sark, Segment objects allow access to underlying Function and Line objects.

```
>>> #
>>> # Reference Lister
>>> #
>>> # List all functions and all references to them in the current section.
>>> #
>>> # Implemented with Sark
>>> #
>>> # See reference implementation here: https://code.google.com/p/idapython/wiki/
->ExampleScripts
>>> #
>>> for function in sark.Segment().functions:
>>> print("Function %s at 0x%x" % (function.name, function.ea))
```

(continues on next page)

(continued from previous page)

```
>>> for ref in function.crefs_to:
>>> print(" called from %s(0x%x)" % (sark.Function(ref).name, ref))
```

Like the sark.Line objects, they encapsulate relevant API into a single object. Some useful members are:

All similarly named members between sark. Line and sark. Segment work similarly as well to avoid confusion.

Getting Segments

There are 2 ways to get segments:

- 1. Using the sark. Segment object, using an address in a segment, a segment name, or the index of a segment.
- 2. Using sark.segments to iterate over segments.

2.3.8 Switch

The switch-case is a common construct in compiled code, and IDA is doing a great job at analyzing it.

```
>>> switch = sark.Switch(idc.here())
>>> for case, target in switch:
... print("{} -> 0x{:08X}".format(case, target))
0 -> 0x004224C9
1 -> 0x004224PF
2 -> 0x0042251B
3 -> 0x0042251B
4 -> 0x0042251B
6 -> 0x0042251B
6 -> 0x0042251B
7 -> 0x0042251B
8 -> 0x0042251B
8 -> 0x0042251B
10 -> 0x0042251B
11 -> 0x0042251B
11 -> 0x00422448
```

It provides the following members

Member	Usage
targets	switch target addresses
cases	switch case values
pairs	iterator of (case, target) pairs
get_cases	get the cases matching a target

The sark.Switch object is similar to a Python dict, mapping cases to targets. switch[case] returns the relevant target, and iteration returning the cases.

Getting Switches

To check if an address is a switch address, use sark.is_switch(ea). To get the switch, use sark. Switch(ea).

2.3.9 Enums

Enums in IDA are a great way to name numbers and bit-values for easier reading.

```
>>> for enum in sark.enums():
      print("{}:".format(enum.name))
. . .
        for member in enum.members:
. . .
           print(" {:<30} = {}".format(member.name, member.value))</pre>
. . .
        print()
. . .
POOL_TYPE:
   NonPagedPool
                                   = 0
   PagedPool
                                   = 1
   NonPagedPoolMustSucceed
                                   = 2
   DontUseThisType
                                   = 3
   NonPagedPoolCacheAligned
                                   = 4
   PagedPoolCacheAligned
                                   = 5
   NonPagedPoolCacheAlignedMustS = 6
   MaxPoolType
                                    = 7
CREATE FILE TYPE:
   CreateFileTypeNone
                                   = 0
                                   = 1
   CreateFileTypeNamedPipe
    CreateFileTypeMailslot
                                   = 2
```

The Sark Enum object provides the following members:

Member	Usage
name	the enum name
comments	enum comments, similar to line comments
eid	the enum-id of the enum
bitfield	is the enum a bitfield
members	the enum member constants

Using the Enum object you can easily enumerate and manipulate enums in IDA.

Enum Members

The .members member of sark.Enum returns a members object. The members object allows easy enumeration and manipulation of the members:

```
>>> my_enum = sark.add_enum("MyEnum")
>>> my_enum.members.add("first", 0)
>>> my_enum.members.add("second", 1)
>>> my_enum.members.add("third", 2)
>>> my_enum.members.remove("second")
>>> for member in my_enum.members:
... print("{} = {}".format(member.name, member.value))
first = 0
third = 2
```

Each member provides the following:

Member	Usage
name	the member name
value	the member value
comments	the member comments
enum	the containing enum

Getting Enums

There are several ways to get an enum. All are summed in the following table:

Code	Explanation
sark.enums()	iterate all the enums in the IDB
<pre>sark.Enum("EnumName")</pre>	get an existing enum by name
<pre>sark.Enum(eid=enum_id)</pre>	get an enum using a known id
<pre>sark.add_enum("NewEnumName")</pre>	create a new enum

2.3.10 IDB Graphs

Earlier we discussed codeblock graphs inside functions. Another interesting graph is the call graph connecting all the functions.

As we have already played with graphs earlier, we will not delve into the details.

Getting IDB Graphs

To get an IDB graph, use sark.graph.get_idb_graph(). The function traverses all xrefs from and to all functions to create a graph of the IDB, with each node being the address of a function's start_ea.

2.3.11 UI

Sark provides some basic utilities and wrappers for IDA's UI.

NXGraph

A natural extension to creating and analyzing graphs, is plotting them. IDA provides a generic API via the idaapi. GraphViewer interface. As Sark mainly uses NetworkX digraphs, the sark.ui.NXGraph class has been created to provide an easy plotting solution.

The NXGraph constructor takes several arguments:

Argument	Desctription
graph	the graph to plot
title	(opt.) title for the graph
handler	(opt.) a default handler for nodes
padding	(opt.) visual padding of nodes

After an NXGraph is created, use . Show() to display it.

Node Handlers

To allow different types of node data, NXGraph uses node handlers. Node handlers inherit from sark.ui. BasicNodeHandler and implement the callbacks required for them (all are optional).

Callback	Usage
on_get_text	returns the text to display for the node
on_click	handles a click on the node. Return True to set the cursor on it.
on_double_click	same as on_click
on_hint	the hint to show
on_bg_color	returns the background color for the node
on_frame_color	returns the frame (border) color for the node

There are 2 existing handlers you can use.

Handler	Info
BasicNodeHa	aThe most basic handler. Calls str to get node text, and nothing else. This is the default handler
	for NXGraph.
AddressNode	Harssiumes all nodes are IDB addresses. For node text, it shows the address' name if it exists, or a
	hex address otherwise. On double click, it jumps to the clicked address.

Menu Manager

Sark provides a menu-manager class to allow the addition of top-level menus to IDA's GUI. This is done by abusing QT to find the top level menu, but you don't need to worry about that.

2										
<u>F</u> ile	<u>E</u> dit	<u>J</u> ump	Searc <u>h</u>	<u>V</u> iew	Deb <u>ugg</u> er	<u>O</u> ptions	<u>W</u> indows	Help	My Menu	
									My A	ction

>>>	# Use the manager to add top-level menus
>>>	<pre>menu_manager = sark.ui.MenuManager()</pre>
>>>	<pre>menu_manager.add_menu("My Menu")</pre>
>>>	# Use the standard API to add menu items
>>>	# Assume the action's text is "My Action"
>>>	<pre>idaapi.attach_action_to_menu("My Menu/", "SomeActionName", idaapi.SETMENU_APP)</pre>
>>>	# When a menu is not needed, remove it
>>>	<pre>menu_manager.remove_menu("My Menu")</pre>
>>>	# When you are done with the manager (and want to remove all menus you added.)
>>>	# clear it before deleting.
>>>	menu_manager.clear()

As you can see in the above code, the *MenuManager* class only handles the addition of a top-level menu. After that, IDA's own APIs can be used freely with the created menu to add or remove menu items

2.3.12 Miscellaneous

Sark also has a lot of functionality outside of the core objects.

Function	Description
sark.	returns a start, end pair, where None is replaced with the start-
<pre>fix_addresses(start=None,</pre>	address and end-address of the IDB accordingly
end=None)	
sark.	checks if the addresses are in the same function
is_same_function(eal,	
ea2)	
sark.	returns the name of the address if it exists. Otherwise a hex representation
<pre>get_name_or_address(ea)</pre>	is returned


2.4 Examples

2.4.1 Capture Huge Screenshots

Usage

Click on the image for full scale screenshot.

Warning: really big image file.



Code


```
import sark.qt
widget = sark.qt.get_widget("IDA View-A")
sark.qt.resize(widget, 7000, 18000)
# Move the view about a bit to capture the entire function
sark.qt.capture_widget(widget, "huge-screenshot.png")
# Crop the image to remove extra background.
```

2.4.2 Plotting a Call Graph

Usage

Using Windows 8.1 http.sys. Before MS15-034.

```
draw_call_graph(sark.Function(name="_UlpParseRange@32").ea, to=True, distance=4)
```



Code

```
import sark
import networkx as nx
def draw_call_graph(ea, distance=2, to=False):
    # First, get the IDB graph (caching it might be a good idea
    # as this operation can be time consuming on large IDBs)
   idb_graph = sark.graph.get_idb_graph()
    # Get the address of the function to use in the graph
   func_ea = sark.Function(ea).ea
    # Create the call graph
   if to:
        # If we want the calls to our function, we need to reverse
        # the graph
       idb_graph = idb_graph.reverse()
    # Use NetworkX to limit the IDB graph
   call_graph = nx.ego_graph(idb_graph, func_ea, distance)
    # Paint the root node red
   call_graph.node[func_ea][sark.ui.NXGraph.BG_COLOR] = 0x80
    if to:
        # If we reversed it before, we need to reverse it again
```

(continues on next page)

(continued from previous page)

```
# to make the links point the right way
call_graph = call_graph.reverse()
# Create an NXGraph viewer
viewer = sark.ui.NXGraph(call_graph, handler=sark.ui.AddressNodeHandler())
# Show the graph
viewer.Show()
```

2.5 Plugins

2.5.1 Installing Plugins

The IDA Way

IDA provides a single way to install plugins - stick them in the plugins subdirectory and you're good to go.

While this is great for compiled plugins, as your build scripts can place the newly compiled plugin there for you, it is not as comfortable when using scripted plugins. Forgetting to copy the latest version, or updating the code in the plugins directory instead of your repository can both lead to annoying problems and waste precious time.

Moreover, access to the plugins directory requires root access.

The Sark Way

To combat the limitations of IDAs plugin loading mechanism, Sark provides the plugin_loader.py plugin. Once installed (in the classic IDA way) it allows you to define plugin-lists - a system-wide list and a user-specific list - to be loaded automatically.

The lists are simple, consisting of full-paths and line-comments:

```
C:\Plugins\my_plugin.py
# This is a comment. Comments are whole lines.
C:\OtherPlugins\another_plugin.py
```

Both lists are named plugins.list and are automatically created by IDA as empty lists at the following locations:

- System-Wide Under IDA's cfg subdirectory. The path can be found using idaapi.idadir(idaapi. CFG_SUBDIR). This list requires root access to modify as it is in IDA's installation directory.
- User-Specific Under IDA's user-directory. \$HOME/.idapro on Linux, %appdata/%HexRays/IDA Pro on
 Windows. The path can be found using idaapi.get_user_idadir(). Each user can set his own plugins
 to load, thus eliminating the need for root access.

To install your plugins, just add them to one of the lists. This allows you to easily update plugins as you go without ever needing to copy them.

2.5.2 Show Meaningful

When reversing an executable, we often need to deal with a large amount of unknown code. To combat this, we usually look for strings and library functions, and use them as guides as we interpret the code. When those are ample,

we hardly need to look at the assembly code to infer meaning. On the other hand, the need to constantly jump into functions, pan them around to see all the strings, then jump back out is quite time consuming and confusing.

Well, no more!

The "Meaningful" plugin allows you to get all the information you need with a simple hotkey.


Usage

Whenever inside a function, just press Alt + 0 to get a table of all the meaningful objects in it:

Meaning Type		; in 'py_data_	format to py dict' : 0x100DE0A0	~
		Adduoge		
Type	Usage	Address	Object	
	0	0		
code	0x100DE0B2	0x1068E7F0	impPyGILState_GetThisThreadState	
str	0x100DE0C7	0x10459654	'idaapi.cpp'	
str	0x100DE0CC	0x10459660	"*** WARNING: Code at %s:%d should have the GIL, but apparently doesn't ***\n"	
code	0x100DE0D1	0x10002045	intcdecl msq(char const *,)	
str	0x100DE13F	0x104576C4	'hotkey'	
str	0x100DE148	0x104576B8	'menu name'	
str	0x100DE151	0x1045769C	'name'	
str	0x100DE15D	0x104576EC	'value size'	
str	0x100DE169	0x10457724	'text width'	
str	0x100DE174	0x10457740	'cbsize'	
str	0x100DE180	0x10457694	'props'	
str	0x100DE185	0x104596AC	'{s:i,s:i,s:i,s:k,s:s,s:s,s:s}'	
code	0x100DE18A	0x1068E854	imp Py BuildValue	
				~
Python				

Since the output is at the Output window, a double click on an address will take you to it.

To make things even more agile, you can press Ctrl + Alt + 0 whenever on a line referencing a function to get the values displayed for that function:



				î
Meaning Type	ful References Usage	in 'SWIG_Init Address	ializeModule' : 0x102DB700 Object	
code code code code code code	0x102DB741 0x102DB757 0x102DB812 0x102DB812 0x102DB89A 0x102DB8D7	0x102DB960 0x102DB9B0 0x1001EF70 0x1001EF70 0x1001EF70 0x10026E90	SWIG_Python_GetModule SWIG_Python_SetModule SWIG_MangledTypeQueryModule SWIG_MangledTypeQueryModule SWIG_TypeCheck	
				~
Python				

2.5.3 Quick Copy

The quick copy allows you to easily copy data from the IDB.

Usage

Copying Addresses


To copy the address of the current line, just press Ctrl + Alt + C. It will get copied as a hex number, prefixed with 0x.

To copy the file offset of the current line, simply press Ctrl + Alt + O. It will get copied as a hex number (like line address copying), prefixed with 0x.

Copying Bytes

Pressing Ctrl + Shift + C copies the bytes of the current line or selection.

Copying the current line:



Will result in 8b 4d 08, while copying a selection:

	<pre>.text:100DE0FC .text:100DE0FC</pre>		; ·				^
1	.text:100DE0FC		100	c_100DE0FC:		; CODE XREF: py_data	a
₩ •	.text:100DE0FC	8B 4D	08		mov	ecx, [ebp+arg_0]	
•	.text:100DE0FF				mov	edx, [ecx+14h]	
•	.text:100DE102 .text:100DE105				MOV	[ebp+var_4], edx	
	000DD4FC 100DE0F	C: py_d	ata_format_	_to_py_dict:loc	100DE0FC	(Synchronized with Hex View-1)	٦,
	<					>	

Will result in 8b 4d 08 8b 51 14.

2.5.4 Autostruct

Creating and applying structs in IDA can be quite a hassle.

Go to the structure window, create a structure, define members at specific offsets, go to the disassembly to apply them, go back to the structure view to correct errors, apply other members... And on and on it goes.

The Autostruct plugin does all this work for you, without ever having to leave the IDA view. It automatically creates structs, defines member offsets, and applies them in the disassembly view.

Usage

1. Select a line (or lines) containing struct references

	5: mov cmp jnz mov jmp	; CODE XREF: py_data eax, [ebp+arg_0] dword ptr [eax+10h], 0 short loc_100DE117 [ebp+var_8], offset unk_10456CFB short loc_100DE120	a_f ^
00	DD508 100DE10	08: py_data_format_(Synchronized with Hex	Vi(v
↓ <u>↓</u> <			>


- 2. Press Shift + T
- 3. Set the struct name

Struct Name	MyStruct							
		ОК	Cancel					


4. Choose the register holding the struct base for the selected code. Autostruct will automatically suggest the most likely candidate in the selection.

Register	eax			1
		OK	Cancel	

At this point, Autostruct will try and create a new struct, populate it with relevant offsets, and apply it to the selection.



5. If a structure of the given name already exists, you will need to select whether to modify the existing structure, apply without modification, or cancel.



6. Struct creation and modification happen seamlessly

0000000	^
00000000 MyStruct	<pre>struc ; (sizeof=0x1C, mappedto_1609)</pre>
0000000	db ? ; undefined
0000001	db ? ; undefined
00000002	db ? ; undefined
00000003	db ? ; undefined
00000004	db ? ; undefined
00000005	db ? ; undefined
00000006	db ? ; undefined
0000007	db ? ; undefined
00000008 offset_8	dd ? ; XREF: py_data_format_
000000C	db ? ; undefined
000000D	db ? ; undefined
000000E	db ? ; undefined
000000F	db ? ; undefined
00000010 offset_10	dd ? ; XREF: py_data_format_
00000014	db ? ; undefined
00000015	db ? ; undefined
00000016	db ? ; undefined
00000017	db ? ; undefined
00000018 offset_18	dd ? ; XREF: py_data_format_
	ends
0000001C	
324. MyStruct:000F	✓
<	>

Known Issues

Misaligned Member Creation When attempting to create a member at an offset belonging to another member, Autostruct will fail. This usually happens when a previous definition was incorrect (wrong member size) or when


members are unions. At this point, manual handling (redefining the large member as a smaller one) is required.

2.5.5 Xrefs Graph

The Xrefs-Graph is used to easily generate interactive xref graphs.

Usage

Anywhere within the IDA-View, just right-click¹, and select the desired option:




In the popup dialog, enter the distance (recursion level) desired from the source:

n Please enter a number		×	
Distance From Source		\square	
Input	Cancel		~

Once you press OK, the plugin will generate an interactive xrefs graph:

 $^{^{1}}$ In IDA 6.6 or earlier, use <code>View/Graph/Xrefs</code> from source or <code>View/Graph/Xrefs</code> to source, as context menus cannot be augmented.



A double-click on any block will take you to the relevant address. Also, names in the blocks will be updated as you rename functions.

Known Issues

Node Groups While creation of node groups *is* possible via IDA's GUI, it is not presently supported in the plugin. Creation of node groups may cause unpredictable errors.

2.6 Debugging IDAPython Scripts

While IDAPython is extremely useful, it can be a bit of a hassle to debug IDA Pro plugins. This tutorial will give get you started on debugging IDAPython scripts and plugins using Python Tools for Visual Studio.

And yes, it is completely free.

2.6.1 The Setup

For this tutorial, we will be using the following software:

- 1. IDA Pro 6.8
- 2. Visual Studio Community
- 3. Python Tools for Visual Studio, documentation can be found here.
- 4. Python's ptvsd module. Install using pip install ptvsd.
- 5. The following plugin:

```
# filename: ptvsd_enable.py
import idaapi
import ptvsd
try:
    # Enable the debugger. Raises exception if called more than once.
   ptvsd.enable_attach(secret="IDA")
except:
   pass
class DebugPlugin(idaapi.plugin_t):
    flags = idaapi.PLUGIN_FIX
    comment = "PTVSD Debug Enable"
   help = "Enable debugging using PTVSD"
   wanted_name = "PTVSD"
   wanted_hotkey = ""
    def init(self):
        return idaapi.PLUGIN_KEEP
    def term(self):
        pass
    def run(self, arg):
        pass
def PLUGIN_ENTRY():
    return DebugPlugin()
```

For the purposes of this tutorial, you can try and debug this plugin:

```
# filename: sample_debuggee.py
import idaapi

def my_debugged_function():
    # Set breakpoint here!
    pass

class SamplePlugin(idaapi.plugin_t):
    flags = idaapi.PLUGIN_PROC
    comment = "Sample Debuggee"
    help = "Sample Debuggee"
    wanted_name = "Sample Debuggee"
    wanted_hotkey = "Shift+D"

    def init(self):
        return idaapi.PLUGIN_KEEP

    def term(self):
        pass
```

(continues on next page)

(continued from previous page)

```
def run(self, arg):
    my_debugged_function()
def PLUGIN_ENTRY():
    return SamplePlugin()
```

2.6.2 Debugging

- 1. Put ptvsd_enable.py (provided above) in IDA's plugins directory. If you want to use the sample debuggee, put it in the plugins directory as well.
- 2. Start IDA and load an IDB (otherwise weird issues arise)
- 3. Load the code you want to debug into Visual Studio and set breakpoints.
- 4. In Visual Studio (with the plugin file open), use DEBUG->Attach to process

ludio (Administrator)) DEBUG TEAM TOOLS VMWARE TEST ANALYZE WINDOW Windows art Ŧ Graphics Start Debugging F5 ņ blo Start Without Debugging Ctrl+F5 ⊳ 讍 Execute Project in Python Interactive Shift+Alt+F5 e[©] Attach to Process... Other Debug Targets

5. In the dialog, select <code>idaq.exe</code> and <code>click</code> <code>Attach</code>

		Atta	ch to Process			?
Transport:	Default					
Qualifier:					✓ Find	
Transport Informati The default transpo Monitor (MSVSMO	ort lets you selee	t processes on this computer or a r	emote computer running the Micro	soft Visual Studio Re	emote Debugging	
Attach to: Available Processes	Automa	tic: Python code			Select.	
Process	ID	Title	Туре	User Name	Session	^
idaq.exe	6080	IDA v6.8.150428	Python Engin		1	
į.						*
Show processes	from all users				Refresh	

6. We are now attached. Once a breakpoint is hit, Visual Studio will break and let you debug.

7. Have fun debugging!

2.6.3 Important Notes

- 1. When debugging (breaking and stepping), IDA will be frozen.
- 2. Load your IDB prior to attaching the debugger.
- 3. For easy debug-on-demand, keep ptvsd_enable.py in IDA's plugins directory at all times.
- 4. To set breakpoints, make sure you load into VS the files that are actually loaded by IDA.

If you find any issues with the tutorial, please submit them here.

2.7 Support

2.7.1 IDA 7.4 & Python 3

Those versions are under active support and expected to receive updates.

IDA 7.4 made 2 significant changes that affect support

- 1. Python 3 support
- 2. Python 2: 6.95 compatibility APIs OFF by default
- IDA 7.4 release notes

This means that all code breaks by default - be it Python 2 or 3. While adapting Sark to the new APIs & Python 3 I concluded that actively maintaining & developing multiple (IDA 7.4 and lower, Python 2 & 3) versions incurs an

overhead that is too high for me. As a result - Sark will only support Python 3 on IDA 7.4. Older versions of IDA will get bugfixes. IDA 7.4 with Python 2 will receive no support.

If you need Python 2 support on IDA 7.4, please contact me or create an issue on this repo. I am not opposed to adding bugfix-based support.

2.7.2 Older Versions

Older versions of IDA (7.3 and lower) using Python 2 are still supported for bugfixes.

The older version is maintained on the IDA-6.x branch.

Installation of the older version follows the same flow as before:

pip2 install -U git+https://github.com/tmr232/Sark.git@IDA-6.x#egg=Sark

To develop locally, clone the repo & check-out the IDA-6.x branch.

2.8 How To Contribute

The Sark project was created to provide an intuitive, easy to use scripting layer for IDA Pro. If something seems like the right-way to do something, it should probably be added to Sark.

If you have something you think is worth adding, either submit a new issue or (preferably) create a pull-request.

When contributing, try and follow these guidelines:

- Add yourself to the AUTHORS.rst file in alphabetical order. Every contribution shall be credited.
- Each new feature must have a reproducible test-case or usage. If it can't be used, it will not get in.
- Obey PEP 8 and PEP 257.
- All code should be documented. Usage samples and references to the IDASDK headers are a bonus.
- Write meaningful commit messages.
- No change is too small. You are welcome to fix typos, convention violations, or plain ugly code. All contributions are welcome.
- When submitting a fix to a bug, describe the bug being fixed. Include both the bug and the desired results. Creating an issue for the bug is good practice.
- When reporting bugs, make sure you mention your OS and IDA version.
- Sark has tests (though the coverage is bad...). When adding features, it is advisable to add matching tests.

If you can't adhere to the guidelines, **submit your pull requests anyway**. Maybe someone else can improve on it. Thanks for contributing!

2.9 Credits

Sark is written and maintained by Tamir Bahar.

2.9.1 Contributors

The following people have contributed directly or indirectly to this project:

- darx0r
- iamtimmy
- ynvb
- OfficialMan

Please add yourself here alphabetically when you submit your first pull request.