VisiOmatic

Release 2.0

E.Bertin, C.Marmo, H.Bouy

November 23, 2016

Contents

1	Introduction	1		
2	Technical overview 2.1 Client Side: VisiOmatic 2.2 Server-side: iipsrv	3 3 3		
3	How to use VisiOmatic3.1The main window3.2The Coordinates Pane3.3The Navigation Pane3.4Advanced Settings	5 5 6 6		
4	VisiOmatic set-up and customization			
5	VisiOmatic programming interface 5.1 Classes 5.2 Utility functions	13 14 27		
6	Server installation and configuration 6.1 Pre-requisites 6.2 Downloading iipsrv 6.3 Installing iipsrv 6.4 Web server configuration 6.5 iipsrv configuration and testing 6.6 System configuration	 31 31 32 32 32 35 39 		
7	Acknowledgements	41		
Bi	bliography	43		

Introduction

The purpose of this manual is to help administrators and data scientists setting up and operating **VisiOmatic** and **IIPImage-astro** together.

This manual is divided in four main sections. The first section gives a technical overview of **IIPImage** and **VisiOmatic**, and their capabilities. The second section will guide administrators through installation and configuration of **IIPImage-astro**. The third section explains how to set up and customize the **VisiOmatic** web interface through concrete examples. Finally, the last section provides a full description of the web client API.

Technical overview

VisiOmatic and **IIPImage-astro** form a complete remote visualization system for large multiband astronomical image data. The **VisiOmatic** client interface runs in standard web browsers, generating image requests to a server on behalf of the user. These HTTP requests are processed in real-time by the **IIPImage-astro** server to compute and deliver JPEG-compressed images which are then updated almost immediately in the interface.

2.1 Client Side: VisiOmatic

The **VisiOmatic** web client interface [1] is built on top of the **Leaflet** Javascript mini-framework (e.g., MapBox, OpenStreetMap, ...). The **VisiOmatic** interface is fully asynchronous, and is particularly immune to connection glitches. It is embeddable in regular Web pages, blog posts, portals, or wiki entries. It is compatible with touchscreen interfaces such as those offered by iOS and Android mobile devices. The position and appearance of widgets is fully customizable through module options and Cascading Style Sheets. The graphic engine relies purely on Javascript and HTML5 and not on proprietary technology such as Adobe Flash or Microsoft Silverlight. It is fully compatible with the current breed of popular web browsers, including Mozilla Firefox (v4.0 and above), Google Chrome (v10.0 and above), Apple Safari (v5.1 and above), Microsoft Edge (v20.10240 an above) and Opera (v10.5 and above).

2.2 Server-side: iipsrv

The **IIPImage-astro** server software consists of a modified version of the open-source **IIPImage** package [6][1], an FCGI (Fast Common Gateway Interface) application written in C++. **IIPImage** operates as a webservice that encodes and streams in real-time large high resolution images which are delivered in the form of compressed "tiles". It is designed to be fast and bandwidth-efficient with low processor and memory requirements. It is licensed under version 3 of the GNU General Public License.

Compared to other existing solutions, **IIPImage** has the enormous advantage of providing on-the-fly JPEG compression as well as access to uncompressed pixel data. This means that it can operate directly on science-grade multispectral data stored in floating-point format, and perform operations such as rescaling or filtering before sending out the resulting image to the client. Also, contrary to other solutions dealing with multispectral data, most of the image processing and compositing is done server-side. This dramatically decreases the quantity of information that has to be sent to the browser, and the amount of computing which must be performed client-side, making the exploration of large datacubes from a smartphone a comfortable experience, even through a 3G connection.

2.2.1 Data management

All the data for a given image data cube are stored in a single, huge BigTIFF file. The initial conversion from the FITS astronomical image format to BigTIFF is handled by the **STIFF** software [7]. On modern hardware, the current **STIFF** conversion rate for transcoding a FITS file to an **IIPImage**-ready tiled pyramidal BigTIFF

ranges from about 5Mpixel/s to 25Mpixel/s (20-100MB/s) depending on the chosen TIFF compression scheme and system I/O performance. Hence in principle FITS frames with dimensions of up to 16k×16k can be converted in a matter of seconds, and just-in-time conversion could be a viable option for such images.

Vector data are stored in GeoJSON format. GeoJSON offers a compact, yet human-friendly representation of features such as markers, lines, polygons, and can easily be generated from e.g., CSV or ds9 region files.

2.2.2 Security

Data security is a major issue for online services. In **IIPImage**, three mechanisms allow the webmaster to control the dissemination of data:

- Paths where the data files are located are not accessible from the web; they are only accessible by the FCGI application on the server, and absolute or relative access through upper levels of the directory tree is forbidden.
- The same origin security policy in web browsers restricts data access to servers located in the same domain as the server hosting the client code, and prevents Javascript applications on websites from other domains sending AJAX requests directly to the **IIPImage** server. If however data sharing with other domains is a desired feature, **IIPImage** implements the CORS mechanism to allow such requests from selected or all external websites.
- As other tile-based image servers, **IIPImage** itself would not prevent a user to download a complete high resolution JPEG image through small pieces, using a dedicated script. If this is an issue, **IIPImage** offers a configurable on-the-fly, randomized digital watermarking feature.

2.2.3 Performance

IIPImage is known for being particularly efficient. Since 2013 a significant amount of work has gone into optimizing further the C++ server code, by streamlining the processing of vectorized floating-point data and improving I/O performance with Terabyte-sized datasets [1]. Current server code is able to serve from about 50 to 500 256×256 JPEG tiles per second per CPU core (2.5GHz). The output image stream from a single 16-core server under heavy load (tens of thousands of tile requests per second) is thus capable of saturating a 1 Gbit/s connection.

Provided that the client interface restricts the number of operations possible with the data, caching image tiles is an efficient way of increasing the throughput of the system. In addition to the caching of image tiles done client-side in the browser, **IIPImage** offers two explicit levels of tile caches server-side:

- In memory, integrated within the application
- Distributed, thanks to the MemCached caching system.

How to use VisiOmatic

3.1 The main window

The Figure below shows the main window of the VisiOmatic web interface in its default configuration.

The main window contains a "slippy map" carrying the current image layer and optional vector overlays, plus a series of widgets. One navigates through the image and its overlays by "dragging" the map to the desired position. On computers this is done by clicking and holding the left button while moving the mouse, or by using the keyboard arrow keys. On touch devices one must press and move a finger throughout the screen.

At the top left, two magnifier buttons can be used to zoom in () or out (). One can also zoom using the mouse wheel or the -/+ keys on computers, or with a pinch gesture on touch devices. The user can switch to/from full screen mode by clicking the button (third from the top). The \blacksquare button (last from the top) opens the Advanced Settings Menu.

The coordinates of the *center* of the current field-of-view (indicated by the cross-shaped reticle) are displayed at the top-right of the main window, in the *Coordinate Pane*. In some configurations, a drop-down list allows one to switch between equatorial (RA,Dec) and other types of coordinates.

Below the coordinates, a *Navigation Pane* may be offered, offering a larger view of the current image, as well as the current field of view, represented by a shaded orange box.

The scale, as measured at the center of the main window, is displayed in the lower left corner.

3.2 The Coordinates Pane

The Coordinates Pane allows the user to:

- 1. check the central coordinates of the current field of view
- 2. pan to specific coordinates or to a given object.

To move to specific coordinates or objects, simply click in the coordinates pane, and enter the desired coordinates or object name. VisiOmatic uses Simbad to parse the input coordinates and object names. According to the Simbad Query-by-Coordinates webpage, the following coordinates writings are allowed:

- 20 54 05.689 +37 01 17.38
- 10:12:45.3-45:17:50
- 15h17m-11d10m
- 15h17+89d15
- 275d11m15.6954s+17d59m59.876s
- 12.34567h-17.87654d
- 350.123456d-17.33333d

• 350.123456 -17.33333

while the dictionary of nomenclature for object identifiers can be found here.

3.3 The Navigation Pane

The Navigation Pane allows the user to quickly move over the image. Just drag the shaded orange rectangle representing the current field of view to the desired location. The Navigation Pane can be minimized by clicking on the pair of arrows that appear on the top right when hovering the area.

3.4 Advanced Settings

The Advanced Settings button gives access to a taskbar with five tabs, from top to bottom and as illustrated in figmix:

- If Channel Mixing, which allows the user to choose which image channels to use for display or color compositing
- U Image Preferences, which gives the user control over the contrast, color saturation, gamma correction and JPEG compression level. There is also a switch for inverting the color map.
- Catalog Overlays for superimposing multiple catalogs in vector form, e.g., the 2MASS Point Source Catalog [2] or the SDSS Photometric Catalog [3].
- Region Overlays, for overlaying Points Of Interest (such as local catalogs) or any local vector data sets in GeoJSON format.
- Profile Overlays, for plotting image profiles and (pseudo-)spectral energy distributions from the full precision pixel values stored on the server.
- (i) Documentation, which opens a panel where any web page can be embedded, e.g., an online-manual.

3.4.1 Channel Mixing

The Channel Mixing panel has two modes, which can be selected using the radio buttons located at the top of the dialog: the Single Channel (monochromatic) mode, and the Multi-Channel (color composite) mixing mode.

In Single Channel mode, one can:

- Select an image channel for display
- · Select a color map among a selection of four
- Set the minimum and maximum channel levels

In Multi-Channel mode, one can:

- Select an image channel to be included in the color mix
- Set the color this channel contributes to the mix
- Set the minimum and maximum channel levels
- Click on a channel name in the active channel list to edit a channel contributing to the current mix, or click on the trashcan button to remove it.

3.4.2 Image Preferences 🛈

The Image Preference dialog gives access to global image display settings:

- Color map inversion (negative mode)
- Contrast (scaling factor)
- Color saturation (0 for black&white, >1 for exaggerating colors)
- Gamma correction (2.2 for linear output on a properly calibrated monitor, higher values for brightening dark regions, lower values for darkening)
- JPEG quality percentage. The lower the quality percentage, the more compressed the image and the more artifacts in the rendering.

Note: Users with a low bandwidth can improve the reactivity of the display by setting a lower JPEG quality percentage.

3.4.3 Catalog Overlays

The Catalog Overlay dialog allows the user to download and overlay catalogs in the current field of view. The available list of catalogs and the rendering of catalog sources (marker, cross, circle with magnitude-dependent radius, ellipse, etc.) depends on client settings. In the current default interface all catalogs are queried from the *VizieR* service at *CDS* [5].

To query a catalog, move the map and adjust the zoom level to the desired field of view; choose the catalog from the drop-down catalog selector and an overlay color from the color selector, then click the "GO" button. After a few seconds a new overlay with the chosen color should appear, as well as a new entry in the active catalog list below the drop down selector. Each overlay may be turned off or on by clicking on the check-mark in the corresponding entry of the active catalog list, or simply discarded by clicking on the trashcan button.

Depending on the implementation in the client, sources may be clickable and have pop-up information windows attached.

3.4.4 Region Overlays 🖗

The Region Overlay dialog allows the user to overlay Points/Regions Of Interest, such as local catalogs, detector footprints, etc. These POIs/ROIs may be clickable and have information attached for display in pop-up windows.

The Region Overlay selection mechanism is exactly the same as that of Catalog Overlays.

3.4.5 Profile Overlays

The Profile overlay dialog gives the user the possibility to extract pixel values directly from the scientific data. These data are unaffected by channel mixing, image scaling or compression.

The profile option extracts series of pixel values along lines of constant galactic longitude or latitude. The line color is pink by default and can be changed using the color picker. The line itself is positioned on the image by first dragging the map to the desired start coordinate, pressing the "START" button, and dragging the map to the desired end coordinate and pressing the "END" button. After some calculation, a window appears with a plot of the image profile along the selected line. In mono-channel mode, a single line is plotted that corresponds to the currently selected channel. In color mode, all active channels are plotted, with their channel mixing color. On devices equipped with a mouse one can zoom inside the plots by clicking with the left button and selecting the zoom region. Double-click to zoom out. The plot window can be closed by clicking/touching the small cross in the upper right corner, and reopened at any time by clicking on the line.

The spectrum option, as its name implied extracts pixel data along the channel axis at a given position. The position is selected by dragging the map to the desired coordinate and clicking on the "Go" button. A circle marker appears with the color that was selected using the color picker (purple by default). After some calculation, a window pops out with the "spectrum" of pixel values at the selected coordinate. Note that the ordering of pixel values follows that of the channels in the data cube.

3.4.6 Documentation panel (i)

Clicking on the (i) symbol (which may be located at the bottom of the taskbar) brings up the online documentation panel. A navigation bar is located at the bottom of the panel to facilitate browsing through the provided documentation or website sections and come back to the main page. Finally, a download button (PDF Symbol

(L) located at the bottom right of the Manual Pane may be present to allow the user saving an entire manual as a PDF file for offline reading.

VisiOmatic set-up and customization

Let us now describe the HTML and JavaScript code that make up a typical **VisiOmatic**-based web client. We will assume that the **IIPImage-astro** FCGI is already up and ready to serve pixel data on the server (see *Server installation and configuration*).

The **VisiOmatic** web client [1] works essentially as a large **Leaflet** plug-in, providing subproperties to the original **Leaflet** "classes" with new or overloaded methods. The whole client fits in a single HTML file. The relevant part of the HTML file begins with the inclusion of the **Leaflet**, jqPlot, Spectrum and VisiOmatic Cascading Style Sheets in the HTML header:

```
<!DOCTYPE html>
<html lang="en">
<html lang="en"</html lang
```

The Leaflet map itself may be styled (background color, dimensions):

```
<style type='text/css'>
body {padding: 0; margin: 0; }
html,body,#map { width: 100%; height: 100%; }
</style>
```

The following Javascript library files must be included: jQuery (V2.1.4+), jqPlot (V1.0.8+), Spectrum (V1.7.1+), Leaflet (V1.0) and VisiOmatic (V2.0+). Custom Catalog objects may be included too.

```
<script src='visiomatic/dist/jquery-min.js'></script>
<script src='visiomatic/dist/jqplot-min.js'></script>
<script src='visiomatic/dist/spectrum-min.js'></script>
<script src='Leaflet/dist/leaflet.js'></script>
<script src='visiomatic/dist/visiomatic.js'></script>
<script src='catalogs.custom.js'></script>
</head>
```

The whole **Leaflet/VisiOmatic** interface, including advanced menus, fits in a <div> HTML element. The element can be styled to occupy the whole HTML body (as in this dedicated viewer example), or a smaller section of an existing web page. There can be several independent viewing areas ("maps") per web page; each of them must have a different id attribute. The map below is given a black background.

```
<body></body></body> id='map' style='background:black'></div>
```

Next comes the JavaScript code. The first thing it does is to capture the URL of the web page. The L.IIPUtils.parseURL() utility function (see *description in next chapter*) parses it to generate a dictionary of query string keyword/value pairs that we will use to modify specific viewer settings:

```
<script>
var args = L.IIPUtils.parseURL(window.location.search.substring(1));
```

For instance, if the current webpage URL is http://myviewer.org?foo=ok&bar=1, args['foo'] will contain 'ok' and args['bar'] will contain '1'.

The L.map() command initializes the map inside the HTML element that carries the given id ('map' in this example):

var map = L.map('map', {fullscreenControl: true, zoom: 5});

Note the fullscreenControl option (false by default) that adds a Full-Screen switch to the regular **Leaflet** interface.

The heart of the viewer code is the instantiation and initialization of the image layer with L.tileLayer.iip() (see *next chapter*). L.tileLayer.iip() accepts a query string comprised of the FastCGI URL and the name of the data file, plus a set of options:

```
var iip = '/fcgi-bin/iipsrv.fcgi?FIF=cfhtls_d1.ptif',
    layer = L.tileLayer.iip(iip, {
  center: args['center'] ? args['center'] : false,
  fov: args['fov'] ? parseFloat(args['fov']) : false,
  mixingMode: args['mode'] ? args['mode'] : 'color',
  defaultChannel: args['channel'] ?
    parseInt(args['channel'], 10) : 2,
  contrast: 0.7,
  gamma: 2.8,
  colorSat: 2.0,
  channelColors: [[0,0,1],[0,1,1],[0,1,0],[1,1,0],[1,0,0]],
  channelLabels: [
    'u band',
    'q band',
    'r band',
    'i band',
    'z band'
 ],
}).addTo(map);
```

The example above illustrates some options including

- using query arguments in the URL of the present web page to set the initial center coordinates, zoom level, mixing mode and monochromatic channel index for the viewer,
- changing the default image contrast, gamma factor and color saturation,
- applying colors to the different channels (channelColors),
- labeling every image channel (channelLabels).

The rest of the code instantiates controls that will help the user interact with the data. First of all, a map scale in angular units (pixel units are turned off), a central reticle, and the coordinate input/output widget are set up:

```
L.control.scale.wcs({pixels: false}).addTo(map);
L.control.reticle().addTo(map);
var wcsControl = L.control.wcs({
    coordinates: [{label: 'RA,Dec', units: 'HMS'}],
    position: 'topright'
}).addTo(map);
```

Next a "navigation map" is added, using L.control.extraMap(). The navigation map is synchronized with the main map. The tile layer object in the navigation map must be distinct from that of the main map, even if it deals with the same data-cube, as here. For displaying the navigation layer we select only channels #2,#3 and #4:

```
var navlayer = L.tileLayer.iip(iip, {
    channelColors: [,[0,0,1],[0,1,0],[1,0,0],],
});
var navmap = L.control.extraMap(navlayer, {
    position: 'topright',
    width: 128,
    height: 128,
    zoomLevelOffset: -6,
    nativeCelsys: true,
}).addTo(map);
```

We now initialize a side-bar that will regroup all advanced controls, and set up the channel mixing controls and the image settings controls:

```
var sidebar = L.control.sidebar().addTo(map);
L.control.iip.channel().addTo(sidebar);
L.control.iip.image().addTo(sidebar);
```

The L.control.iip.catalog() command adds a catalogue overlay selection menu to the interface. The list of catalogues below is comprised of the 2MASS [2], SDSS [3], and Hudelot et al. [4] catalogues (the latter is defined in catalogs.custom.js):

```
L.control.iip.catalog([
  L.Catalog['2MASS'],
  L.Catalog['SDSS'],
  L.Catalog['Hudelot']
]).addTo(sidebar);
```

Regions/Points Of Interest are managed through a very similar interface; using *region objects* in place of *catalog objects*. In our example the objects' content is assigned right in the call to L.control.iip.region():

```
L.control.iip.region(
  [
    {
     url: 'observation_footprint.json',
      name: 'observation footprint',
      description: 'Footprint of the optical observations',
      color: 'blue',
      load: false
    },
    {
      url: 'poi.json',
      name: 'Molinari+ 2011 POIs',
      description: 'Points of Interest discussed in Einstein et al. 2016',
      color: 'orange',
      load: false
    }
  ],
  { nativeCelsys: true }
).addTo(sidebar);
```

L.control.iip.profile() adds a measurement tab:

```
L.control.iip.profile().addTo(sidebar);
```

Finally, L.control.iip.doc() can be invoked to add an online documentation tab. Any website may be displayed in the documentation panel; it is sand-boxed inside an HTML iframe element. Additionally, a URL to a PDF file may be provided, making a "Download PDF" button pop up in the interface.

```
sidebar.addTabList();
L.control.iip.doc('doc/index.html', {
   pdflink: 'doc/doc.pdf'
```

```
}).addTo(sidebar);
</script>
</body>
```

Note the call to sidebar.addTabList() which moves the next tab to the bottom of the side bar.

VisiOmatic programming interface

The **VisiOmatic** client provides the following sub-properties to the original Leaflet "classes" with new or overloaded methods:

Class	Purpose
L.TileLayer.IIP	Manage IIP tile layers
L.CRS.WCS	Handle celestial coordinates
L.Control.IIP	Common class for managing interface menus and widgets (not used di-
	rectly)
L.Control.IIP.Channel	Channel mixing interface
L.Control.IIP.Image	Image settings interface
L.Control.IIP.Catalog	Catalog overlay interface
L.Control.IIP.Profile	Image profile overlay interface
L.Control.IIP.Region	Region- and Point-of-interest interface
L.Control.IIP.Doc	Documentation interface
L.Control.Sidebar	Side menu bar and panels
L.Control.WCS	Coordinate input/output interface
L.Control.Scale.WCS	Celestial or pixel scale line
L.Control.Reticle	Reticle at the center of the map
L.Control.ExtraMap	Secondary map synchronized to the main map
L.RGB	Class for managing R,G,B color triplets that describe color pixels
L.Ellipse/L.EllipseMarker	Class for drawing ellipse overlays in world/pixel coordinates on a map

VisiOmatic also provides set of utility functions, grouped in the L.IIPUtils object:

Function	Purpose
L.IIPUtils.requestURL()	Make an Ajax call to the specified server
L.IIPUtils.parseURL()	Parse the given URL and generate a dictionary of query keyword/value
	pairs
L.IIPUtils.checkDomain()	Return the domain of the given URL
L.IIPUtils.isExternal()	Check if the given URL is from an external domain

5.1 Classes

5.1.1 L.TileLayer.IIP

L. TileLayer. IIP manages tile layers with image data queried from an IIP image tile server.

Usage example

```
var map = L.map('map', {fullscreenControl: true});
var iip = '/fcgi-bin/iipsrv.fcgi?FIF=image.ptif';
var ima = L.tileLayer.iip(iip, {cmap: 'jet'}).addTo(map);
```

Creation

```
L.tileLayer.iip(<String>url,<tilelayer-options>options?)
```

instantiates an IIP tile layer object given a URL url.

Options

The constructor supports all options from the regular TileLayer plus

Option	Туре	Default	Description
crs	L.CRS.WCS	Extracted from the data	Coordinate Reference or World Coordi-
	object	header if available; raw pixel coordinates otherwise	nate System
nativeCelSys	Boolean	false	True if native coordinates (e.g., galac-
			tic coordinates) are to be used instead of
			equatorial coordinates
center	String	false	World coordinates (either in
			RA,Dec decimal form or in
			hh:mm:ss.s±dd:mm:ss.s sex-
			agesimal format), or any <i>Sesame</i> - compliant identifier defining the initial
			centering of the map upon layer ini-
			tialization. Sexagesimal coordinates
			and identifier strings are sent to the
			Sesame resolver service for conversion
			to decimal coordinates. Assume x,y
			pixel coordinates if WCS information is
			missing. Use false for default map
			centering.
fov	Float	false	Field of view covered by the map upon
			later initialization, in world coordinates (degrees, or pixel coordinates if WCS
			information is missing). Use false for
			default map zooming.
contrast	Float	1.0	Contrast factor
colorSat	Float	1.0	Color saturation for multi-channel data
			(0.0: B&W, >1.0: enhance)
gamma	Float	1.0 for 8 or 16 bit images	Display gamma
		or 2.2 for 32 bit (integer or	
		floating-point) images	
сМар	String	'grey'	Colormap for single channels or chan-
			<pre>nel combinations. Valid colormaps are 'grey','jet','cold' and 'hot'</pre>
invertCMap	Boolean	false	Invert Colormap or color mix (like a
invercenap	Doolean	TUISC	negative)
quality	Integer	90	JPEG encoding quality in percent
mixingMode	Strings	'color'	Channel mixing mode. Valid modes
			are 'mono' (single-channel) and
			'color'
channelColors	Array of	[rgb(0.0,0.0,1.0),	RGB contribution of each channel to the
	L.RGB color	rgb(0.0,1.0,0.0),	mixing matrix
	triplets	rgb(1.0,0.0,0.0), rgb(0.0,0.0,0.0),	
channelLabels	Array of	['Channel #1',	Channel labels
	strings	'Channel #2',]	
channelLabelMa	-	·.*'	Regular expression matching the labels
	-		of channels that are given a color by de-
			fault
channelUnits	Array of	['ADUs','ADUs',]	Channel units
	strings		
minMaxValues	Array of	Extracted from the	Pairs of lower, higher clipping limits for
	[Float,Float]	data header if avail-	every channel
		able; [[0.0,255.0], [0.0,255.0],]	
		otherwise	
defaultChannel	Integer	0	Default active channel index (used, e.g.,
			in mono-channel mode)
commandString 5.1. Classes	String	null	Query string for overriding settings dur-
J.I. UIA3355			ing layer initialization.

Public methods

L. TileLayer. IIP provides all the regular L. TileLayer methods plus

Method	Returns	Description
getIIPMetaData(<string>url)</string>	String	Send an OBJ request to the
		server specified by url and re-
		turn a string with the max-size,
		tile-size, resolution-number,
		bits-per-channel,
		min-max-sample-values and
		subject IIP meta-data
<pre>rgbToMix(<integer> chan, <l.rgb> rgb)</l.rgb></integer></pre>	—	Update the channel mixing matrix accord-
		ing to the rgb contribution of channel
		chan
updateMono()	—	Set the layer in monochromatic mode us-
		ing the current active channel
updateMix()	—	Update the mixing matrix in color mode
		using the current ChannelColor and
		colSat settings

5.1.2 L.CRS.WCS

L. CRS. WCS is a new class that extends the original L. CRS object to support celestial projections described by the FITS WCS standard. Currently only the PIXEL (Cartesian), CAR, COE, TAN and ZEA projections are supported, in equatorial, ecliptic, galactic, and supergalactic coordinates.

Usage example

var wcs = L.CRS.wcs(header);

Creation

L.CRS.wcs(<String>hdr,options?)

instantiates a CRS WCS object given a FITS header stored in the hdr string.

Options

Option	Туре	Default	Description
ctype	{x: String, y:	{x: 'PIXEL', y:	WCS projection type for both axes
	String}	'PIXEL'}	
nativeCelSys	Boolean	false	If true native coordinates (e.g., galactic
			coordinates) are to be used instead of equa-
			torial coordinates
naxis L.Point [256, 256]		[256, 256]	Dimensions of the full resolution image in
			pixels
nzoom	Integer	9	Number of zoom levels in the pyramid
crpix	L.Point	[129, 129]	Pixel coordinates of the projection center
crval	L.Latlng	[0.0, 0.0]	World coordinates of the projection center
cd	[[Float,Float],	[[1.0,0.0],	Jacobian matrix of the de-projection at the
	[Float,Float]]	[0.0,1.0]]	projection center
natpole	L.LatLng	[90.0, 180.0]	World coordinates of the native pole

Public methods

L.CRS.WCS provides all the regular *L.CRS* methods plus

Method	Returns	Description
<pre>pixelScale (<float> zoom, <l.latlng></l.latlng></float></pre>	Float	Return the angular pixel scale in degrees at
latLng)		current coordinates and zoom level
<pre>rawPixelScale(<l.latlng>latLng)</l.latlng></pre>	Float	Return the angular pixel scale in degrees at
		current coordinates and at full resolution
fovToZoom (<l.map> map, <float> fov,</float></l.map>	Float	Return the zoom level that corresponds to
<l.latlng>latLng)</l.latlng>		the specified Field-of-View in degrees
zoomToFov (<l.map> map, <float> zoom,</float></l.map>	Float	Return the Field-of-View in degrees that
<l.latlng>latLng)</l.latlng>		corresponds to the specified zoom level
<pre>celsysToEq(<l.latlng>latLng)</l.latlng></pre>	L.LatLn	Convert native celestial coordinates to
		equatorial coordinates
<pre>eqToCelsys(<l.latlng>latLng)</l.latlng></pre>	L.LatLn	Convert equatorial coordinates to native
		celestial coordinates

5.1.3 L.Control.IIP.Channel

L.Control.IIP.Channel is a new control class for managing the channel mixing interface.

Usage example

var control = L.control.iip.channel({cMap: 'jet'}).addTo(map);

Creation

```
L.control.iip.channel(<control-options>options?)
```

instantiates a channel mixing control object in the given mode ('mono' or 'color').

Options

The constructor supports all options from other L.Control classes plus

Option	Туре	Default	Description	
title	String 'Channel mixing' Title of the dialog window or p		Title of the dialog window or panel	
mixingMode	Strings	null	Channel mixing mode at start. Valid	
			modes are 'mono' (single-channel),	
			'color', or null for layer settings	
сМар	String	'grey'	Colormap applied to the layer when the	
			interface is attached to the map. Valid	
			colormaps include 'grey', 'jet',	
			'cold' or 'hot'	

Public methods

L.Control.IIP.Channel provides all the existing L.Control methods plus

Method	Returns	Description
<pre>saveSettings (<l.tilelayer.iip></l.tilelayer.iip></pre>	—	Save current interface settings for the
layer, <string> mode)</string>		given layer and mode
<pre>loadSettings (<l.tilelayer.iip></l.tilelayer.iip></pre>	—	Load current interface settings for the
layer, <string> mode)</string>		given IIP layer and mode

5.1.4 L.Control.IIP.Image

L.Control.IIP.Image is a new control class for managing the image settings interface.

Usage example

var control = L.control.iip.image().addTo(map);

Creation

```
L.control.iip.image(<control-options> options?)
```

instantiates an image control object.

Options

The constructor supports all options from other L.Control classes plus

Option	Туре	Default	Description
title	String	'Image	Title of the dialog window or panel
		preferences'	

5.1.5 L.Control.IIP.Catalog

L.Control.IIP.Catalog is a new control class for managing the interface that controls catalog queries and catalog overlays.

Usage example

```
var control = L.control.iip.catalog([L.Catalog['2MASS'], L.Catalog['SDSS'],
L.Catalog['Hudelot']]).addTo(map);
```

Creation

L.control.iip.catalog(<Array of catalogs>, <control-options> options?)

instantiates a catalog control object with the given list of catalogs.

Catalogs

Catalog objects describe the catalogs that can be queried through a pull-down menu in the interface. They have the following properties (there are no default values):

Option	Туре	Example	Description
name	String	'My catalog'	Catalog label as it will
			appear in the pull-
			down menu
attribution	String	'Catalog of my preferred sources by	Attribution or credit
		Me and al. (2015)'	line
url	String	L.Catalog.vizierURL + '/asu-tsv?&	URL template for the
		-mime=csv&-source=II/246&	catalog query
		-out=2MASS,RAJ2000,DEJ2000,	
		Jmag,Hmag,Kmag&-out.meta=&	
		-c.eq={sys}&-c={lng},{lat}&	
		<pre>-c.bd={dlng},{dlat}&-out.max={nmax}'</pre>	
color	String	'#FC04A0'	Default overlay color
			for this catalog
maglim	Float	20.0	Expected limiting
			magnitude of the
			catalog (used to scale
			symbols).
service	String	'Vizier@CDS'	Label describing the
			web service that pro-
			vides the catalog
regionType	String	'box'	Angular query type:
			'box' or 'cone'
properties	Array of	['J', 'H', 'K']	labels for the source
	strings		properties returned
			by the catalog service
			(except coordinates).
units	Array of	['mag', 'mag', 'mag']	units of the source
	strings		properties returned by
	_		the catalog service.
objurl	String	L.Catalog.vizierURL +	URL template for
		'/VizieR-5?-source=II/246&	querying individual
		-c={ra},{dec},eq=J2000&-c.rs=0.01'	sources (e.g., when
			clicking the source ID
			in the popup source
			dialog)

Pre-defined catalogs include '2MASS', 'SDSS', 'PPMXL', 'Abell', 'NVSS', 'FIRST', 'AllWISE', 'GALEX_AIS' and 'GAIA_DR1', all accessible through *VizieR* queries.

Options

The constructor supports all options from other ${\tt L.Control}$ classes plus

Option	Туре	Default	Description
title	String	'Catalog	Title of the dialog window or panel
		overlay'	
nativeCelSys	Boolean	false	True if native coordinates (e.g., galactic coordinates)
			are to be used instead of equatorial coordinates
color	String	'#FFFF00'	Default catalog overlay color
timeOut	Float	30	Time out delay for catalog queries (in seconds)

5.1.6 L.Control.IIP.Profile

L.Control.IIP.Profile is a new control class for managing the interface that controls profile extraction and profile overlays.

var control = L.control.iip.profile().addTo(map);

Creation

```
L.control.iip.profile (<control-options> options?)
```

instantiates a profile control object.

Options

The constructor supports all options from other L.Control classes plus

Option	Туре	Default	Description
title	String	'Catalog	Title of the dialog window or panel
		overlay'	
color	String	'#FFFF00'	Default profile overlay color

5.1.7 L.Control.IIP.Region

L.Control.IIP.Region is a new control class for managing the region interface.

Usage example

```
var control = L.control.iip.region([
 {
   name: 'Region 1',
   description: 'A first region',
   url: 'region1.json',
   color: 'blue',
   load: false
 },{
   name: 'Region 2',
   description: 'A second region',
   url: 'region2.json',
   color: 'orange',
   load: false
    }
 ],
  { nativeCelsys: true }
).addTo(map);
```

Regions are defined in GeoJSON files. Here is an example of the content of a GeoJSON file:

```
}
},{
    "type":"Feature",
    "geometry": {
        "type":"Point",
        "coordinates": [266.46042,-28.82444]
    },
        "properties": {
        "properties": {
        "description":"<h2>A Point of Interest</h2>This object should be worth momitoring.
    }
}
```

The description string inside the GeoJSON properties object can be used to provide the HTML content of a window that pops up when the user clicks on the accompanying region. Note that links in the description should preferably be targeted to appear in a new browser window/tab using the target='blank' attribute setting.

Creation

```
L.control.iip.region(<Array of regions> regions, <control-options> options?)
```

instantiates a region control object given an array of region objects.

Regions

Region objects describe the regions that can be accessed through a pull-down menu in the interface. They have the following properties (there are no default values):

Option	Туре	Example	Description
name	String	'My region'	Region label as it will appear in the pull-
			down menu
description	String	'This is region	HTML string to appear in a popup win-
		A'	dow when clicking over the region (over-
			ridden by the description property in
			the GeoJSON data).
url	String	'myregions.json'	URL of the GeoJSON data
color	String	'#C0AC23'	Default overlay color for this region
load	Boolean	false	If true, region data are automatically
			loaded as the control is attached to the
			map.

Options

Option	Туре	Default	Description
title	String	'Channel mixing'	Title of the dialog window or panel
nativeCelSys	Boolean	false	True if native coordinates (e.g., galactic
			coordinates) are to be used instead of equa-
			torial coordinates
color	String	/#OOFFFF/	Default region overlay color
timeOut	Float	30	Time out delay for region downloads (in
			seconds)

5.1.8 L.Control.IIP.Doc

L.Control.IIP.Doc is a new control class for displaying online documentation.

Usage example

var control = L.control.iip.doc('mydoc/index.html', {pdflink: 'mydoc/mydoc.pdf'}).addTo(map);

Creation

L.control.iip.doc(<String>url, <control-options> options?)

instantiates a doc control object, given a link to the documentation homepage.

Options

The constructor supports all options from other L.Control classes plus

Option	Туре	Default	Description
title	String	'Documentation'	Title of the dialog window or panel
pdflink	String	'mydoc.pdf'	Link a PDF version of the documentation

5.1.9 L.Control.Sidebar

L.Control.Sidebar is a control class for adding sliding panes to the left or the right of the map. It is derived from the leaflet-sidebar plugin by Tobias Bieniek.

Usage example

var sidebar = L.control.sidebar().addTo(map);

Creation

L.control.sidebar(<control-options>options?)

instantiates a sidebar control object.

Options

Option	Туре	Default	Description
title	String	'Toggle	String which will appear in the tooltip
		advanced menu'	while hovering over the sidebar toggle but-
			ton.
forceSeparateButton	Boolean	false	If true, the sidebar toggle button will be
			separated from the zooming control panel

Public methods

L.Control.Sidebar provides all the existing *L.Control* methods plus

Method	Returns	Description
addTabList()	tabList	Create and return a new tabList (collection
		of tabs)
addTab (<string> id, <string> className,</string></string>	Element	Add a new tab to the current tabList,
<pre><string>title,<element>content,<string></string></element></string></pre>		inserting content into the associated pane,
sideClass)		and return the pane Element
open(<string>id)</string>	—	Open sidebar (if necessary) and show the
		tab with the specified ID
close()	—	Close sidebar (if necessary)
toggle()		Collapse or expand the sidebar

5.1.10 L.Control.WCS

L. Control. WCS is a new control class for managing an input/output coordinate widget.

Usage example

```
var control = L.control.wcs(
  {coordinates: [
     {label: 'RA,Dec', units: 'HMS'},
     {label: 'Gal l,b', units: 'deg', nativeCelsys: true}
]}
).addTo(map);
```

Creation

L.control.wcs(<control-options> options?)

instantiates a WCS control object.

Options

Option	Туре	Default	Description
title	String	'Scale'	Name of the control (to be used for
			tooltips)
coordinates	Array of	[{ label: 'RA,	Set of coordinates settings (see be-
	coordinates	Dec', units: 'HMS',	low)
		<pre>nativeCelsys: false }]</pre>	
centerQueryKe	yString	'center'	Name of the URL query string field
			that should contain the current cen-
			ter of the map when pressing the
			"Copy to Clipboard" button
fovQueryKey	String	'fov'	Name of the URL query string
			field that should contain the cur-
			rent Field-of-View of the map when
			pressing the "Copy to Clipboard"
			button

Coordinates

Coordinates objects describe the coordinates that can be selected through a pull-down menu to the left of the coordinate entry widget. They have the following properties (there are no default values):

Option	Туре	Example	Description
label	String	'RA, Dec'	Coordinate label as it will appear in the pull-down menu
units	String	'HMS'	Coordinate units/types as they will appear in the interface:
			'HMS' for hh:mm:ss.s±dd:mm:ss.s sexagesimal
			format, 'deg' for decimal degrees, 'other' for raw
			decimal output.
nativeCelSys	Boolean	false	True if native coordinates (e.g., galactic coordinates) are
			to be used instead of equatorial coordinates

5.1.11 L.Control.Scale.WCS

L.Control.Scale.WCS is a new control class derived from L.Control.Scale that adds a scale to the map. It supports both angular and pixel units.

Usage example

var control = L.control.scale.wcs({pixels: false}).addTo(map);

Creation

```
L.control.scale.wcs (<control-scale-options> options?)
```

instantiates a WCS scale control object.

Options

The constructor supports all the L.Control.Scale options plus

Option	Туре	Default	Description	
title	String	'Scale'	Name of the control (to be used for tooltips)	
degrees	Boolean	true	Whether to show the degree scale line	
			(deg/arcmin/arcsec/mas)	
pixels	Boolean	true	Whether to show the pixel scale line	
custom	Boolean	false	Whether to show the custom scale line	
customScale	float	1.0	Custom scale factor in pixels	
customUnits	String	"	Name of the custom scale unit	
planetRadius	float	6378137.0	Planet radius in meters (for metric and imperial units)	

5.1.12 L.Control.Reticle

L.Control.Reticle is a new control class that adds a crosshair at the center of the map window.

Usage example

```
var control = L.control.reticle().addTo(map);
```

Creation

```
L.control.reticle()
```

instantiates a reticle control object.

Options

The constructor has no option.

5.1.13 L.Control.ExtraMap

L.Control.ExtraMap is a new control class for displaying an additional map synchronized with the main map, picture-in-picture style. It is an adaptation of Leaflet-MiniMap by Norkart.

Usage example

```
var control = L.control.extraMap(
  L.tileLayer.iip('/fcgi-bin/iipsrv.fcgi?FIF=image.ptif'),
        {
            position: 'topright',
            width: 192,
            height: 128,
            zoomLevelOffset: -6,
        }
).addTo(map);
```

Creation

```
L.control.extraMap(<L.TileLayer>layer,<control-options>options?)
```

instantiates an extraMap control object with the given layer. Note that the layer must not be shared with the main map or another extraMap.

Options

Option	Туре	Default	Description
title	String	'Navigation	Name of the control (to be used for
		mini-map.	tooltips)
		Grab to	
		navigate'	
toggleDisplay	Boolean	true	Whether the extraMap should display a
			minimization button
strings	Array of strings	{hideText:	Labels for the toggle button (appear in
		'Hide map',	tooltips)
		showText:	
		'Show map'}	
autoToggleDisplay	Boolean	false	Whether the extraMap should hide auto-
			matically if the main map bounds do not
			fit within the extraMap bounds (useful
			when zoomLevelFixed is set)
zoomLevelFixed	Boolean or Inte-	false	Valid, fixed zoom level for the ex-
	ger		traMap, or false if a dynamic
			zoomLevelOffset is to be applied
			instead
zoomLevelOffset	Integer	-5	Offset applied to the zoom in the ex-
			traMap with respect to that of the main
			map
zoomAnimation	Boolean	false	Whether the extraMap should have an
			animated zoom (if true, will cause the
			extraMap to lag a bit after the main map)
width	Integer	150	Width of the ExtraMap in pixels
height	Integer	150	Height of the ExtraMap in pixels
collapsedWidth	Integer	24	Width of the toggleMarker and the Ex-
			traMap when collapsed, in pixels
collapsedHeight	Integer	24	Height of the toggleMarker and the Ex-
			traMap when collapsed, in pixels
aimingRectOptions	path-options	{color:	Style of the aiming rectangle
		′#FF7800′,	(clickable is always forced to
		weight: 1,	false)
		clickable:	
		false}	
shadowRectOptions	path-options	{color:	Style of the shadow aiming rectan-
		′#803C00′,	gle (clickable is always forced to
		weight: 1,	false)
		opacity: 0,	
		fillOpacity:	
		Ο,	
		clickable:	
		false}	

Public methods

L.Control.ExtraMap provides all the existing L.Control methods plus

Method	Returns	Description
<pre>changeLayer(<l.tilelayer>layer)</l.tilelayer></pre>	—	Replace the current extraMap layer with
		the one provided

5.1.14 L.RGB

L. *RGB* is a new class for managing **R**,**G**,**B** color triplets that describe color pixels.

```
var rgb = L.rgb(0.2,0.4,0.0);
var rgb = L.rgb([0.2,0.4,0.0]);
var rgb = L.rgb('#336600');
```

Creation

L.rgb (<Float> r, <Float> g, <Float> b) instantiates an RGB object with the given red, green and blue components.

5.1.15 L.Ellipse

5.1.16 L.EllipseMarker

L.Ellipse and L.EllipseMarker are new classes for drawing ellipse overlays on a map, with parameters defined in world and pixel coordinates, respectively.

Usage example

```
var path = L.ellipse(latLng, {
    majAxis: 0.0210, minAxis: 0.0045, posAngle: -30.0
}).addTo(map);
```

```
var path = L.ellipseMarker(latLng, {
    majAxis: 10.0, minAxis: 3.0, posAngle: 24.0
}).addTo(map);
```

Creation

L.ellipse(<L.LatLng>latLng, <path-options>options?) instantiates an ellipse object centered on position latLng.

L.ellipseMarker (<L.LatLng> latLng, <path-options> options?) instantiates an ellipse marker object centered on position latLng.

Option	Туре	Default	Description	
majAxis	Float	101	Ellipse major axis in degrees (L.Ellipse) or in pixels	
			(L.EllipseMarker)	
minAxis	Float	101	Ellipse minor axis in degrees (L.Ellipse) or in pixels	
			(L.EllipseMarker)	
posAngle	Float	'0'	'0' Ellipse position angle in degrees East-of-North (L.Ellipse) or CCW	
			<pre>from x-axis(L.EllipseMarker)</pre>	

Both constructors support all options from other ${\tt L.Path}$ classes plus

5.2 Utility functions

5.2.1 L.IIPUtils.requestURL()

L.IIPUtils.requestURL() is used throughout **VisiOmatic** to send Ajax requests to a given URL.

Usage

L.IIPUtils.requestURL(<String>url,<String>purpose,<Function>action,<Object>context,<Float>timeOut)

```
L.IIPUtils.requestURL(
    'http://cdsweb.u-strasbg.fr/cgi-bin/nph-sesame/-oI/A?M31',
    'getting coordinates for M31',
    function (context, httpRequest) { console.log(context, httpRequest); },
    this,
    10
);
```

Arguments

Name	Туре	Description
url	String	URL to which the request must be sent
purpose	String	Short description of the request purpose
action	Function (context, httpRequest)	Reference to a function to which the context and
		the httpRequest objects will be passed upon
		completion of the request
context	Object	The context object (e.g., this), will be passed
		as a first argument to the action function
timeOut	Float	Time out delay in seconds. No time out if argument
		is missing.

5.2.2 L.IIPUtils.parseURL()

L.IIPUtils.parseURL() parses a URL and returns a dictionary of query string keyword/value pairs.

Usage

L.IIPUtils.parseURL(<String>url)

Usage example

```
args = L.IIPUtils.parseURL(
    'http://myviewer.org/?channel=2&mode=mono'
);
console.log(args['channel'], args['mode']);
```

Arguments

Name	Туре	Description
url	String	URL to be parsed

5.2.3 L.IIPUtils.checkDomain()

L.IIPUtils.checkDomain() parses a URL and returns the domain name associated with it.

Usage

L.IIPUtils.checkDomain(<String>url)

domain = L.IIPUtils.checkDomain('http://myviewer.org/test');

Arguments

Name	Туре	Description
url	String	URL to be parsed

5.2.4 L.IIPUtils.isExternal()

L.IIPUtils.isExternal() parses a URL and returns true if it belongs to the current domain or false otherwise.

Usage

L.IIPUtils.isExternal(<String>url)

Usage example

flag = L.IIPUtils.isExternal('http://myviewer.org/doc/');

Arguments

Name	Туре	Description
url	String	URL to be parsed

5.2.5 L.IIPUtils.copyToClipboard()

L.IIPUtils.copyToClipboard() copies the given string to clipboard.

Usage

L.IIPUtils.copyToClipboard(<String>text)

Usage example

flag = L.IIPUtils.copyToClipboard('http://myurl');

Arguments

Name	Туре	Description
text	String	String to be copied to clipboard

5.2.6 L.IIPUtils.flashElement()

 $\tt L.IIPUtils.flashElement()$ temporily highlights a DOM element using a short (<400ms) "flashing" animation.

Usage

L.IIPUtils.flashElement(<Element>elem)

Usage example

```
flag = L.IIPUtils.flashElement(myInput);
```

Arguments

Name	Туре	Description
elem	Element	Element to highlight

Server installation and configuration

IIPImage is a FastCGI application and as such it requires a web server to run.

This section describes how to install and configure the **IIPImage** server from scratch. Further information can be found on the official IIPImage webpage.

6.1 Pre-requisites

6.1.1 Hardware

The **IIPImage** server (**iipsrv**) is meant to run on one or several server machines, with multiple CPU cores. The "astronomy-oriented" version of **iipsrv** is largely vectorized but it is single threaded; multiple CPU cores are taken advantage of through multiple instances spawned by the web server.

iipsrv operates on large data files (image data cubes), which can be as large as several Terabytes. The performance of the astro version is often I/O-limited, especially when it comes to latency. It is therefore important that the data files be located on a fast storage system, with low access times. Ideally this will be an enterprise-level array of SSDs. The lower performance of slower devices, such as spinning disks, can partially be compensated with random access memory by taking advantage of the operating system caching of file operations, as well as the built-in **iipsrv** caching mechanisms. In all cases, the more memory available for caching there is on the system, the more responsive the server will be under heavy load.

In what follows, we will assume that the image data reside in the /raid/array/ directory.

6.1.2 Operating System

This installation guide focuses on Linux. Nevertheless **IIPImage** has been designed to be cross-platform and has been successfully tested on Linux, Sun Solaris, Mac OS X and Windows.

6.1.3 Software

Before starting the installation, one should make sure that "development packages" (coming with header files) of the following libraries have been installed on the server:

- LibFCGI v2.4+
- LibJPEG Turbo v1.2+, or libJPEG
- LibTIFF v4.0+
- zLib v1.2+

Note that **iipsrv** relies on the BigTIFF format for managing image data files larger than 2GB. If BigTIFF support is not included in the **LibTIFF** packages available for your Linux distribution (e.g., because it is too old), a manual installation of **LibTIFF** v4.0+ may be necessary.

6.2 Downloading iipsrv

The source package for this version is available on GitHub. We strongly recommend against installing the master version of IIPImage at this stage, as it has not yet been optimized for working with the **VisiOmatic** client.

6.3 Installing iipsrv

1. Clone the project:

\$ git clone https://github.com/cmarmo/iipsrv-astro.git

2. Enter the project directory:

```
$ cd iipsrv-astro
```

3. Generate configuration files for compilation and installation:

```
$ sh autogen.sh
$ ./configure
```

• Although the command above should work in most cases, the configure script offers many customization options (see ./configure --help), including the possibility to change the paths where include and library files are located. For instance for managing manual installations of the TIFF library:

\$./configure --with-tiff-includes=<DIR> --with-tiff-libraries=<DIR>

• The Intel compiler, **icc**, is able to vectorize loops containing transcendental functions and generally provides superior performance in **iipsrv**, compared to the GNU compiler. If **icc** is installed on your system, the following configuration line will generate an executable optimized for a wide range of machines based on INTEL processors:

```
$ ./configure CXX=icc CXXFLAGS="-O3 -axSSSE3,SSE4.1,SSE4.2,AVX,CORE-AVX2,CORE-AVX-I -no-prec-
```

4. Compile and install:

```
$ make
$ sudo cp src/iipsrv.fcgi /<your>/<fcgi-bin>/<directory>
```

6.4 Web server configuration

The real life performance of **iipsrv** for serving tiles critically depends on the HTTP web server configuration. It depends even more on the HTTP server itself, especially in high concurrency environments.

6.4.1 Assessing server performance

In [1], four HTTP server packages — Apache v2.4.1, lighttpd v1.4.35, NGINX v1.4.7 and OpenLiteSpeed v1.2.7 — were benchmarked with iipsrv. Fig. 6.1 shows how efficiently each of these servers responds to bursts of tile queries for various levels of concurrency (the number of queries in each burst). Tile queries were simulated using a modified version of the Apache Benchmarking tool benchmarking tool on a local machine, connected through a 10GbE link. The result is expressed in terms of throughput (the number of tiles per seconds) and latency (the average time it takes for tiles to be returned). Perfect server behaviour would consist of constant throughput, and latency that increases linearly with concurrency beyond some threshold, as queries are queued inside the server pipeline.

As can be seen, HTTP server packages behave very differently in this test. If we set the limit for acceptable latency to 1 second, we see that a 12-core system is able to manage bursts of up to 2,000 simultaneous queries




Fig. 6.1: **IIPImage-astro** tile-serving throughput and latency as a function of concurrency for four different HTTP servers running on the same 12-core Linux system.

with **OpenLiteSpeed**, which corresponds to about 100 users frantically browsing through the image. With **Apache**, these numbers are ten times lower, and both throughput and latency behave much more erratically.

All HTTP server packages were configured so as to maximize tile serving performance. Although some aspects may have not been fully optimized, **OpenLiteSpeed** comes out as the clear winner in this test. This is why we recommend it for running **IIPImage**. Nevertheless, in the sections below we also provide configuration guides for all four packages.

6.4.2 Apache

The mod_fastcgi module must be installed and enabled. A directory containing FastCGI programs should be created and readable by **Apache** processes. Make sure that your **Apache** configuration file (or the configuration file for the FCGI module) contains the following lines

```
LoadModule fastcgi_module /path/to/apachemodules/mod_fastcgi.so
# Create a directory for the iipsrv binary
ScriptAlias /fcgi-bin/ "/path/to/fcgi/directory/fcgi-bin/"
#
# Set the options on that directory
<Directory "/path/to/fcgi/directory/fcgi-bin/">
AllowOverride None
Options None
# Syntax for access is different in Apache 2.4 - uncomment appropriate version
 # Apache 2.2
    Order allow, deny
 #
#
    Allow from all
 #
# Apache 2.4
Require all granted
</Directory>
```

Finally, the **iipsrv** configuration file, iipsrv.conf must be copied in the **Apache** configuration directory (e.g., /etc/httpd/conf.d/). The following iipsrv.conf features typical settings for a 12-core machine:

```
# Set our environment variables for the IIP server
FcgidInitialEnv VERBOSITY "0"
FcgidInitialEnv LOGFILE "/tmp/iipsrv.log"
FcgidInitialEnv MAX_IMAGE_CACHE_SIZE "100"
FcgidInitialEnv JPEG_QUALITY "90"
FcgidInitialEnv MAX_CVT "3000"
FcgidInitialEnv MEMCACHED_SERVERS "localhost"
FcgidInitialEnv FILESYSTEM_PREFIX "/raid/iip/"
# Define the idle timeout as unlimited and the number of # processes we want
FcgidIdleTimeout -1
FcgidMaxProcessesPerClass 12
```

6.4.3 lighttpd

lighttpd comes with built-in FastCGI support. To configure **iipsrv**, add in your **lighttpd** directory an ASCII file iipsrv.conf containing

```
fastcgi.server = ( "/fcgi-bin/iipsrv.fcgi" =>
  (( "host" => "127.0.0.1",
    "port" => 9000,
    "check-local" => "disable",
    "min-procs" => 1,
    "max-procs" => 12,
    "bin-path" => server_root + "/fcgi-bin/iipsrv.fcgi",
    "bin-environment" => (
        "LOGFILE" => log_root + "/iipsrv.log",
        "VERBOSITY" => "3",
```

```
"MAX_IMAGE_CACHE_SIZE" => "100",
"FILENAME_PATTERN" => "_pyr_",
"JPEG_QUALITY" => "90",
"MAX_CVT" => "3000",
"MEMCACHED_SERVERS" => "localhost",
"FILESYSTEM_PREFIX" => "/raid/iip/"
)
```

For best performances edit the lighttpd server settings in /etc/lighttpd/lighttpd.conf:

```
server.use-ipv6 = "disable"
server.document-root = server_root + "/html"
server.max-fds = 300000
server.stat-cache-engine = "fam"
server.max-connections = 100000
server.max-keep-alive-idle = 4
server.max-keep-alive-requests = 4
```

Then restart the **lighttpd** server.

6.4.4 NGINX

6.4.5 OpenLiteSpeed

The latest stable version of the **OpenLiteSpeed** web server (**lsws**) can be downloaded from http://open.litespeedtech.com/. On most machines, installing **lsws** from the source package is as simple as

```
$ ./configure
$ make
$ sudo make install
```

On RedHat-like systems (e.g., RedHat, Fedora, CentOS,...), the OpenLiteSpeed web server is started with

\$ service lsws start

OpenLiteSpeed comes with a graphical web interface which is by default accessible on port 7080 of the server. The default administrator login and password are admin and 123456. Any change to the server configuration made in the interface requires applying a "Graceful Restart" (follow instructions on the web page).

Configuring **OpenLiteSpeed** for **iipsrv** starts by adding a new "virtual host", or modifying the default one that comes with **OpenLiteSpeed** (Fig. 6.2).

The virtual host menu has several tabs. For this FastCGI application we are mostly concerned with the Basic, External App and Context tabs.

In the Basic tab, one should change the Virtual Host Name field to, e.g., *iipsrv-vhost*, and set ExtApp Set UID Mode to DocRoot UID (see Fig. 6.3).

The External App tab is where the FastCGI executable must be defined and where it can be fine-tuned. Fig. 6.4 shows an example of a configuration which is appropriate for a 12-core server (Max Connections = 12 and Instances = 12) with high throughput (Connection Keepalive Timout = 5).

Finally, an FCGI entry should be added in the Context tab (Fig. 6.5).

6.5 iipsrv configuration and testing

The IIPImage webpage gives a description of all the configuration parameters known to **iipsrv**. The following parameters require particular attention:

lome	Actions Con	figuration Web Console Help	
erve	r Listeners (1) Vi	irtual Hosts (1) Virtual Host Templates (3)	
'irtual	Hosts		
Vietu	al Hosts		
VIILU			
Virtua	l Host List		Add
	Name 合	Virtual Host Root 🛖	Action
		\$SERVER ROOT/DEFAULT/	View/Edit Delete

Copyright © 2013-2015 LiteSpeed Technologies, Inc. All Rights Reserved.

Fig. 6.2: A single "virtual host" is sufficient for operating **iipsrv**.

r		bServ	CI .							Litespeed We	b Server Open	1.3.12 L
lome	Actions	С	onfiguratio	on	Web Console	Help						
erver	Listeners	(1)	Virtual	Hos	sts (1) Virtual	Host Templates ((3)					
/irtual H	ost » iipsrv	-vhost										
Basic	General	Log	Secur	ity	External App	Script Handler	Rewrite	Context	SSL	Web Socket Proxy	Modules	
Base												Edi
Virtual Ho	ost Name			0	iipsrv-vhost							
Virtual Ho	ost Root			0	\$SERVER_ROOT/I	DEFAULT/						
Config Fi	le			0	\$VH_ROOT/conf/vh	nconf.xml						
Notes				0								
Connect	ion											Edi
Max Kee	p-Alive Reque	ests		0	Not Set							
Smart Ke	ep-Alive			0	Not Set							
Security												Edi
Follow Sy	mbolic Link			0	Yes							
Enable S	cripts/ExtApp	s		2	Yes							
Restraine	ed			0	Yes							
ExtApp S	et UID Mode			0	DocRoot UID							
Per Clier	nt Throttling			_								Edi
Static Re	quests/secon	d		0	Not Set							
Dynamic	Requests/se	cond		2								
Outbound	d Bandwidth (bytes/s	ec)	2								
Inbound I	Bandwidth (b	/tes/sec	:)	2								

Copyright © 2013-2015 LiteSpeed Technologies, Inc. All Rights Reserved.

Fig. 6.3: Example of a configuration for the ${\tt Basic}$ tab in the ${\tt Virtual}$ ${\tt Host}$ section.



lome Actions (Configuration	Web Console	Help							
erver Listeners (1)	Virtual Hos	sts (1) Virtual	Host Templates	5 (3)						
′irtual Host » iipsrv-vhos	st									
Basic General Log	Security	External App	Script Handle	r Rewrite	Context	SSL	Web Sock	et Proxy	Modules	
 Give a name that easy tr Address can be IPv4 sor /myfcgi.sock. UDS is chrooted in chrou For local FCGI, Unix dor the FCGI is inaccessible Local FCGI can be started 	cket address "IF ot environment. main socket is p from other ma	P:PORT", like 192.1 referred due to security	68.1.3:7777 and loca	alhost:7777 or U ormance. If you	have to use I	Pv4 socke	et, set the IP p			
FastCGI App Definition									c	Save B
A 1	0									
		iipsrv-app 127.0.0.1:9000								
Address			-CGI server	_	_			_		_
Address	0	127.0.0.1:9000								
Address Notes Max Connections	0	127.0.0.1:9000	e: 1 - 2000 90 HE SIZE=100							
Name Address Notes Max Connections Environment Initial Request Timeout (secs	© 0 0 0 0	IIPImage Fast IIPImage Fast I2 VERBOSITY=0 JPEG_QUALITY=0 MAX_CVT=3000 MAX_IMAGE CACI	e: 1 - 2000 90 HE SIZE=100							

Retry Timeout (secs)	2	number >= 0 [15
Persistent Connection	0	• Yes No Not Set
Connection Keepalive Timeout	0	number valid range: -1 - 10000
Response Buffering	2	Yes
Auto Start	2	Yes 🔺
Command	2	/var/www/fcgi-bin/iipsrv.fcgi
Back Log	0	number valid range: 1 - 100
Instances	0	number valid range: 0 - 1000 12
suEXEC User	2	
suEXEC Group	2	
umask	2	
Run On Start Up	2	No
Max Idle Time	0	number >= -1
Priority	0	number valid range: -20 - 20

Fig. 6.4: Example of a configuration for the ${\tt External}$ App tab in the ${\tt Virtual}$ Host section.

Iome Actions Configu	ation	Web Console Help
erver Listeners (1) Virtu	al Ho	sts (1) Virtual Host Templates (3)
'irtual Host » iipsrv-vhost		
Basic General Log Sec	urity	External App Script Handler Rewrite Context SSL Web Socket Proxy Modules
FCGI Context Definition		Edit Delete Bac
URI	0	/fcgi-bin/
Fast CGI App	0	[VHost Level]: iipsrv-app
Notes	0	send to iipsrv Fast-CGI
Extra Headers	2	Not Set
Realm		Not Set
Authentication Name	0	Not Set
Require (Authorized Users/Groups)	2	Not Set
Access Allowed	2	Not Set
Access Denied	2	Not Set
Authorizer	2	Not Set
Add Default Charset	2	Off
Customized Default Charset	2	Not Set
Enable IP GeoLocation	2	Not Set

Copyright © 2013-2015 LiteSpeed Technologies, Inc. All Rights Reserved.

Fig. 6.5: Example of a FastCGI entry in the ${\tt Context}$ tab of the ${\tt Virtual}$ Host section.

- FILESYSTEM_PREFIX is a prefix added by ipsrv to the image data path for all queries. For security reasons, it is strongly advised to set FILESYSTEM_PREFIX to a path which does not directly or indirectly lead to a system or user directory, or to any file data that must remain unaccessible to the users.
- VERBOSITY should be set to 0 for performance reasons.
- CORS manages Cross Origin Resource Sharing. It must be set to * if the tiles are to be accessible to any client (such as 3rd party applications) outside of those provided by the web server itself.
- MAX_IMAGE_CACHE_SIZE sets the size of the **iipsrv** JPEG image cache (in MB), which is allocated in memory for every instance. Typical values range from 100 to 2000, depending on the amount of memory in the server, and the number of **iipsrv** instances.
- MEMCACHED_SERVERS can be used to specify a comma-separated list of IP addresses with optional port numbers (e.g., 127.0.0.1:8888) that provide caching capabilities using the Memcached protocol. It is strongly advised to use Memcached in all cases where high traffic loads involving majoritarily identical tile queries are to be expected, e.g., for public outreach applications.

Once the server installed and configured, pointing a web browser to the **iipsrv** FCGI URL without any argument (e.g., "http://myurl/fcgi-bin/iipsrv.fcgi") should return a web page similar to that of Fig. 6.6.



Fig. 6.6: Web page returned by the **iipsrv** FCGI in the absence of arguments.

6.6 System configuration

Server performance also depends on system settings. For maximizing server responsiveness under high concurrency, we recommend following the prescriptions of [8]. Some appropriate sysctl.conf are given on the G-WAN website and were used with great success during **iipsrv** tests. They are reproduced below:

```
fs.file-max = 300000
net.core.netdev_max_backlog = 400000
net.core.optmem_max = 10000000
net.core.rmem_default = 10000000
net.core.rmem_max = 10000000
net.core.somaxconn = 100000
net.core.wmem_default = 10000000
net.core.wmem_max = 10000000
net.ipv4.conf.all.rp_filter = 1
net.ipv4.conf.default.rp_filter = 1
net.ipv4.ip_local_port_range = 1024 65535
net.ipv4.tcp_congestion_control = bic
net.ipv4.tcp_ecn = 0
net.ipv4.tcp_max_syn_backlog = 12000
net.ipv4.tcp_max_tw_buckets = 2000000
net.ipv4.tcp_mem = 30000000 30000000 30000000
net.ipv4.tcp_rmem = 30000000 30000000 30000000
net.ipv4.tcp_sack = 1
net.ipv4.tcp_syncookies = 1
net.ipv4.tcp_timestamps = 1
net.ipv4.tcp_wmem = 30000000 30000000 30000000
# optionally, avoid TIME_WAIT states on localhost no-HTTP Keep-Alive tests:
     "error: connect() failed: Cannot assign requested address (99)"
#
# On Linux, the 2MSL time is hardcoded to 60 seconds in /include/net/tcp.h:
# #define TCP_TIMEWAIT_LEN (60*HZ)
# The option below is safe to use:
net.ipv4.tcp_tw_reuse = 1
# The option below lets you reduce TIME_WAITs further
# but this option is for benchmarks, NOT for production (NAT issues)
# net.ipv4.tcp_tw_recycle = 1
# Increase nf_conntrack
net.netfilter.nf_conntrack_max = 262144
```

Acknowledgements

VisiOmatic implements services provided by the *Sesame* name resolver and the *VizieR* catalog access tool developed at *CDS*, Strasbourg, France.

Development of VisiOmatic v2.0 was made possible by the ESA/ESTEC Faculty through a grant acquired by G. Pilbratt for the ESAimage viewer project.

Bibliography

- [1] E. Bertin, R. Pillay, and C. Marmo. Web-based visualization of very large scientific astronomy imagery. *Astronomy and Computing*, 10:43–53, 2015.
- [2] R. M. Cutri, M. F. Skrutskie, S. van Dyk, C. A. Beichman, J. M. Carpenter, T. Chester, L. Cambresy, T. Evans, J. Fowler, J. Gizis, E. Howard, J. Huchra, T. Jarrett, E. L. Kopan, J. D. Kirkpatrick, R. M. Light, K. A. Marsh, H. McCallon, S. Schneider, R. Stiening, M. Sykes, M. Weinberg, W. A. Wheaton, S. Wheelock, and N. Zacarias. VizieR Online Data Catalog: 2MASS All-Sky Catalog of Point Sources (Cutri+ 2003). *VizieR Online Data Catalog*, 2246:0, 2003.
- [3] K. N. Abazajian, J. K. Adelman-McCarthy, M. A. Agüeros, S. S. Allam, C. Allende Prieto, D. An, K. S. J. Anderson, S. F. Anderson, J. Annis, N. A. Bahcall, and et al. The Seventh Data Release of the Sloan Digital Sky Survey. *ApJS*, 182:543–558, 2009.
- [4] P. Hudelot, J.-C. Cuillandre, K. Withington, Y. Goranova, H. McCracken, F. Magnard, Y. Mellier, N. Regnault, M. Betoule, H. Aussel, J. J. Kavelaars, P. Fernique, F. Bonnarel, F. Ochsenbein, and O. Ilbert. The final Canada-France-Hawaii Telescope Legacy Survey Survey (CFHTLS) release. *VizieR Online Data Catalog*, 2012.
- [5] F. Ochsenbein, P. Bauer, and J. Marcout. The VizieR database of astronomical catalogues. Astronomy and Astrophysics Supplement Series, 143:23–32, 2000.
- [6] Denis Pitzalis, Ruven Pillay, and Christian Lahanier. A new concept in high resolution internet image browsing. In 10th International Conference on Electronic Publishing, 75–85. Bansko, Bulgaria, June 2006. Bulgarian Academy of Sciences, Bulgaria. 10th International Conference on Electronic Publishing, organised by the Bulgarian Academy of Sciences, Bulgaria, 14-16 June 2006.
- [7] E. Bertin. Displaying Digital Deep Sky Images. In P. Ballester, D. Egret, and N. P. F. Lorente, editors, Astronomical Data Analysis Software and Systems XXI, volume 461 of Astronomical Society of the Pacific Conference Series, 263. September 2012.
- [8] Bryan Veal and Annie Foong. Performance scalability of a multi-core web server. In Proceedings of the 3rd ACM/IEEE Symposium on Architecture for Networking and Communications Systems, ANCS '07, 57–66. New York, NY, USA, 2007. ACM.