
Bastille Documentation

Release 0.6.20200202-beta

Christer Edwards

May 20, 2020

Contents:

1	Installation	3
1.1	PKG	3
1.2	ports	3
1.3	GIT	3
2	Network Requirements	5
2.1	Local Area Network	5
2.2	Public Network	6
2.3	/etc/pf.conf	6
3	Usage	9
4	Targeting	11
5	Examples: Containers	13
6	Examples: Releases	15
7	Bastille sub-commands	17
7.1	bootstrap	17
7.2	Releases	17
7.3	Templates	18
7.4	cmd	18
7.5	console	19
7.6	cp	19
7.7	create	20
7.8	destroy	20
7.9	htop	21
7.10	pkg	21
7.11	restart	24
7.12	service	24
7.13	start	24
7.14	stop	25
7.15	sysrc	25
7.16	top	25
7.17	update	26
7.18	upgrade	27

7.19	verify	27
8	Template	29
8.1	Applying Templates	30
9	jail.conf	33
9.1	devfs_ruleset	33
9.2	enforce_statfs	34
9.3	exec.clean	34
9.4	exec.consolelog	34
9.5	exec.start	34
9.6	exec.stop	35
9.7	host.hostname	35
9.8	interface	35
9.9	mount.devfs	35
9.10	mount.fstab	35
9.11	path	35
9.12	securelevel	36
10	Copyright	37

Welcome to the official Bastille documentation. This collection of documents will outline installation and usage of Bastille.

The latest version of this documentation can always be found at <https://docs.bastillebsd.org>.

Bastille is available in the official FreeBSD ports tree at *sysutils/bastille*. Binary packages available in *quarterly* and *latest* repositories.

Current version is *0.6.20200202*.

To install from the FreeBSD package repository:

- quarterly repository may be older version
- latest repository will match recent ports

1.1 PKG

```
pkg install bastille
```

To install from source (don't worry, no compiling):

1.2 ports

```
make -C /usr/ports/sysutils/bastille install clean
```

1.3 GIT

```
git clone https://github.com/BastilleBSD/bastille.git
cd bastille
make install
```

This method will install the latest files from GitHub directly onto your system. It is verbose about the files it installs (for later removal), and also has a *make uninstall* target.

Network Requirements

Here's the scenario. You've installed Bastille at home or in the cloud and want to get started putting applications in secure little containers, but how do I get these containers on the network?

Bastille tries to be flexible about how to network containerized applications. The two most common methods are described here. Consider both options to decide which design work best for your needs. One of the methods works better across clouds while the other is simpler if used in local area networks.

As you've probably seen, Bastille containers require certain information when they are created. An IP address has to be assigned to the container through which all network traffic will flow.

When the container is started the IP address assigned at creation will be bound to a network interface. In FreeBSD these interfaces have different names, but look something like *em0*, *bge0*, *re0*, etc. On a virtual machine it may be *vtnet0*. You get the idea...

Note: if you are running in the cloud and only have a single public IP you may want the Public Network option. See below.

2.1 Local Area Network

I will cover the local area network (LAN) method first. This method is simpler to get going and works well in a home network (or similar) where adding alias IP addresses is no problem.

Bastille allows you to define the interface you want the IP attached to when you create it. An example:

```
bastille create alcatraz 12.1-RELEASE 192.168.1.50 em0
```

When the *alcatraz* container is started it will add *192.168.1.50* as an IP alias to the *em0* interface. It will then simply be another member of the hosts network. Other networked systems (firewall permitting) should be able to reach services at that address.

This method is the simplest. All you need to know is the name of your network interface and a free IP on your current network.

(Bastille does try to verify that the interface name you provide it is a valid interface. This validation has not been exhaustively tested yet in Bastille's beta state.)

2.2 Public Network

In this section I'll describe how to network containers in a public network such as a cloud hosting provider (AWS, digital ocean, vultr, etc)

In the public cloud you don't often have access to multiple private IP addresses for your virtual machines. This means if you want to create multiple containers and assign them all IP addresses, you'll need to create a new network.

What I recommend is creating a cloned loopback interface (*bastille0*) and assigning all the containers private (rfc1918) addresses on that interface. The setup I develop on and use Bastille day to day uses the *10.0.0.0/8* address range. I have the ability to use whatever address I want within that range because I've created my own private network. The host system then acts as the firewall, permitting and denying traffic as needed.

I find this setup the most flexible across all types of networks. It can be used in public and private networks just the same and it allows me to keep containers off the network until I allow access.

Having said all that here are instructions I used to configure the network with a private loopback interface and system firewall. The system firewall NATs traffic out of containers and can selectively redirect traffic into containers based on connection ports (ie; 80, 443, etc.)

First, create the loopback interface:

```
ishmael ~ # sysrc cloned_interfaces+=lo1
ishmael ~ # sysrc ifconfig_lo1_name="bastille0"
ishmael ~ # service netif cloneup
```

Second, enable the firewall:

```
ishmael ~ # sysrc pf_enable="YES"
```

Create the firewall rules:

2.3 /etc/pf.conf

```
ext_if="vtnet0"

set block-policy return
scrub in on $ext_if all fragment reassemble
set skip on lo

table <jails> persist
nat on $ext_if from <jails> to any -> ($ext_if)

## static rdr example
## rdr pass inet proto tcp from any to any port {80, 443} -> 10.17.89.45

## dynamic rdr anchor (see below)
rdr-anchor "rdr/*"

block in all
pass out quick modulate state
```

(continues on next page)

(continued from previous page)

```
antispoof for $ext_if inet
pass in inet proto tcp from any to any port ssh flags S/SA modulate state

# If you are using dynamic rdr also need to ensure that the external port
# range you are using is open
# pass in inet proto tcp any to any port <rdr-start>:<rdr-end>
```

- Make sure to change the *ext_if* variable to match your host system interface.
- Make sure to include the last line (*port ssh*) or you'll end up locked out.

Note: if you have an existing firewall, the key lines for in/out traffic to containers are:

```
nat on $ext_if from <jails> to any -> ($ext_if)

## static rdr example
## rdr pass inet proto tcp from any to any port {80, 443} -> 10.17.89.45
```

The *nat* routes traffic from the loopback interface to the external interface for outbound access.

The *rdr pass ...* will redirect traffic from the host firewall on port X to the ip of Container Y. The example shown redirects web traffic (80 & 443) to the containers at *10.17.89.45*.

dynamic rdr anchor (see below) *rdr-anchor "rdr/*"*

The *rdr-anchor "rdr/*"* enables dynamic rdr rules to be setup using the *bastille rdr* command at runtime - eg.

```
bastille rdr <jail> tcp 2001 22 # Redirects tcp port 2001 on host to 22 on jail
bastille rdr <jail> udp 2053 53 # Same for udp
bastille rdr <jail> list # List dynamic rdr rules
bastille rdr <jail> clear # Clear dynamic rdr rules
```

Note that if you are redirecting ports where the host is also listening (eg. *ssh*) you should make sure that the host service is not listening on the cloned interface - eg. for *ssh* set *sshd_flags* in *rc.conf*

```
sshd_flags="-o ListenAddress=<hostname>"
```

Finally, start up the firewall:

```
ishmael ~ # service pf restart
```

At this point you'll likely be disconnected from the host. Reconnect the *ssh* session and continue.

This step only needs to be done once in order to prepare the host.

Usage

```
ishmael ~ # bastille -h
Bastille is an open-source system for automating deployment and management of
containerized applications on FreeBSD.

Usage:
  bastille command [ALL|glob] [args]

Available Commands:
  bootstrap  Bootstrap a FreeBSD release for container base.
  cmd        Execute arbitrary command on targeted container(s).
  console    Console into a running container.
  cp         cp(1) files from host to targeted container(s).
  create     Create a new thin container or a thick container if -T|--thick option
↳specified.
  destroy    Destroy a stopped container or a FreeBSD release.
  help       Help about any command
  htop       Interactive process viewer (requires htop).
  list       List containers, releases, templates, or logs.
  pkg        Manipulate binary packages within targeted container(s). See pkg(8).
  restart    Restart a running container.
  service    Manage services within targeted containers(s).
  start      Start a stopped container.
  stop       Stop a running container.
  sysrc      Safely edit rc files within targeted container(s).
  template   Apply file templates to targeted container(s).
  top        Display and update information about the top(1) cpu processes.
  update     Update container base -pX release.
  upgrade    Upgrade container release to X.Y-RELEASE.
  verify     Compare release against a "known good" index.
  zfs        Manage (get|set) zfs attributes on targeted container(s).

Use "bastille -v|--version" for version information.
Use "bastille command -h|--help" for more information about a command.
```


Bastille uses a *command-target-args* syntax, meaning that each command requires a target. Targets are usually containers, but can also be releases.

Targeting a containers is done by providing the exact containers name.

Targeting a release is done by providing the release name. (Note: do not include the *-pX* point-release version.)

Bastille includes a pre-defined keyword ALL to target all running containers.

In the future I would like to support more options, including globbing, lists and regular-expressions.

Examples: Containers

```
ishmael ~ # bastille ...
```

command	target	args	description
cmd	ALL	'sockstat -4'	execute <i>sockstat -4</i> in ALL containers (ip4 sockets)
console	mariadb02	—	console (shell) access to mariadb02
pkg	web01 'install nginx'		install nginx package in web01 container
pkg	ALL	upgrade	upgrade packages in ALL containers
pkg	ALL	audit	(CVE) audit packages in ALL containers
sysrc	web01	nginx_enable=YES	execute <i>sysrc nginx_enable=YES</i> in web01 container
template	ALL	username/base	apply <i>username/base</i> template to ALL containers
start	web02	—	start web02 container
cp bastion03 /tmp/resolv.conf-cf etc/resolv.conf copy host-path to container-path in bastion03			
create	folsom	12.0-RELEASE 10.17.89.10	create 12.0 container named <i>folsom</i> with IP

CHAPTER 6

Examples: Releases

```
ishmael ~ # bastille ...
```

command	target	args	description
bootstrap	12.0-RELEASE	—	bootstrap 12.0-RELEASE release
update	11.3-RELEASE	—	update 11.2-RELEASE release
upgrade	11.2-RELEASE	11.3-RELEASE	update 11.2-RELEASE release
verify	11.3-RELEASE	—	update 11.2-RELEASE release

Bastille sub-commands

7.1 bootstrap

The bootstrap sub-command is used to download and extract releases and templates for use with Bastille containers. A valid release is needed before containers can be created. Templates are optional but are managed in the same manner.

Note: your mileage may vary with unsupported releases and releases newer than the host system likely will NOT work at all. Bastille tries to filter for valid release names. If you find it will not bootstrap a valid release, please let us know.

In this document we will describe using the *bootstrap* sub-command with both releases and templates. We begin with releases.

7.2 Releases

7.2.1 Example

To *bootstrap* a release, run the bootstrap sub-command with the release version as the argument.

```
ishmael ~ # bastille bootstrap 11.3-RELEASE [update]
ishmael ~ # bastille bootstrap 12.0-RELEASE
ishmael ~ # bastille bootstrap 12.1-RELEASE
```

This command will ensure the required directory structures are in place and download the requested release. For each requested release, *bootstrap* will download the base.txz. These files are verified (sha256 via MANIFEST file) before they are extracted for use.

7.2.2 Tips

The *bootstrap* sub-command can now take (0.5.20191125+) an optional second argument of “update”. If this argument is used, *bastille update* will be run immediately after the bootstrap, effectively bootstrapping and applying security patches and errata in one motion.

7.2.3 Notes

The bootstrap subcommand is generally only used once to prepare the system. The only other use case for the bootstrap command is when a new FreeBSD version is released and you want to start deploying containers on that version.

To update a release as patches are made available, see the *bastille update* command.

Downloaded artifacts are stored in the *bastille/cache/version* directory. “bootstrapped” releases are stored in *bastille/releases/version*.

To manually bootstrap a release (aka bring your own archive), place your archive in *bastille/cache/name* and extract to *bastille/releases/name*. Your mileage may vary; let me know what happens.

7.3 Templates

Bastille aims to integrate container automation into the platform while maintaining a simple, uncomplicated design. Templates are git repositories with automation definitions for packages, services, file overlays, etc.

To download one of these templates see the example below.

7.3.1 Example

```
ishmael ~ # bastille bootstrap https://gitlab.com/bastillebsd-templates/nginx
ishmael ~ # bastille bootstrap https://gitlab.com/bastillebsd-templates/mariadb-server
ishmael ~ # bastille bootstrap https://gitlab.com/bastillebsd-templates/python3
```

7.3.2 Tips

See the documentation on templates for more information on how they work and how you can create or customize your own. Templates are a powerful part of Bastille and facilitate full container automation.

7.3.3 Notes

If you don't want to bother with git to use templates you can create them manually on the Bastille system and apply them.

Templates are stored in *bastille/templates/namespace/name*. If you'd like to create a new template on your local system, simply create a new namespace within the templates directory and then one for the template. This namespacing allows users and groups to have templates without conflicting template names.

Once you've created the directory structure you can begin filling it with template hooks. Once you have a minimum number of hooks (at least one) you can begin applying your template.

7.4 cmd

To execute commands within the container you can use *bastille cmd*.

```
ishmael ~ # bastille cmd folsom 'ps -auxw'
[folsom]:
USER  PID %CPU %MEM  VSZ  RSS TT  STAT  STARTED    TIME COMMAND
root  71464  0.0  0.0 14536 2000 -  IsJ   4:52PM 0:00.00 /usr/sbin/syslogd -ss
root  77447  0.0  0.0 16632 2140 -  SsJ   4:52PM 0:00.00 /usr/sbin/cron -J 60 -s
root  80591  0.0  0.0 18784 2340 1  R+J   4:53PM 0:00.00 ps -auxw
```

7.5 console

This sub-command launches a login shell into the container. Default is password-less root login.

```
ishmael ~ # bastille console folsom
[folsom]:
FreeBSD 12.1-RELEASE-p1 GENERIC

Welcome to FreeBSD!

Release Notes, Errata: https://www.FreeBSD.org/releases/
Security Advisories:  https://www.FreeBSD.org/security/
FreeBSD Handbook:     https://www.FreeBSD.org/handbook/
FreeBSD FAQ:          https://www.FreeBSD.org/faq/
Questions List:       https://lists.FreeBSD.org/mailman/listinfo/freebsd-questions/
FreeBSD Forums:       https://forums.FreeBSD.org/

Documents installed with the system are in the /usr/local/share/doc/freebsd/
directory, or can be installed later with:  pkg install en-freebsd-doc
For other languages, replace "en" with a language code like de or fr.

Show the version of FreeBSD installed:  freebsd-version ; uname -a
Please include that output and any error messages when posting questions.
Introduction to manual pages:  man man
FreeBSD directory layout:      man hier

Edit /etc/motd to change this login announcement.
root@folsom:~ #
```

At this point you are logged in to the container and have full shell access. The system is yours to use and/or abuse as you like. Any changes made inside the container are limited to the container.

7.6 cp

This command allows efficiently copying files from host to container(s).

```
ishmael ~ # bastille cp ALL /tmp/resolv.conf-cf etc/resolv.conf
[bastion]:

[unbound0]:

[unbound1]:

[squid]:
```

(continues on next page)

(continued from previous page)

```
[nginx]:  
[folsom]:
```

Unless you see errors reported in the output the *cp* was successful.

7.7 create

Bastille create uses any available bootstrapped release to create a lightweight container system. To create a container simply provide a name, bootstrapped release and a private (rfc1918) IP address.

- name
- release
- ip
- interface (optional)

```
ishmael ~ # bastille create folsom 11.3-RELEASE 10.17.89.10 [interface]  
RELEASE: 11.3-RELEASE.  
NAME: folsom.  
IP: 10.17.89.10.
```

This command will create a 11.3-RELEASE container assigning the 10.17.89.10 ip address to the new system.

I recommend using private (rfc1918) ip address ranges for your container. These ranges include:

- 10.0.0.0/8
- 172.16.0.0/12
- 192.168.0.0/16

Bastille does its best to validate the submitted ip is valid. This has not been thoroughly tested—I generally use the 10/8 range.

7.8 destroy

Containers can be destroyed and thrown away just as easily as they were created. Note: containers must be stopped before destroyed.

```
ishmael ~ # bastille stop folsom  
[folsom]:  
folsom: removed
```

```
ishmael ~ # bastille destroy folsom  
Deleting Container: folsom.  
Note: containers console logs not destroyed.  
/usr/local/bastille/logs/folsom_console.log
```


7.9 htop

This one runs *htop* inside the container. note: won't work if you don't have htop installed in the container.

```

 1  [ |           0.5%]  5  [           0.0%]
 2  [ |           0.0%]  6  [           0.0%]
 3  [ |           0.0%]  7  [           0.0%]
 4  [ |           0.0%]  8  [           0.0%]
Mem[|||||||||||||||||7.14G/24.0G]  Tasks: 8, 0 thr; 1 running
Swp[|              0K/2.00G]      Load average: 0.04 0.10 0.08
                                Uptime: 10 days, 22:27:09

  PID USER      PRI  NI  VIRT   RES   S  CPU% MEM%   TIME+  Command
10201 root        20   0   6412  2368   S   0.0  0.0   0:00.02 /usr/sbin/syslogd -ss
34902 root        52   0  11236  6920   S   0.0  0.0   0:00.00 nginx: master process /
36867 nobody     20   0  11236  7556   S   0.0  0.0   0:00.11 | nginx: worker proces
36263 nobody     20   0  11236  7552   S   0.0  0.0   0:00.18 | nginx: worker proces
35024 nobody     20   0  11236  7540   S   0.0  0.0   0:00.09 | nginx: worker proces
34907 nobody     20   0  11236  7552   S   0.0  0.0   0:00.28 | nginx: worker proces
40049 root        20   0   6464  2372   S   0.0  0.0   0:00.06 /usr/sbin/cron -J 60 -s
71424 root        20   0   7160  4124   R   0.0  0.0   0:00.13 /usr/local/bin/htop

F1Help F2Setup F3Search F4Filter F5Sorted F6Collap F7Nice - F8Nice + F9Kill F10Quit

```

7.10 pkg

To manage binary packages within the container use *bastille pkg*.

```

ishmael ~ # bastille pkg folsom 'install vim-console git-lite zsh'
[folsom]:
The package management tool is not yet installed on your system.
Do you want to fetch and install it now? [y/N]: y
Bootstrapping pkg from pkg+http://pkg.FreeBSD.org/FreeBSD:10:amd64/quarterly, please_
↪wait...
Verifying signature with trusted certificate pkg.freebsd.org.2013102301... done
[folsom] Installing pkg-1.10.5_5...
[folsom] Extracting pkg-1.10.5_5: 100%
Updating FreeBSD repository catalogue...
pkg: Repository FreeBSD load error: access repo file(/var/db/pkg/repo-FreeBSD.sqlite)_
↪failed: No such file or directory
[folsom] Fetching meta.txz: 100%    944 B    0.9kB/s    00:01
[folsom] Fetching packagesite.txz: 100%    6 MiB    3.4MB/s    00:02
Processing entries: 100%
FreeBSD repository update completed. 32550 packages processed.
All repositories are up to date.
Updating database digests format: 100%
The following 10 package(s) will be affected (of 0 checked):

New packages to be INSTALLED:

```

(continues on next page)

(continued from previous page)

```

vim-console: 8.1.0342
git-lite: 2.19.1
zsh: 5.6.2
expat: 2.2.6_1
curl: 7.61.1
libnghttp2: 1.33.0
ca_root_nss: 3.40
pcre: 8.42
gettext-runtime: 0.19.8.1_1
indexinfo: 0.3.1

Number of packages to be installed: 10

The process will require 77 MiB more space.
17 MiB to be downloaded.

Proceed with this action? [y/N]: y
[folsom] [1/10] Fetching vim-console-8.1.0342.txz: 100% 5 MiB 5.8MB/s 00:01
[folsom] [2/10] Fetching git-lite-2.19.1.txz: 100% 4 MiB 2.1MB/s 00:02
[folsom] [3/10] Fetching zsh-5.6.2.txz: 100% 4 MiB 4.4MB/s 00:01
[folsom] [4/10] Fetching expat-2.2.6_1.txz: 100% 109 KiB 111.8kB/s 00:01
[folsom] [5/10] Fetching curl-7.61.1.txz: 100% 1 MiB 1.2MB/s 00:01
[folsom] [6/10] Fetching libnghttp2-1.33.0.txz: 100% 107 KiB 109.8kB/s 00:01
[folsom] [7/10] Fetching ca_root_nss-3.40.txz: 100% 287 KiB 294.3kB/s 00:01
[folsom] [8/10] Fetching pcre-8.42.txz: 100% 1 MiB 1.2MB/s 00:01
[folsom] [9/10] Fetching gettext-runtime-0.19.8.1_1.txz: 100% 148 KiB 151.3kB/s
↪00:01
[folsom] [10/10] Fetching indexinfo-0.3.1.txz: 100% 6 KiB 5.7kB/s 00:01
Checking integrity... done (0 conflicting)
[folsom] [1/10] Installing libnghttp2-1.33.0...
[folsom] [1/10] Extracting libnghttp2-1.33.0: 100%
[folsom] [2/10] Installing ca_root_nss-3.40...
[folsom] [2/10] Extracting ca_root_nss-3.40: 100%
[folsom] [3/10] Installing indexinfo-0.3.1...
[folsom] [3/10] Extracting indexinfo-0.3.1: 100%
[folsom] [4/10] Installing expat-2.2.6_1...
[folsom] [4/10] Extracting expat-2.2.6_1: 100%
[folsom] [5/10] Installing curl-7.61.1...
[folsom] [5/10] Extracting curl-7.61.1: 100%
[folsom] [6/10] Installing pcre-8.42...
[folsom] [6/10] Extracting pcre-8.42: 100%
[folsom] [7/10] Installing gettext-runtime-0.19.8.1_1...
[folsom] [7/10] Extracting gettext-runtime-0.19.8.1_1: 100%
[folsom] [8/10] Installing vim-console-8.1.0342...
[folsom] [8/10] Extracting vim-console-8.1.0342: 100%
[folsom] [9/10] Installing git-lite-2.19.1...
==> Creating groups.
Creating group 'git_daemon' with gid '964'.
==> Creating users
Creating user 'git_daemon' with uid '964'.
[folsom] [9/10] Extracting git-lite-2.19.1: 100%
[folsom] [10/10] Installing zsh-5.6.2...
[folsom] [10/10] Extracting zsh-5.6.2: 100%

```

The PKG sub-command can, of course, do more than just *install*. The expectation is that you can fully leverage the pkg manager. This means, *install*, *update*, *upgrade*, *audit*, *clean*, *autoremove*, etc., etc.

```
ishmael ~ # bastille pkg ALL upgrade
[bastion]:
Updating pkg.bastillebsd.org repository catalogue...
[bastion] Fetching meta.txz: 100% 560 B 0.6kB/s 00:01
[bastion] Fetching packagesite.txz: 100% 118 KiB 121.3kB/s 00:01
Processing entries: 100%
pkg.bastillebsd.org repository update completed. 493 packages processed.
All repositories are up to date.
Checking for upgrades (1 candidates): 100%
Processing candidates (1 candidates): 100%
Checking integrity... done (0 conflicting)
Your packages are up to date.

[unbound0]:
Updating pkg.bastillebsd.org repository catalogue...
[unbound0] Fetching meta.txz: 100% 560 B 0.6kB/s 00:01
[unbound0] Fetching packagesite.txz: 100% 118 KiB 121.3kB/s 00:01
Processing entries: 100%
pkg.bastillebsd.org repository update completed. 493 packages processed.
All repositories are up to date.
Checking for upgrades (0 candidates): 100%
Processing candidates (0 candidates): 100%
Checking integrity... done (0 conflicting)
Your packages are up to date.

[unbound1]:
Updating pkg.bastillebsd.org repository catalogue...
[unbound1] Fetching meta.txz: 100% 560 B 0.6kB/s 00:01
[unbound1] Fetching packagesite.txz: 100% 118 KiB 121.3kB/s 00:01
Processing entries: 100%
pkg.bastillebsd.org repository update completed. 493 packages processed.
All repositories are up to date.
Checking for upgrades (0 candidates): 100%
Processing candidates (0 candidates): 100%
Checking integrity... done (0 conflicting)
Your packages are up to date.

[squid]:
Updating pkg.bastillebsd.org repository catalogue...
[squid] Fetching meta.txz: 100% 560 B 0.6kB/s 00:01
[squid] Fetching packagesite.txz: 100% 118 KiB 121.3kB/s 00:01
Processing entries: 100%
pkg.bastillebsd.org repository update completed. 493 packages processed.
All repositories are up to date.
Checking for upgrades (0 candidates): 100%
Processing candidates (0 candidates): 100%
Checking integrity... done (0 conflicting)
Your packages are up to date.

[nginx]:
Updating pkg.bastillebsd.org repository catalogue...
[nginx] Fetching meta.txz: 100% 560 B 0.6kB/s 00:01
[nginx] Fetching packagesite.txz: 100% 118 KiB 121.3kB/s 00:01
Processing entries: 100%
pkg.bastillebsd.org repository update completed. 493 packages processed.
All repositories are up to date.
Checking for upgrades (1 candidates): 100%
```

(continues on next page)

(continued from previous page)

```
Processing candidates (1 candidates): 100%
The following 1 package(s) will be affected (of 0 checked):

Installed packages to be UPGRADED:
  nginx-lite: 1.14.0_14,2 -> 1.14.1,2

Number of packages to be upgraded: 1

315 KiB to be downloaded.

Proceed with this action? [y/N]: y
[nginx] [1/1] Fetching nginx-lite-1.14.1,2.txz: 100% 315 KiB 322.8kB/s 00:01
Checking integrity... done (0 conflicting)
[nginx] [1/1] Upgrading nginx-lite from 1.14.0_14,2 to 1.14.1,2...
==> Creating groups.
Using existing group 'www'.
==> Creating users
Using existing user 'www'.
[nginx] [1/1] Extracting nginx-lite-1.14.1,2: 100%
You may need to manually remove /usr/local/etc/nginx/nginx.conf if it is no longer
->needed.
```

7.11 restart

To restart a container you can use the *bastille restart* command.

```
ishmael ~ # bastille restart folsom
[folsom]:
folsom: removed

[folsom]:
folsom: created
```

7.12 service

The *service* sub-command allows for managing services within containers. This allows you to start, stop, restart, and otherwise interact with services running inside the containers.

```
ishmael ~ # bastille service web01 'nginx start'
ishmael ~ # bastille service db01 'mysql-server restart'
ishmael ~ # bastille service proxy 'nginx configtest'
ishmael ~ # bastille service proxy 'nginx enable'
ishmael ~ # bastille service proxy 'nginx disable'
ishmael ~ # bastille service proxy 'nginx delete'
```

7.13 start

To start a container you can use the *bastille start* command.

```
ishmael ~ # bastille start folsom
[folsom]:
folsom: created
```

7.14 stop

To stop a container you can use the *bastille stop* command.

```
ishmael ~ # bastille stop folsom
[folsom]:
folsom: removed
```

7.15 sysrc

The *sysrc* sub-command allows for safely editing system configuration files. In container terms, this allows us to toggle on/off services and options at startup.

```
ishmael ~ # bastille sysrc nginx nginx_enable="YES"
[nginx]:
nginx_enable: NO -> YES
```

See *man sysrc(8)* for more info.

7.16 top

This one runs *top* in that container.

```
last pid: 96267; load averages:  0.16,  0.17,  0.11  up 10+22:37:33  21:59:07
8 processes:   1 running,  7 sleeping
CPU:  0.0% user,  0.0% nice,  0.0% system,  0.0% interrupt,  100% idle
Mem:  6768K Active,  323M Inact,  15G Wired,  7891M Free
ARC:  8391M Total,  4004M MFU,  3376M MRU,  64K Anon,  68M Header,  943M Other
      5937M Compressed,  11G Uncompressed,  1.84:1 Ratio
Swap:  2048M Total,  2048M Free
```

PID	USERNAME	THR	PRI	NICE	SIZE	RES	STATE	C	TIME	WCPU	COMMAND
96267	root	1	20	0	7916K	3192K	CPU1	1	0:00	0.01%	top
34907	nobody	1	20	0	11236K	7552K	kqread	6	0:00	0.00%	nginx
36263	nobody	1	20	0	11236K	7552K	kqread	4	0:00	0.00%	nginx
36867	nobody	1	20	0	11236K	7556K	kqread	2	0:00	0.00%	nginx
35024	nobody	1	20	0	11236K	7540K	kqread	6	0:00	0.00%	nginx
40049	root	1	20	0	6464K	2372K	nanslp	4	0:00	0.00%	cron
10201	root	1	20	0	6412K	2368K	select	5	0:00	0.00%	syslogd
34902	root	1	52	0	11236K	6920K	pause	4	0:00	0.00%	nginx

7.17 update

The `update` command targets a release instead of a container. Because every container is based on a release, when the release is updated all the containers are automatically updated as well.

If no updates are available, a message will be shown:

```
ishmael ~ # bastille update 11.2-RELEASE
Looking up update.FreeBSD.org mirrors... 2 mirrors found.
Fetching metadata signature for 11.2-RELEASE from update4.freebsd.org... done.
Fetching metadata index... done.
Inspecting system... done.
Preparing to download files... done.

No updates needed to update system to 11.2-RELEASE-p4.
No updates are available to install.
```

The older the release, however, the more updates will be available:

```
ishmael ~ # bastille update 10.4-RELEASE
Looking up update.FreeBSD.org mirrors... 2 mirrors found.
Fetching metadata signature for 10.4-RELEASE from update1.freebsd.org... done.
Fetching metadata index... done.
Fetching 2 metadata patches.. done.
Applying metadata patches... done.
Fetching 2 metadata files... done.
Inspecting system... done.
Preparing to download files... done.
```

(continues on next page)

(continued from previous page)

```
The following files will be added as part of updating to 10.4-RELEASE-p13:  
...[snip]...
```

To be safe, you may want to restart any containers that have been updated live.

7.18 upgrade

This command lets you upgrade a release to a new release. Depending on the workflow this can be similar to a *bootstrap*.

```
ishmael ~ # bastille upgrade 11.2-RELEASE 12.0-RELEASE
```

7.19 verify

This command scans a bootstrapped release and validates that everything looks in order. This is not a 100% comprehensive check, but it compares the release against a “known good” index.

If you see errors or issues here, consider deleting and re-bootstrapping the release.

```
ishmael ~ # bastille verify 11.2-RELEASE  
Looking up update.FreeBSD.org mirrors... 2 mirrors found.  
Fetching metadata signature for 11.2-RELEASE from update1.freebsd.org... done.  
Fetching metadata index... done.  
Fetching 1 metadata patches. done.  
Applying metadata patches... done.  
Fetching 1 metadata files... done.  
Inspecting system... done.
```

Template

Looking for ready made CI/CD validated [Bastille Templates](<https://gitlab.com/BastilleBSD-Templates/>)?

Bastille supports a templating system allowing you to apply files, pkgs and execute commands inside the containers automatically.

Currently supported template hooks are: *LIMITS*, *INCLUDE*, *PRE*, *FSTAB*, *PKG*, *OVERLAY*, *SYSRC*, *SERVICE*, *CMD*. Planned template hooks include: *PF*, *LOG*.

Templates are created in `/${bastille_prefix}/templates` and can leverage any of the template hooks. Simply create a new directory named after the template. eg;

```
mkdir -p /usr/local/bastille/templates/username/base
```

To leverage a template hook, create an UPPERCASE file in the root of the template directory named after the hook you want to execute. eg;

```
echo "zsh vim-console git-lite htop" > /usr/local/bastille/templates/username/base/PKG
echo "/usr/bin/chsh -s /usr/local/bin/zsh" > /usr/local/bastille/templates/username/
↳base/CMD
echo "usr" > /usr/local/bastille/templates/username/base/OVERLAY
```

Template hooks are executed in specific order and require specific syntax to work as expected. This table outlines those requirements:

HOOK	format	example
LIMITS	resource value	memoryuse 1G
INCLUDE	template path/URL	http?://TEMPLATE_URL or project/path
PRE	/bin/sh command	mkdir -p /usr/local/my_app/html
FSTAB	fstab syntax	/host/path container/path nullfs ro 0 0
PKG	port/pkg name(s)	vim-console zsh git-lite tree htop
OVERLAY	path(s)	etc root usr (one per line)
SYSRC	sysrc command(s)	nginx_enable=YES
SERVICE	service command	'nginx start' OR 'postfix reload'
CMD	/bin/sh command	/usr/bin/chsh -s /usr/local/bin/zsh

Note: SYSRC requires that NO quotes be used or that quotes (“) be escaped ie; (“)

In addition to supporting template hooks, Bastille supports overlaying files into the container. This is done by placing the files in their full path, using the template directory as “/”.

An example here may help. Think of *bastille/templates/username/base*, our example template, as the root of our filesystem overlay. If you create an *etc/hosts* or *etc/resolv.conf* inside the base template directory, these can be overlaid into your container.

Note: due to the way FreeBSD segregates user-space, the majority of your overlaid template files will be in *usr/local*. The few general exceptions are the *etc/hosts*, *etc/resolv.conf*, and *etc/rc.conf.local*.

After populating *usr/local* with custom config files that your container will use, be sure to include *usr* in the template OVERLAY definition. eg;

```
echo "usr" > /usr/local/bastille/templates/username/base/OVERLAY
```

The above example “usr” will include anything under “usr” inside the template. You do not need to list individual files. Just include the top-level directory name. List these top-level directories one per line.

8.1 Applying Templates

Containers must be running to apply templates.

Bastille includes a *template* command. This command requires a target and a template name. As covered in the previous section, template names correspond to directory names in the *bastille/templates* directory.

```
ishmael ~ # bastille template ALL username/base
[proxy01]:
Copying files...
Copy complete.
Installing packages.
pkg already bootstrapped at /usr/local/sbin/pkg
vulnxml file up-to-date
0 problem(s) in the installed packages found.
Updating bastillebsd.org repository catalogue...
[cdn] Fetching meta.txz: 100%   560 B   0.6kB/s   00:01
[cdn] Fetching packagesite.txz: 100%  121 KiB 124.3kB/s   00:01
Processing entries: 100%
bastillebsd.org repository update completed. 499 packages processed.
All repositories are up to date.
Checking integrity... done (0 conflicting)
The most recent version of packages are already installed
Updating services.
cron_flags: -J 60 -> -J 60
sendmail_enable: NONE -> NONE
syslogd_flags: -ss -> -ss
Executing final command(s).
chsh: user information updated
Template Complete.

[web01]:
Copying files...
Copy complete.
Installing packages.
pkg already bootstrapped at /usr/local/sbin/pkg
vulnxml file up-to-date
```

(continues on next page)

(continued from previous page)

```
0 problem(s) in the installed packages found.
Updating pkg.bastillebsd.org repository catalogue...
[poudriere] Fetching meta.txz: 100%   560 B   0.6kB/s   00:01
[poudriere] Fetching packagesite.txz: 100% 121 KiB 124.3kB/s   00:01
Processing entries: 100%
pkg.bastillebsd.org repository update completed. 499 packages processed.
Updating bastillebsd.org repository catalogue...
[poudriere] Fetching meta.txz: 100%   560 B   0.6kB/s   00:01
[poudriere] Fetching packagesite.txz: 100% 121 KiB 124.3kB/s   00:01
Processing entries: 100%
bastillebsd.org repository update completed. 499 packages processed.
All repositories are up to date.
Checking integrity... done (0 conflicting)
The most recent version of packages are already installed
Updating services.
cron_flags: -J 60 -> -J 60
sendmail_enable: NONE -> NONE
syslogd_flags: -ss -> -ss
Executing final command(s).
chsh: user information updated
Template Complete.
```

Note: FreeBSD introduced container technology twenty years ago, long before the industry standardized on the term “container”. Internally, FreeBSD refers to these containers as “jails”.

In this section we'll look at the default config for a new container. The defaults are sane for most applications, but if you want to tweak the settings here they are.

A *jail.conf* template is used each time a new container is created. This template looks like this:

```
{name} {
    devfs_ruleset = 4;
    enforce_statfs = 2;
    exec.clean;
    exec.consolelog = /usr/local/bastille/logs/{name}_console.log;
    exec.start = '/bin/sh /etc/rc';
    exec.stop = '/bin/sh /etc/rc.shutdown';
    host.hostname = {name};
    interface = {interface};
    mount.devfs;
    mount.fstab = /usr/local/bastille/jails/{name}/fstab;
    path = /usr/local/bastille/jails/{name}/root;
    securelevel = 2;

    ip4.addr = x.x.x.x;
    ip6 = disable;
}
```

9.1 devfs_ruleset

devfs_ruleset

The number of the devfs ruleset that is enforced for mounting devfs in this jail. A value of zero (default) means no ruleset is enforced. Descendant jails inherit the parent jail's devfs ruleset enforcement. Mounting devfs inside a jail is possible only if the `allow.mount` and `allow.mount.devfs` permissions are effective and `enforce_statfs` is set to a value lower than 2.

(continues on next page)

(continued from previous page)

Devfs rules and rulesets cannot be viewed or modified from inside a jail.

NOTE: It is important that only appropriate device nodes in devfs be exposed to a jail; access to disk devices in the jail may permit processes in the jail to bypass the jail sandboxing by modifying files outside of the jail. See devfs(8) for information on how to use devfs rules to limit access to entries in the per-jail devfs. A simple devfs ruleset for jails is available as ruleset #4 in /etc/defaults/devfs.rules.

9.2 enforce_statfs

enforce_statfs

This determines what information processes in a jail are able to get about mount points. It affects the behaviour of the following syscalls: statfs(2), fstatfs(2), getfsstat(2), and fhstatfs(2) (as well as similar compatibility syscalls). When set to 0, all mount points are available without any restrictions. When set to 1, only mount points below the jail's chroot directory are visible. In addition to that, the path to the jail's chroot directory is removed from the front of their pathnames. When set to 2 (default), above syscalls can operate only on a mount-point where the jail's chroot directory is located.

9.3 exec.clean

exec.clean

Run commands in a clean environment. The environment is discarded except for HOME, SHELL, TERM and USER. HOME and SHELL are set to the target login's default values. USER is set to the target login. TERM is imported from the current environment. The environment variables from the login class capability database for the target login are also set.

9.4 exec.consolelog

exec.consolelog

A file to direct `command` output (stdout and stderr) to.

9.5 exec.start

exec.start

Command(s) to run in the jail environment when a jail is created. A typical `command` to run is `"sh /etc/rc"`.

9.6 exec.stop

```
exec.stop
Command(s) to run in the jail environment before a jail is
removed, and after any exec.prestop commands have completed. A
typical command to run is "sh /etc/rc.shutdown".
```

9.7 host.hostname

```
host.hostname
The hostname of the jail. Other similar parameters are
host.domainname, host.hostuuid and host.hostid.
```

9.8 interface

```
interface
A network interface to add the jail's IP addresses (ip4.addr and
ip6.addr) to. An alias for each address will be added to the
interface before the jail is created, and will be removed from
the interface after the jail is removed.
```

9.9 mount.devfs

```
mount.devfs
Mount a devfs(5) filesystem on the chrooted /dev directory, and
apply the ruleset in the devfs_ruleset parameter (or a default of
ruleset 4: devfsrules_jail) to restrict the devices visible
inside the jail.
```

9.10 mount.fstab

```
mount.fstab
An fstab(5) format file containing filesystems to mount before
creating a jail.
```

9.11 path

```
path
The directory which is to be the root of the jail. Any commands
run inside the jail, either by jail or from jexec(8), are run
from this directory.
```

9.12 securelevel

By default, Bastille containers run at *securelevel* = 2;. See below for the implications of kernel security levels and when they might be altered.

Note: Bastille does not currently have any mechanism to automatically change *securelevel* settings. My recommendation is this only be altered manually on a case-by-case basis and that “Highly secure mode” is a sane default for most use cases.

The kernel runs with five different security levels. Any super-user process can raise the level, but no process can lower it. The security levels are:

- 1 Permanently insecure mode - always run the system in insecure mode. This is the default initial value.
- 0 Insecure mode - immutable and append-only flags may be turned off. All devices may be read or written subject to their permissions.
- 1 Secure mode - the system immutable and system append-only flags may not be turned off; disks for mounted file systems, /dev/mem and /dev/kmem may not be opened for writing; /dev/io (if your platform has it) may not be opened at all; kernel modules (see *kld(4)*) may not be loaded or unloaded. The kernel debugger may not be entered using the *debug.kdb.enter sysctl*. A panic or trap cannot be forced using the *debug.kdb.panic* and other *sysctl*'s.
- 2 Highly secure mode - same as secure mode, plus disks may not be opened for writing (except by *mount(2)*) whether mounted or not. This level precludes tampering with file systems by unmounting them, but also inhibits running *newfs(8)* while the system is multi-user.

In addition, kernel time changes are restricted to less than or equal to one second. Attempts to change the time by more than this will log the message "Time adjustment clamped to +1 second".
- 3 Network secure mode - same as highly secure mode, plus IP packet filter rules (see *ipfw(8)*, *ipfirewall(4)* and *pfctl(8)*) cannot be changed and *dummynet(4)* or *pf(4)* configuration cannot be adjusted.

CHAPTER 10

Copyright

This content is copyright Christer Edwards. All rights reserved.

Duplication of this content without the express written permission of the author is not permitted.

Note: this documentation is included with the source code in *docs*.