
kmos Documentation

Release 0.3.21

Max J. Hoffmann

Nov 29, 2017

1	Tutorials	3
1.1	Installation	3
1.2	Screenshots	11
1.3	A first kMC Model—the API way	11
1.4	Running the Model—the GUI way	15
1.5	How To Prepare a Model and Run It Interactively	15
1.6	Running the Model—the API way	16
1.7	Generate Grids of Sampled Data	18
1.8	Manipulating the Model at Runtime	18
1.9	Running models in parallel	18
1.10	Development	19
2	Topic Guides	21
2.1	The Concept of Kinetic Monte Carlo	21
2.2	Modelling Workflows	23
2.3	The kmos data model	24
2.4	How the kmos kMC algorithm works	24
2.5	The otf Backend	27
2.6	The Process Syntax	30
2.7	The Site/Coordinate Syntax	32
3	Reference	35
3.1	Command Line Interface (CLI)	35
3.2	Data Types	36
3.3	Editor frontend	41
3.4	Runtime frontend	41
3.5	kmos kMC project DTD	48
3.6	Backends	50
4	Trouble Shooting	81
5	Frequently Asked Questions	83
	Python Module Index	85




Fig. 1: Things you can do with kmos.

kmos is a vigorous attempt to make (lattice) kMC modelling more accessible.

kmos is designed for and by kMC model developers. As of this writing there is no standardized way to develop kMC models, thus there is no standardized way to use kmos. kmos can be an Editor, an API, a viewer. However all in all kmos wants to save time filled with repetitive labor and enlarge your stride.

Not sure how to begin? Start with the [API tutorial](#).

1.1 Installation

1.1.1 Introduction

Feature overview

With *kmos* you can:

- easily create and modify kMC models through GUI
- store and exchange kMC models through XML
- generate fast, platform independent, self-contained code¹
- run kMC models through GUI or python bindings

kmos has been developed in the context of first-principles based modelling of surface chemical reactions but might be of help for other types of kMC models as well.

kmos' goal is to significantly reduce the time you need to implement and run a lattice kmc simulation. However it can not help you plan the model.

kmos can be invoked directly from the command line in one of the following ways:

```
kmos [help] (all|benchmark|build|edit|export|help|import|rebuild|run|settings-  
↪export|shell|version|view|xml) [options]
```

or it may be used as an API via the *kmos* module.

1.1.2 Installation on Ubuntu Linux

You can fetch the current version of *kmos* using *git*

```
git clone http://www.github.com/mhoffman/kmos
```

and install it using *setuptools*

¹ The source code is generated in Fortran90, written in a modular fashion. Python bindings are generated using *f2py*.

```
cd kmos/  
./setup.py install [--user]
```

To use the core functionality (programmatic model setup, code generation, model execution) kmos has a fairly modest dependency foot-print. You will need

```
python-numpy, a Fortran compiler, python-lxml
```

In order to watch the model run on screen you will additionally need

```
python-matplotlib, python-ase
```

Finally in order to use all features, in particular the GUI model editor of kmos you have to install a number of dependencies. This should not be very difficult on a recent Linux distribution with package management. So on Ubuntu it suffices to call:

```
sudo apt-get install gfortran python-dev python-pip \  
python-glade2 python-kiwi python-pygoocanvas
```

Unfortunately Debian/Ubuntu have discontinued maintaining the *gazpacho* package which I find very unfortunate since it eased gtk GUI building a lot and I haven't found a simple transition path (simple as in one reliable conversion script and two changed import lines) towards gtkbuilder. *Gazpacho* itself depends on *python-support* which is not maintained by Debian/Ubuntu anymore, too. Therefore for the moment I can only suggest to fetch the latest *python-support* and the latest *gazpacho* package and install it manually with:

```
wget http://ftp.de.debian.org/debian/pool/main/p/python-support/python-support_1.0.  
↳15_all.deb  
wget https://gist.github.com/mhoffman/d2a9466c22f33a9e046b/raw/  
↳4c73c5029f3c01e656f161c7459f720aff331705/gazpacho_0.7.2-3_all.deb  
sudo dpkg -i python-support*.deb  
sudo dpkg -i gazpacho_*.deb
```

The remaining python dependencies are installed with pip:

```
pip install -r requirements.txt
```

To ease the installation of requirements on Ubuntu one can simply run (this is tested with clean installations of *Ubuntu 16.04.3 LTS* and *Ubuntu 17.04*):

```
./tools/kmos-install-dependencies-ubuntu.sh
```

If you plan to use a specific branch (for example *develop*) perform a *git checkout* and run *setuptools* again:

```
git checkout develop  
./setup.py install [--user]
```

If you think this dependency list hurts. Yes, it does! And I am happy about any suggestions how to minimize it. However one should note these dependencies are only required for the model development. Running a model has virtually no dependencies except for a Fortran compiler.

1.1.3 Installation on openSUSE 12.1 Linux

On a recent openSUSE some dependencies are distributed a little different but nevertheless doable. We start by install some package from the repositories

```
sudo zypper install libgfortran46, python-lxml, python-matplotlib, \  
python-numpy, python-numpy-devel, python-goocanvas,  
python-imaging
```

And two more packages SUSE packages have to be fetched from the openSUSE [build service](#)

- [gaspacho](#)
- [python-kiwi](#)

For each one just download the *.tar.bz2 files. Unpack them and inside run

```
python setup.py install
```

In the same vein you can install ASE. Download a recent version from the [GitLab website](#) unzip it and install it with

```
python setup.py install
```

1.1.4 Installation on openSUSE 13.1 Linux

In order to use the editor GUI you will want to install python-kiwi (not KIWI) and right now you can find a recent build [here](#) .

1.1.5 Installation on Mac OS X 10.10 or above

There is more than one way to get required dependencies. I have tested MacPorts and worked quite well.

1. **Get MacPorts** Search for MacPorts online, you'll need to install Xcode in the process
2. Install Python, lxml, numpy, ipython, ASE, gcc48. I assume you are using Python 2.7. kmos has not been thoroughly tested with Python 3.X, yet, but should not be too hard.

Having MacPorts this can be as simple as

```
sudo port install -v py27-ipython
sudo port select --set ipython py27-ipython

sudo port install gcc48
sudo port select --set gcc mp-gcc48 # need to that f2py finds a
↳ compiler

sudo port install py27-readline
sudo port install py27-goocanvas
sudo port install py27-lxml
sudo port install kiwi
# possibly more ...

# if you install these package manually, skip pip :-)
sudo port install py27-pip
sudo port select --set pip pip27

pip install python-ase --user
pip install python-kmos --user
```

1.1.6 Installation on windoze 7

In order for kmos to work in a recent windoze we need a number of programs.

1. **Python** If you have no python previously installed you should try [Enthought Python Distribution \(EPD\)](#) in its free version since it already comes with a number of useful libraries such a numpy, scipy, ipython and matplotlib.

Otherwise you can simply download Python from [python.org](#) and this installation has been successfully tested using python 2.7.

2. **numpy** Fetch it for *your version* of python from [sourceforge's Numpy site](#) and install it. [Not needed with EPD]
3. **MinGW** provides free Fortran and C compilers and can be obtained from the [sourceforge's MinGW site](#) . Make sure you make a tick for the Fortran and the C compiler.
4. **pyGTK** is needed for the GUI frontend so fetch the [all-in-one](#) bundle installer and install most of it.
5. **lxml** is an awesome library to process xml files, which has unfortunately not fully found its way into the standard library. As of this writing the latest version with prebuilt binaries is [lxml 2.2.8](#) and installation works without troubles.
6. **ASE** is needed for the representation of atoms in the frontend. So download the latest from the [GitLab website](#) and install it. This has to be installed using e.g. the powershell. So after unpacking it, fire up the powershell, cd to the directory and run

```
python setup.py install
```

in there. Note that there is currently a slight glitch in the *setup.py* script on windoze, so open *setup.py* in a text editor and find the line saying

```
version = ...
```

comment out the lines above it and hard-code the current version number.

7. **kmos** is finally what we are after, so download the latest version from [github](#) and install it in the same way as you installed **ASE**.

There are probably a number of small changes you have to make which are not described in this document. Please post questions and comments in the [issues forum](#) .

1.1.7 Installing JANAF Thermochemical Tables

You can conveniently use gas phase chemical potentials inserted in rate constant expressions using JANAF Thermochemical Tables. A couple of molecules are automatically supported. If you need support for more gas-phase species, drop me a line.

The tabulated values are not distributed since the terms of distribution do not permit this. Fortunately manual installation is easy. Just create a directory called *janaf_data* anywhere on your python path. To see the directories on your python path run

```
python -c"import sys; print(sys.path)"
```

Inside the *janaf_data* directory has to be a file named *__init__.py*, so that python recognizes it as a module

```
touch __init__.py
```

Then copy all needed data files from the [NIST website](#) in the tab-delimited text format to the *janaf_data* directory. To download the ASCII file, search for your molecule. In the results page click on 'view' under 'JANAF Table' and click on 'Download table in tab-delimited text format.' at the bottom of that page.

Todo

test installation on other platforms

The screenshot displays the kmos software interface. On the left, a vertical menu contains options: New, Add Lattice, Add Species, Add Parameter, Add Process, Open, Save, Save As, Export Source, Help, and Quit. The main window shows a lattice of atoms (teal and red spheres) with a black box highlighting a specific site. The right panel is a table with columns 'Name' and 'Info'.

Name	Info
ruo2	visible
Parameters	
A	20.0616*angstrom**2
E_CO_bridge	-1.6
E_CO_cus	-1.3
E_CODiff_bridge_bridge	0.6
E_CODiff_bridge_cus	1.6
E_CODiff_cus_bridge	1.3
E_CODiff_cus_cus	1.7
E_O_bridge	-2.3
E_O_cus	-1.0
E_Odiff_bridge_bridge	0.7
E_Odiff_bridge_cus	2.3
E_Odiff_cus_bridge	1.0
E_Odiff_cus_cus	1.6
E_react_Obridge_CObridge	1.5
E_react_Obridge_COcus	0.8
E_react_Ocus_CObridge	1.2
E_react_Ocus_COcus	0.9
T	450
p_COgas	1
p_O2gas	1
Processes	
CO_adsorption_bridge	$p_{COgas} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{CO} / \beta}$
CO_adsorption_cus	$p_{COgas} \cdot \bar{A} / 2 \cdot \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{CO} / \beta}$
CO_desorption_bridge	$p_{COgas} \cdot \bar{A} / 2 \cdot \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{CO} / \beta} \cdot \exp(\beta \cdot (E_{CO_bridge} - E_{CO_cus}))$
CO_desorption_cus	$p_{COgas} \cdot \bar{A} / 2 \cdot \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{CO} / \beta} \cdot \exp(\beta \cdot (E_{CO_cus} - E_{CO_bridge}))$
CODiff_bridge_down	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{CODiff_bridge_bridge} - E_{CODiff_bridge_cus}))$
CODiff_bridge_left	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{CODiff_bridge_cus} - E_{CODiff_bridge_bridge}))$
CODiff_bridge_right	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{CODiff_bridge_cus} - E_{CODiff_bridge_bridge}))$
CODiff_bridge_up	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{CODiff_bridge_bridge} - E_{CODiff_bridge_cus}))$
CODiff_cus_down	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{CODiff_cus_cus} - E_{CODiff_cus_bridge}))$
CODiff_cus_left	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{CODiff_cus_bridge} - E_{CODiff_cus_cus}))$
CODiff_cus_right	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{CODiff_cus_bridge} - E_{CODiff_cus_cus}))$
CODiff_cus_up	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{CODiff_cus_cus} - E_{CODiff_cus_bridge}))$
O2_adsorption_bridge_right	$p_{O2gas} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{O2} / \beta}$
O2_adsorption_bridge_up	$p_{O2gas} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{O2} / \beta}$
O2_adsorption_cus_right	$p_{O2gas} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{O2} / \beta}$
O2_adsorption_cus_up	$p_{O2gas} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{O2} / \beta}$
O2_desorption_bridge_right	$p_{O2gas} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{O2} / \beta} \cdot \exp(\beta \cdot (E_{O_bridge_right} - E_{O_cus_right}))$
O2_desorption_bridge_up	$p_{O2gas} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{O2} / \beta} \cdot \exp(\beta \cdot (E_{O_bridge_up} - E_{O_cus_up}))$
O2_desorption_cus_right	$p_{O2gas} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{O2} / \beta} \cdot \exp(\beta \cdot (E_{O_cus_right} - E_{O_cus_up}))$
O2_desorption_cus_up	$p_{O2gas} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{mass} \cdot m_{O2} / \beta} \cdot \exp(\beta \cdot (E_{O_cus_up} - E_{O_cus_right}))$
Odiff_bridge_down	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{Odiff_bridge_bridge} - E_{Odiff_bridge_cus}))$
Odiff_bridge_left	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{Odiff_bridge_cus} - E_{Odiff_bridge_bridge}))$

Fig. 1.1: The lattice view allows to define sites by simple pointing.




Fig. 1.2: Model parameters can be defined including ranges to vary them over in the runtime viewer.

The screenshot shows the kmos software interface. On the left, there is a menu bar with 'File', 'Edit', 'Insert', and 'Help'. Below it is a vertical toolbar with buttons for 'New', 'Add Lattice', 'Add Species', 'Add Parameter', 'Add Process', 'Open', 'Save', 'Save As', 'Export Source', 'Help', and 'Quit'. The main area is divided into three sections:

- Name:** A text input field containing 'CO'.
- Color:** A color selection box with a black swatch.
- Representation:** A text input field containing the ASE atoms constructor string: `Atoms('CO',[0,0,0],[0,0,1.2])`.

On the right side, there is a table with two columns: 'Name' and 'Info'. The table lists various processes and their corresponding information. The 'Processes' section is expanded, showing a list of processes and their formulas. The 'Species' section is also expanded, showing a list of species.

Name	Info
E_react_Obridge_CObridge	1.5
E_react_Obridge_COcus	0.8
E_react_OCus_CObridge	1.2
E_react_OCus_COcus	0.9
T	450
p_COgas	1
p_O2gas	1
Processes	
CO_adsorption_bridge	$p_{\text{COgas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{CO}} / \beta}$
CO_adsorption_cus	$p_{\text{COgas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{CO}} / \beta}$
CO_desorption_bridge	$p_{\text{COgas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{CO}} / \beta} \cdot \exp(\beta \cdot (E_{\text{CO_bridge}} - E_{\text{CO_cus}}))$
CO_desorption_cus	$p_{\text{COgas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{CO}} / \beta} \cdot \exp(\beta \cdot (E_{\text{CO_cus}} - E_{\text{CO_bridge}}))$
Codiff_bridge_down	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Codiff_bridge_bridge}} - E_{\text{Codiff_bridge_cus}}))$
Codiff_bridge_left	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Codiff_bridge_cus}} - E_{\text{Codiff_bridge_bridge}}))$
Codiff_bridge_right	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Codiff_bridge_bridge}} - E_{\text{Codiff_bridge_cus}}))$
Codiff_bridge_up	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Codiff_bridge_bridge}} - E_{\text{Codiff_bridge_cus}}))$
Codiff_cus_down	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Codiff_cus_cus}} - E_{\text{Codiff_cus_bridge}}))$
Codiff_cus_left	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Codiff_cus_bridge}} - E_{\text{Codiff_cus_cus}}))$
Codiff_cus_right	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Codiff_cus_bridge}} - E_{\text{Codiff_cus_cus}}))$
Codiff_cus_up	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Codiff_cus_cus}} - E_{\text{Codiff_cus_bridge}}))$
O2_adsorption_bridge_right	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta}$
O2_adsorption_bridge_up	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta}$
O2_adsorption_cus_right	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta}$
O2_adsorption_cus_up	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta}$
O2_desorption_bridge_right	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta} \cdot \exp(\beta \cdot (E_{\text{O_bridge_right}} - E_{\text{O_cus_right}}))$
O2_desorption_bridge_up	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta} \cdot \exp(\beta \cdot (E_{\text{O_bridge_up}} - E_{\text{O_cus_up}}))$
O2_desorption_cus_right	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta} \cdot \exp(\beta \cdot (E_{\text{O_cus_right}} - E_{\text{O_bridge_right}}))$
O2_desorption_cus_up	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta} \cdot \exp(\beta \cdot (E_{\text{O_cus_up}} - E_{\text{O_bridge_up}}))$
Odiff_bridge_down	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_bridge_bridge}} - E_{\text{Odiff_bridge_cus}}))$
Odiff_bridge_left	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_bridge_cus}} - E_{\text{Odiff_bridge_bridge}}))$
Odiff_bridge_right	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_bridge_bridge}} - E_{\text{Odiff_bridge_cus}}))$
Odiff_bridge_up	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_bridge_bridge}} - E_{\text{Odiff_bridge_cus}}))$
Odiff_cus_down	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_cus_cus}} - E_{\text{Odiff_cus_bridge}}))$
Odiff_cus_left	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_cus_bridge}} - E_{\text{Odiff_cus_cus}}))$
Odiff_cus_right	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_cus_bridge}} - E_{\text{Odiff_cus_cus}}))$
Odiff_cus_up	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_cus_cus}} - E_{\text{Odiff_cus_bridge}}))$
React_bridge_down	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot E_{\text{react_Obridge_CObridge}})$
React_bridge_left	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot E_{\text{react_Obridge_COcus}})$
React_bridge_right	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot E_{\text{react_Obridge_COcus}})$
React_bridge_up	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot E_{\text{react_Obridge_CObridge}})$
React_cus_down	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot E_{\text{react_OCus_COcus}})$
React_cus_left	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot E_{\text{react_OCus_CObridge}})$
React_cus_right	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot E_{\text{react_OCus_CObridge}})$
React_cus_up	$(\beta \cdot h)^{-1} \cdot \exp(-\beta \cdot E_{\text{react_OCus_COcus}})$
Species	
CO	
O	
empty	

Fig. 1.3: Species can be added here. The color is used to represent them in the 2D editor view. The string is an ASE atoms constructor for display at runtime.

The screenshot displays the kmos software interface. On the left, a menu bar includes 'File', 'Edit', 'Insert', and 'Help'. Below it, a 'New' button is active, and the 'Name' field contains 'COdiff_cus_right'. The 'Chemical expression' field is set to 'CO@cus + empty@bridge -> empty@cus + CO@bridge', and the 'Rate expression' field contains ' $\beta a^h \cdot (-1) \cdot \exp(-\beta \cdot (E_{\text{COdiff_cus_bridge}}) \cdot eV)$ '. The main workspace is divided into a 'Reservoir Area' (top) and a 'Lattice Area' (bottom), both showing a grid of points. The 'Reservoir Area' has three colored circles (black, red, white) and the 'Lattice Area' has two white circles. On the right, a table lists various processes and their associated info.

Name	Info
E_react_Obridge_CObridge	1.5
E_react_Obridge_COcus	0.8
E_react_Ocus_CObridge	1.2
E_react_Ocus_COcus	0.9
T	450
p_COgas	1
p_O2gas	1
Processes	
CO_adsorption_bridge	$p_{\text{COgas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{CO}} / \beta$
CO_adsorption_cus	$p_{\text{COgas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{CO}} / \beta$
CO_desorption_bridge	$p_{\text{COgas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{CO}} / \beta \cdot \exp(\beta \cdot (E_{\text{CO_bridge}})) \cdot eV$
CO_desorption_cus	$p_{\text{COgas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{CO}} / \beta \cdot \exp(\beta \cdot (E_{\text{CO_cus}})) \cdot eV$
COdiff_bridge_down	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{COdiff_bridge_bridge}})) \cdot eV$
COdiff_bridge_left	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{COdiff_bridge_cus}})) \cdot eV$
COdiff_bridge_right	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{COdiff_bridge_cus}})) \cdot eV$
COdiff_bridge_up	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{COdiff_bridge_bridge}})) \cdot eV$
COdiff_cus_down	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{COdiff_cus_cus}})) \cdot eV$
COdiff_cus_left	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{COdiff_cus_bridge}})) \cdot eV$
COdiff_cus_right	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{COdiff_cus_bridge}})) \cdot eV$
COdiff_cus_up	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{COdiff_cus_cus}})) \cdot eV$
O2_adsorption_bridge_right	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta$
O2_adsorption_bridge_up	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta$
O2_adsorption_cus_right	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta$
O2_adsorption_cus_up	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta$
O2_desorption_bridge_right	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta \cdot \exp(\beta \cdot (E_{\text{O_bridge}})) \cdot eV$
O2_desorption_bridge_up	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta \cdot \exp(\beta \cdot (2 \cdot E_{\text{O_bridge}})) \cdot eV$
O2_desorption_cus_right	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta \cdot \exp(\beta \cdot (E_{\text{O_cus}})) \cdot eV$
O2_desorption_cus_up	$p_{\text{O2gas}} \cdot \bar{A} / \sqrt{2 \cdot \pi} \cdot u_{\text{mass}} \cdot m_{\text{O2}} / \beta \cdot \exp(\beta \cdot (2 \cdot E_{\text{O_cus}})) \cdot eV$
Odiff_bridge_down	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_bridge_bridge}})) \cdot eV$
Odiff_bridge_left	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_bridge_cus}})) \cdot eV$
Odiff_bridge_right	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_bridge_cus}})) \cdot eV$
Odiff_bridge_up	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_bridge_bridge}})) \cdot eV$
Odiff_cus_down	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_cus_cus}})) \cdot eV$
Odiff_cus_left	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_cus_bridge}})) \cdot eV$
Odiff_cus_right	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_cus_bridge}})) \cdot eV$
Odiff_cus_up	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{Odiff_cus_cus}})) \cdot eV$
React_bridge_down	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{react_Obridge_CObridge}})) \cdot eV$
React_bridge_left	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{react_Obridge_COcus}})) \cdot eV$
React_bridge_right	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{react_Obridge_COcus}})) \cdot eV$
React_bridge_up	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{react_Obridge_CObridge}})) \cdot eV$
React_cus_down	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{react_Ocus_COcus}})) \cdot eV$
React_cus_left	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{react_Ocus_CObridge}})) \cdot eV$
React_cus_right	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{react_Ocus_CObridge}})) \cdot eV$
React_cus_up	$(\beta \cdot a^h)^{-1} \cdot \exp(-\beta \cdot (E_{\text{react_Ocus_COcus}})) \cdot eV$
Species	
CO	
O	
empty	

Fig. 1.4: Processes can be added by point and click or by entering a chemical expression.

1.2 Screenshots

1.2.1 The Editor

1.2.2 The Runtime View




Fig. 1.5: The compiled module can be run and watched in realtime. When parameters are changed this is immediately reflected in the rate constants.

1.3 A first kMC Model—the API way

In general there are two interfaces to *defining* a new model: A GUI and an API. While the GUI can be quite nice especially for beginners, it turns out that the API is better maintained simply because ... well, maintaining a GUI is a lot more work.

So we will start by learning how to setup the model using the API which will turn out not to be hard at all. It is knowing how to do this will also pay-off especially if you starting tinkering with your existing models and make little changes here and there.

1.3.1 Construct the model

We start by making the necessary import statements (in `*python*` or better `*ipython*`):

```
from kmos.types import *
from kmos.io import *
import numpy as np
```

which imports all classes that make up a kMC project. The functions from `kmos.io` will only be needed at the end to save the project or to export compilable code.

The example sketched out here leads you to a kMC model for CO adsorption and desorption on Pd(100) including a simple lateral interaction. Granted this hardly excites surface scientists but we need to start somewhere, right?

First you should instantiate a new project and fill in meta information

```
pt = Project()
pt.set_meta(author = 'Your Name',
            email = 'your.name@server.com',
            model_name = 'MyFirstModel',
            model_dimension = 2,)
```

Next you add some species or states. Note that whichever species you add first is the default species with which all sites in the system will be initialized. Of course this can be changed later

For surface science simulations it is useful to define an *empty* state, so we add

```
pt.add_species(name='empty')
```

and some surface species. Given you want to simulate CO adsorption and desorption on a single crystal surface you would say

```
pt.add_species(name='CO',
               representation="Atoms('CO', [[0,0,0], [0,0,1.2]])")
```

where the string passed as *representation* is a string representing a CO molecule which can be evaluated in `ASE` namespace.

Once you have all species declared is a good time to think about the geometry. To keep it simple we will stick with a simple-cubic lattice in 2D which could for example represent the (100) surface of a fcc crystal with only one adsorption site per unit cell. You start by giving your layer a name

```
layer = pt.add_layer(name='simple_cubic')
```

and adding a site

```
layer.sites.append(Site(name='hollow', pos='0.5 0.5 0.5',
                       default_species='empty'))
```

Where *pos* is given in fractional coordinates, so this site will be in the center of the unit cell.

Simple, huh? Now you wonder where all the rest of the geometry went? For a simple reason: the geometric location of a site is meaningless from a kMC point of view. In order to solve the master equation none of the numerical coordinates of any lattice sites matter since the master equation is only defined in terms of states and transition between these. However to allow a graphical representation of the simulation one can add geometry as you have already done for the site. You set the size of the unit cell via

```
pt.lattice.cell = np.diag([3.5, 3.5, 10])
```

which are prototypical dimensions for a single-crystal surface in Angstrom.

Ok, let us see what we managed so far: you have a *lattice* with a *site* that can be either *empty* or occupied with *CO*.

1.3.2 Populate process list and parameter list

The remaining work is to populate the *process list* and the *parameter list*. The parameter list defines the parameters that can be used in the expressions of the rate constants. In principle one could do without the parameter list and simply hard code all parameters in the process list, however one loses some nifty functionality like easily changing parameters on-the-fly or even interactively.

A second benefit is that you achieve a clear separation of the kinetic model from the barrier input, which usually has a different origin.

In practice filling the parameter list and the process list is often an iterative process, however since we have a fairly short list, we can try to set all parameters at once.

First of all you want to define the external parameters to which our model is coupled. Here we use the temperature and the CO partial pressure:

```
pt.add_parameter(name='T', value=600., adjustable=True, min=400, max=800)
pt.add_parameter(name='p_CO', value=1., adjustable=True, min=1e-10, max=1.e2)
```

You can also set a default value and a minimum and maximum value set defines how the scrollbars behave later in the runtime GUI.

To describe the adsorption rate constant you will need the area of the unit cell:

```
pt.add_parameter(name='A', value='(3.5*angstrom)**2')
```

Last but not least you need a binding energy of the particle on the surface. Since without further ado we have no value for the gas phase chemical potential, we'll just call it deltaG and keep it adjustable

```
pt.add_parameter(name='deltaG', value='-0.5', adjustable=True,
                 min=-1.3, max=0.3)
```

To define processes we first need a coordinate³

```
coord = pt.lattice.generate_coord('hollow.(0,0,0).simple_cubic')
```

Then you need to have at least two processes. A process or elementary step in kMC means that a certain local configuration must be given so that something can happen at a certain rate constant. In the framework here this is phrased in terms of 'conditions' and 'actions'.² So for example an adsorption requires at least one site to be empty (condition). Then this site can be occupied by CO (action) with a rate constant. Written down in code this looks as follows

```
pt.add_process(name='CO_adsorption',
              conditions=[Condition(coord=coord, species='empty')],
              actions=[Action(coord=coord, species='CO')],
              rate_constant='p_CO*bar*A/sqrt(2*pi*umass*m_CO/beta)')
```

Note: In order to ensure correct functioning of the kmos kMC solver every action should have a corresponding condition for the same coordinate.

³ The description of coordinates follows the simple syntax of the coordinate syntax and the *topic guide* explains how that works.

² You will have to describe all processes in terms of *conditions* and *actions* and you find a more complete description in the *topic guide* to the process description syntax.

Now you might wonder, how come we can simply use `m_CO` and `beta` and such. Well, that is because the evaluator will do some trickery to resolve such terms. So `beta` will be first be translated into $1/(k_{\text{boltzmann}}*T)$ and as long as you have set a parameter T before, this will go through. Same is true for `m_CO`, here the atomic masses are looked up and added. Note that we need conversion factors of `bar` and `umass`.

Then the desorption process is almost the same, except the reverse:

```
pt.add_process(name='CO_desorption',
               conditions=[Condition(coord=coord, species='CO')],
               actions=[Action(coord=coord, species='empty')],
               rate_constant='p_CO*bar*A/sqrt(2*pi*umass*m_CO/
↪beta)*exp(beta*deltaG*eV)')
```

To reduce typing, kmos also knows a shorthand notation for processes. In order to produce the same process you could also type

```
pt.parse_process('CO_desorption; CO@hollow->empty@hollow ; p_CO*bar*A/
↪sqrt(2*pi*umass*m_CO/beta)*exp(beta*deltaG*eV)')
```

and since any non-existing on either the left or the right side of the `->` symbol is replaced by a corresponding term with the `default_species` (in this case `empty`) you could as well type

```
pt.parse_process('CO_desorption; CO@hollow->; p_CO*bar*A/sqrt(2*pi*umass*m_CO/
↪beta)*exp(beta*deltaG*eV)')
```

and to make it even shorter you can parse and add the process on one line

```
pt.parse_and_add_process('CO_desorption; CO@hollow->; p_CO*bar*A/sqrt(2*pi*umass*m_
↪CO/beta)*exp(beta*deltaG*eV)')
```

In order to add processes on more than one site possible spanning across unit cells, there is a shorthand as well. The full-fledged syntax for each coordinate is

```
"<site-name>.<offset>.<lattice>"
```

check *Manual generation* for details.

1.3.3 Export, save, compile

Next, it's a good idea to save your work

```
pt.filename = 'myfirst_kmc.xml'
pt.save()
```

Now is the time to leave the python shell. In the current directory you should see a `myfirst_kmc.xml`. This XML file contains the full definition of your model and you can create the source code and binaries in just one line. So on the command line in the same directory as the XML file you run

```
kmos export myfirst_kmc.xml
```

or alternatively if you are still on the ipython shell and don't like to quit it you can use the API hook of the command line interface like

```
import kmos.cli
kmos.cli.main('export myfirst_kmc.xml')
```

Make sure this finishes gracefully without any line containing an error.

If you now `cd` to that folder `myfirst_kmc` and run:

```
kmos view
```

... and dada! Your first running kMC model right there!

If you wonder why the CO molecules are basically just dangling there in mid-air that is because you have no background setup, yet. Choose a transition metal of your choice and add it to the lattice setup for extra credit :-).

Wondering where to go from here? If the work-flow makes complete sense, you have a specific model in mind, and just need some more idioms to implement it I suggest you take a look at the [examples folder](#). for some hints. To learn more about the kmos approach and methods you should into [topic guides](#).

1.3.4 Taking it home

Despite its simplicity you have now seen all elements needed to implement a kMC model and hopefully gotten a first feeling for the workflow.

Todo

describe modelling more complicated structures and e.g. boundary conditions

1.4 Running the Model—the GUI way

After successfully exporting and compiling a model you get two files: `kmc_model.so` and `kmc_settings.py`. These two files are really all you need for simulations. So a simple way to view the model is the

```
kmos view
```

command from the command line. For this two work you need to be in the same directory as these two file (more precisely these two files need to be in the python import path) and you should see an instance of your model running. This feature can be quite useful to quickly obtain an intuitive understanding of the model at hand. A lot of settings can be changed through the `kmc_settings.py` such as rate constant or parameters. To be even more interactive you can set a parameter to be adjustable. This can happen either in the generating XML file or directly in the `kmc_settings.py`. Also make sure to set sensible minimum and maximum values.

1.5 How To Prepare a Model and Run It Interactively

If you want to prepare a model in a certain way (parameters, size, configuration) and then run it interactively from there, there is in easy way, too. Just write a little python script. The with-statement is nice because it takes care of the correct allocation and deallocation

```
#!/usr/bin/env python

from kmos.run import KMC_Model
from kmos.view import main

with KMC_Model(print_rates=False, banner=False) as model:
    model.settings.simulation_size = 5

with KMC_Model(print_rates=False, banner=False) as model:
    model.do_steps(int(1e7))
    model.double()
    model.double()
    # one or more changes to the model
```

```
# ...
main(model)
```

Or you can use the hook in the *kmc_settings.py* called *setup_model*. This function will be invoked at startup every time you call

```
kmos view, run, or benchmark
```

Though it can easily get overwritten, when exporting or rebuilding. To minimize this risk, you e.g. place the *setup_model* function in a separate file called *setup_model.py* and insert into *kmc_settings.py*

```
from setup_model import setup_model
```

Next time you overwrite *kmc_settings.py* you just need to add this line again.

1.6 Running the Model—the API way

In order to analyze a model quantitatively it is more practical to write small client scripts that directly talk to the runtime API. As time passes and more of these scripts are written over and over some standard functionality will likely be integrated into the runtime API. For starters a simple script could look as follows

```
#!/usr/bin/env python
from kmos.run import KMC_Model
model = KMC_Model()
```

An alternative way that gets you started fast it to run

```
kmos shell
```

and just interact directly with *model*. It is often a good idea to

```
%logstart some_scriptname.py
```

first in the IPython command to save what you have typed for later use.

As you can see by default the model prints a disclaimer and all rate constants, which can each be turned off by instantiating

```
model = KMC_Model(print_rates=False, banner=False)
```

The most important method is of course how to run the model, which you can do by saying

```
model.do_steps(100000)
```

which would run the model by 100,000 kMC steps.

Let's say you want to change the temperature and a partial pressure of the model you could type

```
model.parameters.T = 550
model.parameters.p_COgas = 0.5
```

and all rate constants are instantly updated. In order get a quick overview of the current settings you can issue e.g.

```
print(model.parameters)
print(model.rate_constants)
```

or just

```
print(model)
```

Now an instantiated and configured model has mainly two functions: run kMC steps and report its current configuration.

To analyze the current state you may use

```
atoms = model.get_atoms()
```

Note: If you want to fetch data from the current state without actually visualizing the geometry can speed up the `get_atoms()` call using

```
atoms = model.get_atoms(geometry=False)
```

This will return an ASE atoms object of the current system, but it also contains some additional data piggy-backed such as

```
model.get_occupation_header()
atoms.occupation

model.get_tof_header()
atoms.tof_data

atoms.kmc_time
atoms.kmc_step
```

These quantities are often sufficient when running and simulating a catalyst surface, but of course the model could be expanded to more observables. The Fortran modules *base*, *lattice*, and *proclist* are attributes of the model instance so, please feel free to explore the model instance e.g. using ipython and

```
model.base.<TAB>
model.lattice.<TAB>
model.proclist.<TAB>
```

etc..

The *occupation* is a 2-dimensional array which contains the *occupation* for each surface *site* divided by the number of unit cell. The first slot denotes the species and the second slot denotes the surface site, i.e.

```
occupation = model.get_atoms().occupation
occupation[species, site-1]
```

So given there is a *hydrogen* species in the model, the occupation of *hydrogen* across all site type can be accessed like

```
hydrogen_occupation = occupation[model.proclist.hydrogen]
```

To access the coverage of one surface site, we have to remember to subtract 1, when using the the builtin constants, like so

```
hollow_occupation = occupation[:, model.lattice.hollow-1]
```

Lastly it is important to call

```
model.deallocate()
```

once the simulation is finished as this frees the memory allocated by the Fortran modules. This is particularly necessary if you want to run more than one simulation in one script.

1.7 Generate Grids of Sampled Data

For some kMC applications you simply require a large number of data points across a set of external parameters (phase diagrams, microkinetic models). For this case there is a convenient class *ModelRunner* to work with

```
from kmos.run import ModelRunner, PressureParameter, TemperatureParameter

class ScanKinetics(ModelRunner):
    p_O2gas = PressureParameter(1)
    T = TemperatureParameter(600)
    p_COgas = PressureParameter(min=1, max=10, steps=40)

ScanKinetics().run(init_steps=1e8, sample_steps=1e8, cores=4)
```

This script generates data points over the specified range(s). The temperature parameters is uniform grids over $1/T$ and the pressure parameters is uniform over $\log(p)$. The script can be run synchronously over many cores as long as the cores can access the same file system. You have to test whether the steps before sampling (*init_steps*) as well as the batch size (*sample_steps*) is sufficient.

1.8 Manipulating the Model at Runtime

It is quite easy to change not only model parameters but also the configuration at runtime. For instance if one would like to prepare a surface with a certain configuration or pattern.

Given you instantiated a *model* instance a site occupation can be changed by calling

```
model.put(site=[x,y,z,n], model.proclist.<species>)
```

However if changing many sites at once this is quite inefficient, since each *put* call, adjusts the book-keeping database. To circumvent this you can use the *_put* method, like so

```
model._put(...)
model._put(...)
...
model._adjust_database()
```

though at the end one must not forget to call *_adjust_database()* before executing any next step or the database of available processes is inaccurate and the model instance will crash soon.

You can also get or set the whole configuration of the lattice at once using

```
config = model._get_configuration()
# possible change config
model._set_configuration(config)
```

1.9 Running models in parallel

Due to the global clock in kMC there seems to be no simple and efficient way to parallelize a kMC program. kmos certainly cannot parallelize a single system over processors. However one can run several kmos instances in parallel which might accelerate sampling or efficiently check for steady state conditions.

However in many applications it is still useful to run several models separately at once, for example to scan some set of parameters on a multicore computer. This kind of problem can be considered *embarrassingly parallel* since it requires no communication between the runs.

This is made very simple through the *multiprocessing* module, which is in the Python standard library since version 2.6. For older versions this needs to be *downloaded* <<http://pypi.python.org/pypi/multiprocessing/>> and installed manually. The latter is pretty straightforward.

Then besides *kmos* we need to import *multiprocessing*

```
from multiprocessing import Process
from numpy import linspace
from kmos.run import KMC_Model
```

and let's say you wanted to scan a range of temperature, while keeping all other parameteres constant. You first define a function, that takes a set of temperatures and runs the simulation for each

```
def run_temperatures(temperatures):
    for T in temperatures:
        model = KMC_Model()
        model.parameters.T = T
        model.do_steps(100000)

        # do some evaluation

    model.deallocate()
```

In order to split our full range of input parameters, we can use a utility function

```
from kmos.utils import split_sequence
```

All that is left to do, is to define the input parameters, split the list and start subprocesses for each sublist

```
if __name__ == '__main__':
    temperatures = linspace(300, 600, 50)
    nproc = 8
    for temperatures in split_sequence(temperatures, nproc):
        p = Process(target=run_temperatures, args=(temperatures, ))
        p.start()
```

1.10 Development

Contributions of any sort are of course quite welcome. Patches and comments are ideally sent in form of email, pull request, or github issues.

To make synergizing a most pleasing experience I suggest you use git, nose, pep8, and pylint

```
sudo apt-get install git python-nose pep8 pylint
```

When sending a patch please make sure the nose tests pass, i.e. run from the top project directory

```
nosetests
```

To make testing and comparison even easier it would be helpful if you create an account with [Travis CI](#) and run your commits through the test suite.

Have a look at Google's Python [style guide](#) as far as style questions go.

The conceptual parts of this topic guide predate the [kmos paper \(arXiv\)](#). Please refer to the paper for a thorough background on kMC and lattice kMC on crystal surfaces. The more technical parts stated below might still be useful for using kmos.

2.1 The Concept of Kinetic Monte Carlo

2.1.1 Why use Kinetic Monte Carlo?

There is a class of systems in nature for which the spatiotemporal evolution can be described using a master type of equation. While chemical reactions at surfaces is one of them, it is not limited to those.

The master equation imposes that given a probability distribution $\rho_i(t)$ over states, the probability distribution at one infinitesimal time Δt later can be obtained from

$$\rho_i(t + \Delta t) = \rho_i(t) + \sum_j -k_{ji}\rho_j(t)dt + k_{ij}\rho_j(t)dt$$

where the important bit is that each $\rho(t)$ only depends on the state just before the current state. The matrix k_{ij} consists of constant real entries, which describe the rate at which the system can propagate from state j to state i . In other words the system is without memory which is usually known as the Markov approximation.

Kinetic Monte Carlo (kMC) integrates this equation by generating a state-to-state trajectory using a preset catalog of transitions or elementary steps and a rate constant for each elementary step. The reason to generate state-to-state trajectories rather than just propagating the entire probability distribution at once is that the transition matrix k_{ij} easily becomes too large for many systems at hand that even storing it would be too large for any storage device in foreseeable future.

As a quick estimate consider a system with 100 sites and 3 possible states for each site, thus having 3^{100} different configurations. The matrix to store all transition elements would have $(3^{100})^2 \approx 2.66 \cdot 10^{95}$ entries, which exceeds the number of atoms on our planet by roughly 45 orders of magnitude.¹ And even though most of these elements would be zero since the number of accessible states is usually a lot smaller, there seems to be no simple way to transform to and solve this irreducible matrix in the general case.

Thus it is a lot more feasible to take one particular configuration and figure out the next process as well as the time it takes to get there and obtain ensemble averages from time averages taken over a sufficiently long trajectory. The basic steps can be described as follows

¹ Wolfram Alpha's [estimate](#) for number of atoms on earth.

2.1.2 Basic Kinetic Carlo Algorithm

- **Fix rate constants** k_{ij} initial state x_i , and initial time t
- while $t < t_{\max}$ do
 1. draw random numbers $R_1, R_2 \in]0, 1]$
 2. find l such that $\sum_{j=1}^l k_{ij} < k_{i,\text{tot}} R_1 < \sum_{j=1}^{l+1} k_{ij}$
 3. increment time $t \rightarrow t - \frac{\ln(R_2)}{k_{i,\text{tot}}}$
- end

2.1.3 Justification of the Algorithm

Let's understand why this simulates a physical process. The Markov approximation mentioned above implies several things: not only does it mean one can determine the next process from the current state. It also implies that all processes happen independently of one another because any memory of the system is erased after each step. Another great simplification is that rate constants simply add to a total rate, which is sometimes referred to as **Matthiessen's rule**, viz the rate with which *any* process occurs is simply $\sum_i k_i$.

First, one can show that the probability that n such processes occur in a time interval t is given by a Poisson distribution²

$$P(n, t) = \frac{e^{-k_{\text{tot}}t} (k_{\text{tot}}t)^n}{n!}.$$

The waiting time or escape time t_w between two such processes is characterized by the probability that *zero* such processes have occurred

$$P(0, t_w) = e^{-k_{\text{tot}}t_w}, \quad (2.1)$$

which, as expected, leads to an average waiting time of

$$\langle t_w \rangle = \frac{\int_0^\infty dt_w t_w e^{-k_{\text{tot}}t_w}}{\int_0^\infty dt_w e^{-k_{\text{tot}}t_w}} = \frac{1}{k_{\text{tot}}}.$$

Therefore at every step, we need to advance the time by a random number that is distributed according to (2.1). One can obtain such a random number from a uniformly distributed random number $R_2 \in]0, 1]$ via $-\ln(R_2)/k_{\text{tot}}$.³

Second, we need to select the next process. The next process occurs randomly but if we did this a very large number of times for the same initial state the number of times each process is chosen should be proportional to its rate constant. Experimentally one could achieve this by randomly sprinkling sand over an arrangement of buckets, where the size of the bucket is proportional to the rate constant and count each hit by a grain of sand in a bucket as one executed process. Computationally the same is achieved by steps 2 and 3.

2.1.4 Further Reading

For a very practical introduction I recommend Arthur Voter's tutorial⁴ and Fichthorn⁵ for a derivation, why Δt is chosen they way it is. The example given there is also an excellent exercise for any beginning kMC modeler. For recent review on implementation techniques I recommend the review by Reese et al.⁶ and for a review over status and outlook I recommend the one by Reuter⁷.

² C. Gardiner, 2004. *Handbook of Stochastic Methods: for Physics, Chemistry, and the Natural Sciences*. Springer, 3rd edition, ISBN:3540208828.

³ P. W. H. T. S. A, V. W. T, and F. B. P, 2007 *Numerical Recipes 3rd Edition: The Art of Scientific Computing*. Cambridge University Pres, 3rd edition, ISBN:0521768589, p. 287. [link](#)

⁴ Voter, Arthur F. "Introduction to the Kinetic Monte Carlo Method." In *Radiation Effects in Solids*, 1–23, 2007. http://dx.doi.org/10.1007/978-1-4020-5295-8_1. [link](#)

⁵ Fichthorn, Kristen A., and W. H. Weinberg. "Theoretical Foundations of Dynamical Monte Carlo Simulations." *The Journal of Chemical Physics* 95, no. 2 (July 15, 1991): 1090–1096. [link](#)

⁶ Reese, J. S., S. Raimondeau, and D. G. Vlachos. "Monte Carlo Algorithms for Complex Surface Reaction Mechanisms: Efficiency and Accuracy." *Journal of Computational Physics* 173, no. 1 (October 10, 2001): 302–321. [link](#)

⁷ Reuter, Karsten. "First-principles Kinetic Monte Carlo Simulations for Heterogeneous Catalysis: Concepts, Status and Frontiers". Wiley-VCH, 2009. [link](#)

2.2 Modelling Workflows

At the core of modelling lies the art to capture the most important features of a system and leave all others out. kmos is designed around the fact that modelling is a creative and iterative process.

A typical type of approach for modelling could be:

1. start with educated guess
2. calculate outcome
3. compare various observables and qualitative behavior with reference system
4. adapt model, goto 2. or publish model

So while this procedure is quite generic it may help to illustrate that the chances to find and capture the relevant features of a system are enhanced if the trial/learn loop is as short as possible.

2.2.1 kMC Modeling

A good way to define a model is to use a paper and pencil to draw your lattice, choose the species that you will need, draw each process and write down an expression for each rate constant, and finally fix all energy barriers and external parameters that you will need. Putting a model prepared like this into a computer is a simple exercise. You enter a new model by filling in

- meta information
- lattice
- species
- parameters
- processes

in roughly this order or open an existing one by opening a kMC XML file.

If you want to see the model run `kmos export <xml-file>` and you will get a subfolder with a self-contained Fortran90 code, which solves the model. If all necessary dependencies are installed you can simply run `kmos view` in the export folder.

2.2.2 kmos workflows

Since *kmos* has several entry points, there are several ways of using it. This section will outline different ways of using kmos:

- *the render script*

Just write complete scripts as outlined in `../tutorials/first_model_api`. Export source from there or inspect XML file with one of the next methods below.

- *the GUI editor*

Open an existing project *.xml file with

```
kmos edit <project_name>.xml
```

and inspect or edit it through on screen

- *the CLI editor*

Open an existing project *.xml file with

```
kmos import <project_name>.xml
```

and edit the project interactively on the ipython console.

- *edit the XML file*

Just open the XML file of your kmos project with a text editor of your choice and inspect or your model right there. This might only be a last resort to figure out what is going on. XML is often not considered very readable and note that changing variable names in one place might often break inconsistencies in other.

2.3 The kmos data model

The guide explains how kmos handles represent a kmc model internally, which is important to know if one wants to write new functionality.

The different functions and front-ends of kmos all interact in some way or another with instances of the Project class. A Project instance is a representation of a kmc model. If you fire up 'kmos edit' with an xml file, kmos validates the XML file and stores the content in a Project instance. If you export source code, kmos runs over the Project and creates the necessary Fortran 90 source code.

So the following things are in a Project:

- meta
- lattice(layers)
- species
- parameters
- processes

The language used here stems from modelling atomic movement on a fixed or evolving lattice like structure. In a more general context one may rephrase them as :

- meta -> information about project
- lattice -> geometry
- species -> states
- parameters
- processes -> transitions

2.4 How the kmos kMC algorithm works

kmos asks you to describe your model to the processor in seemingly arcane ways. It can save model descriptions in XML but they are basically unreadable and a pain to edit. The API has some glitches and is probably incomplete: so why learn it?

Because it is fast (in two ways).

The code it produces is commonly faster than naive implementations of the kMC method. Most straightforward implementations of kMC take a time proportional to $2*N$ per kMC step, where N is the number of sites in the system. However the code that kmos produces is $O(1)$ until the RAM of your system is exceeded. As benchmarks have shown this may happen when 100,000 or more sites are required. However tests have also shown that kmos can be faster than $O(N)$ implementations from around 60-100 sites. If you have different experiences please let me know but I think this gives some rule of thumb.

Why is it faster? Straightforward implementations of kMC scan the entire system twice per kMC step. First to determine the total rate, then to determine the next process to be executed. The present implementation does not. kmos keeps a database of available processes which allow to quickly pick the next process. It also updates the database of available processes which cost additional overhead. However this overhead is independent of the system's size and only scales with the degree of interaction between sites, which is seems hard to define in general terms.

The second way reason why it is fast is because you can formulate processes in a intuitive fashion and let kmos figure how to make fast running code out of it. So we save in human time and CPU time, which is essentially human time as well. Yay!

To illustrate just how fast the algorithm is the graph below shows the CPU time needed to simulate 1 million kMC steps on a simple cubic lattice in 2 dimension with two reacting species and without lateral interaction. As this shows the CPU time spent per kMC step as nearly constant for up nearly 10^5 sites.




Fig. 2.1: Benchmark for a simple surface reaction model. All simulations have been performed on a single CPU of Intel I7-2600K with 3.40 GHz clock speed.

2.4.1 The kmos O(1) solver

So what makes the kMC solver so furiously fast? The underlying data structure is shown in the picture above. The most important part is that the solver never scans the entire system for available processes except at program initialization.

Please have a look at the sketch of data structures above. Given that all arrays are initialized and populated, in each kMC step the following things happen:

In the first step we need to identify the next process and site. To do so we draw a random number $R_1 \in [0, 1]$. This number has to be scaled to k_{tot} , so we multiply it with the last field in *accum. rates*. Next we simply perform a [binary search](#) for the right process on *accum. rates*. Having determined the process, we pick a site using a second random number R_2 , which is constant in time since *avail sites* is filled up with the available site for each process from the left.

Totally independent of this we calculate the duration of the current step with another random number R_3 using

$$\Delta t = \frac{-\log(R_3)}{k_{\text{tot}}}$$




Fig. 2.2: The data model underlying the kmos solver. The central component is the *avail_sites* array which stores for each elementary step the sites for which it is executable. Secondly it stores the location in memory, where the availability of the site is stored for direct access. The array of *rate constants* holds the numeric rate constant and only changes, when a physical parameter is changed. The *nr of sites* array holds the total number of sites for each process and needs to be updated whenever a process becomes available und unavailable. The *accum. rates* has to be updated once per kMC step and holds the accumulated rate constant for each processes. That is, the last field of accum. rates holds k_{tot} , the total rate of the system.

So, while the determination of process and site is extremely straightforward, the CPU intensive part just starts now. The *proclist* module is written in such a way, for each elementary step it updates the *avail sites* array only in the local neighborhood of the site, where the process is executed. It is furthermore heuristically optimized in order to require only a minimal number of *if*-statement to figure out which database updates are necessary. This will be explained in greater detail in the next subsection.

For the current description it is sufficient to know that for all database updates by the *proclist* module :

- the *nr of sites* array is updated as well.
- adding or deleting an available site only takes constant time, since the number of available sites as well as the memory addresses is always updated. Thus new sites are simply added at the end of the list of available sites. When a site has to be deleted the last site in the array is moved to the memory slot available now.

Thus once all local updates are finished the *accum. rates* array is simply updated once. And ready we are for the next kMC step.

Todo

describe translation algorithm

2.5 The otf Backend

NOTICE: The otf backend is still on an EXPERIMENTAL state and not ready for production.

As described in “*How the kmos kMC algorithm works*” the default kmos backends (*local_smart* and *lat_int*) produce code which executes in time $O(1)$ with the system size (total number of sites in the lattice). This is achieved through some book-keeping overhead, in particular storing every rate constant beforehand in an array. For some particular class of problems, *i.e.* those in which extended lateral interactions are taken into account. This implies that some elementary processes need to be included multiple times in the model definition (to account for the effect of the surrounding lattice configuration on the rate constants). Depending on the amount of sites taken into account and the number of different species that participate, the number of repetitions can easily reach several thousands or more. This leads to two undesired effects: First the amount of memory required by the book-keeping structures (which is proportional to the number of processes) could quickly be larger than your system has available. Second, the kmos algorithm is $O(1)$ in system size, but $O(N)$ in number of processes, which eventually leads to a slow down for more complex systems.

The otf backend was developed with these setbacks in mind. otf stands for On The Fly, because rate constants of processes affected by lateral interactions are calculated at runtime, according to user specifications.

NOTE: Up to now only a limited type of lateral interactions are supported at the moment, but the development of additional ones should be easy within the framework of the otf backend.

In this new backend, kmos is not able to generate $O(1)$ code in the system size, but now each process corresponds to a full group of processes from the traditional backends. For this reason, the otf backend is built to deal with simulations in which multisite/multispecies lateral interactions are included and in which the system size is not too large.

TODO: Put numbers to `when_to_use_otf(volume, nr_of_procs)`

2.5.1 Reference

Here we will detail how to set up a kmc model for the otf kmos backend. It will be assumed that the reader is familiar with Tutorial “*A first kMC Model—the API way*” and focus will be in the differences between the traditional backends (*local_smart* and *lat_int*) and otf. Most of the model elements (Project, ConditionAction, Species, Parameter) work exactly the same in the new backend.

The Process object, is the one whose usage is most distinct, as it can take two otf-backend exclusive attributes:

- `otf_rate`: Represent the expression to be used to calculate the rate of the process at runtime. It is parsed similarly to the `rate_constant` attribute and likewise can contain all the user defined parameters, as well as all constant and chemical potentials know to kmos. Additionally, special keywords (namely `base_rate` and `nr_<species>_<flag>`) also have a special meaning. This is described below.
- `bystander_list`: A list objects from the `Bystander` class (described below) to represent the sites which do not participate in the reaction but which affect the rate constant.

Additionally, the meaning of the `rate_constant` attribute is modified. This expression now represents the rate constant in the `default` configuration around the process. What this default configuration means is up to the user, but it will normally be the rate at the zero coverage limit (ZCL).

Additionally a new model description element, the `Bystander`, has been introduced. It has the attributes

- `coord`: Represents a coordinate relative to the coordinates in the process.
- `allowed_species`: This is a list of species, which can affect the rate constant of the process when they sit in `coord`
- `flag`: This is a short string that works a descriptor of the bystander. It is useful when defining the `otf_rate` of the process to which the bystander is associated.

The rate constant to be calculated at runtime for each Process is given by the expression in `otf_rate`. Apart from all standard parameters, kmos also parses the strings

- `base_rate`: Which is evaluated to the value of the `rate_constant` attribute

NOTE: For now, the `base_rate` expression is **required**.

- Any number of expressions of the form `nr_<species>_<flag>`. Where `<species>` is to be replaced by any of the species defined in the model and `<flag>` is to be replaced by one of the flags given to the bystanders of this process.

During export, kmos will write routines that look at the occupation of each of the bystanders at runtime and count the total number of each species within `allowed_species` for each bystander type (flag).

2.5.2 Example

For this we will write down an alternative to the `render_pairwise_interaction.py` example file. Most of the script can be left as is. From the import statements, we can delete the line that imports `itertools`, as we won't be needing it. From then on, up to the point where we have defined all process not affected by lateral interactions, we do not need any changes. We also need to collect a set of all interacting coordinates which will affect CO desorption rate:

```
# fetch a lot of coordinates
coords = pt.lattice.generate_coord_set(size=[2, 2, 2],
                                     layer_name='simplecubic_2d')
# fetch all nearest neighbor coordinates
nn_coords = [nn_coord for i, nn_coord in enumerate(coords)
             if 0 < (np.linalg.norm(nn_coord.pos - center.pos)) <= A]
```

as with traditional backends. With the `otf` backend however, we do not need to account for all possible combinations (and thus we do not need the `itertools` module). In this case, desorption only has one condition and one action:

```
conditions = [Condition(species='CO', coord=center)]
actions = [Action(species='empty', coord=center)]
```

And we use the coordinates we picked to generate some bystanders:

```
bystander_list = [Bystander(coord=coord,
                           allowed_species=['CO'],
                           flag='1nn') for coord in nn_coords]
```

As we are only considering the CO-CO interaction, we only include it in the `allowed_species`, but we could easily have included more species. Now, we need to describe the expressions to calculate the rate constant at runtime. In the original script, the rate is given by:

```
rate_constant = 'p_COgas*A*bar/sqrt(2*m_CO*umass/beta) '/
                '*exp(beta*(E_CO+%s*E_CO_nn-mu_COgas)*eV) ' % N_CO
```

where the `N_CO` is calculated beforehand (in the model building step) for each of the individual lattice configurations. For the `otf` backend, we define the ‘base’ rate constant as the rate at ZCL (`N_CO = 0`), that is:

```
rate_constant = 'p_COgas*A*bar/sqrt(2*m_CO*umass/beta) '/
                '*exp(beta*(E_CO-mu_COgas)*eV) '
```

Finally, we must provide the expression given to calculate the rate given the amount of CO around in our bystanders. For this we simply define:

```
otf_rate = 'base_rate*exp(beta*nr_CO_1nn*E_CO_nn*eV) '
```

All of this comes together in the process definition:

```
proc = Process(name='CO_desorption',
              conditions=conditions,
              actions=actions,
              bystander_list = bystander_list,
              rate_constant=rate_constant,
              otf_rate=otf_rate)
pt.add_process(proc)
```

2.5.3 Advanced OTF rate expressions

In the example above, the `otf_rate` variable for the processes included only a single expression that defined the rate taking into account the values of the `nr_<species>_<flag>` variables. For more complex lateral interaction models, this can become cumbersome. Alternatively, users can define `otf_rate` expressions that span several expressions/lines. Lets assume we are dealing with a model similar to the one above, but now include an additional species, O, and the corresponding lateral interaction energy `E_CO_O` between these two. Similarly to the previous example, the rate would be given by:

```
rate_constant = 'p_COgas*A*bar/sqrt(2*m_CO*umass/beta) '/
                '*exp(beta*(E_CO+%s*E_CO_nn+%s*E_CO_O-mu_COgas)*eV) ' % (N_CO, N_O)
```

where `N_O` is the number of nearest-neighbour O. This rate expression is still fairly simple and the previously described method would work by doing:

```
otf_rate = 'base_rate*exp(beta*(nr_CO_1nn*E_CO_nn+nr_O_1nn*E_CO_O)*eV) '
```

However, equivalently (and maybe more easy to read) we could define:

```
otf_rate = 'Vint = nr_CO_1nn*E_CO_nn+nr_O_1nn*E_CO_O\n'
otf_rate += 'otf_rate = base_rate*exp(beta*Vint*eV) '
```

in which we have defined an auxiliary variable `Vint`. Behind the scenes, these lines are included in the source code automatically generated by `kmos`. Notice the inclusion of explicit `\n` characters. This is necessary because we want the line breaks to be explicitly stored as `\n` in the `.xml` file for export (spaces are ignored by the xml export engine). Since these expression are ultimately compiled as Fortran90 code, variable names are not case sensitive (i.e. `A = ...` and `a = ...` declare the same variable).

Additionally, when we want to include more than one line of code in `otf_rate`, we additionally need to include a line that states `otf_rate = ...` in order for `kmos` to know how to calculate the returned rate.

2.5.4 Running of kmos models

Once the of k model has been defined, the model can be run in a fashion very similar to the default kmos backends most of the differences arise from the

Todo

The rest of this sentence seems to have gotten lost somehow.

2.5.5 Known Issues

1. **Non-optimal updates to rates_matrix.** The current implementation of the backend is still non-optimal and can lead to considerable decrease in speed for larger systems sizes (scaling $O(N_{sites})$). This will be improved ($O(\log(N_{sites}))$) once more tests are conducted.
2. **Process name length limit** f2py will crash during compilation if a process has a name larger than approx. 20 characters.

2.6 The Process Syntax

In kMC language a process is uniquely defined by a configuration *before* the process is executed, a configuration *after* the process is executed, and a rate constant. Here this model is used to define a process by giving it a :

- condition_list
- action_list
- rate_constant

As you might guess each *condition* corresponds to one *before*, and each *action* corresponds to one *after*. In fact conditions and actions are actually of the same class or data type: each condition and action consists of a coordinate and a species which has to *be* or *will be* at the coordinate. This model of process definition also means that each process in one unit cell has to be defined explicitly. Typically on a single crystal surface one will have not one diffusion per species but as many as there are equivalent directions :

- species_diffusion_right
- species_diffusion_up
- species_diffusion_left
- species_diffusion_down

while this seems like a lot of work to define that many processes, it allows for a very clean and simple definition of a process itself. Later you can use geometric measures to abstract these cases as you will see further down.

2.6.1 Adsorption

Let's start with a very simple and basic process: molecular adsorption of a gas phase species, let call it A on a surface site. For this we need a species

```
from kmos.types import *
pt = Project()

A = Species(name='A')
pt.add_species(A)

empty = Species(name='empty')
pt.add_species(empty)
```

and the coordinate of a surface site

```
layer = Layer(name='default')
pt.add_layer(layer)
layer.sites.append(Site(name='a'))
coord = pt.lattice.generate_coord('a.(0,0,0).default')
```

which is for now all we need to define an adsorption process:

```
adsorption = Proces(name='adsorption_A_a',
                    condition_list=[Condition(coord=coord,
                                              species='empty')],
                    action_list=[Action(coord=coord,
                                       species='A')])
pt.add_process(adsorption)
```

Now this wasn't hard, was it?

2.6.2 Diffusion

Let's move to another example, namely the *diffusion* of a particle to the next unit cell in the y-direction. You first need the coordinate of the final site

```
final = pt.lattice.generate_coord('a.(0,1,0).default')
```

and you are good to go

```
diffusion_up = Process('diffusion_A_up',
                       condition_list=[Condition(coord=coord,
                                                  species='A'),
                                       Condition(coord=final,
                                                  species='empty')],
                       condition_list=[Condition(coord=coord,
                                                  species='empty'),
                                       Condition(coord=final,
                                                  species='A')],
                       rate_constant=1)
pt.add_process(diffusion_up)
```

You can complicated this *ad infinitum* but you know all elements needed to define processes.

2.6.3 Avoid Double Counting

Finally a word of warning: *double counting* is a phenomenon sometimes encountered for those process where there is more than one equivalent direction for a process and the coordinates within the process are also equivalent. Think of dissociative oxygen adsorption. Novices typically collect all possible directions (e.g. right, up, left, down) and then define this process for each direction. Later they realize that in fact they *double counted* the process because e.g. adsorption_up is the same processes as adsorption_down, just executed from one site above or below. Then they compensate by dividing each adsorption rate constant by 2. Later realizing that they have to do the same for desorption. Ok, I have done this and believe me it is really bad when you are looking for an error if at the same you already divide the unit cell size by 2 for some reason.

The smart way out is to save the pain and to avoid double counting completely from the beginning and just think how many process are geometrically inequivalent in the unit cell. A simple trick is to only consider processes in the *positive* directions.

2.6.4 Taking It Home

- A process consists of conditions, actions and a rate constant

- *double counting* is best avoided from the beginning

2.7 The Site/Coordinate Syntax

In the atomistic kMC simulations pursued here one defines processes in terms of sites on some more or less fixed lattice. This reflects the physical observation that molecules on surfaces adsorb on very specific locations above a solid.

To represent this in a computer program, we first need to make a small but crucial differentiation: namely the difference between the *sites* of a (surface) structure and the *coordinates* of a process. The difference is that a given structure contains each site defined exactly once, whereas a process may use the same site several times however in a different unit cell. So this differentiation owes to the fact that we commonly simulate highly periodic structures.

Ok, having this out of the way you start to define and use sites and coordinates. The minimum constructor for a site is

```
site = Site(name='site_name')
```

where `site_name` can be a string without spaces and all names should be unique within one layer. Usually it is reasonable to add a position in relative coordinates right-away like so

```
site = Site(name='hollow', pos='0.5 0.5 0.0')
```

which would place the site at the bottom center of the cell. A direct benefit is that you can measure distances between coordinates later on to, e.g. select all nearest neighbor or next-nearest neighbor sites.

A site can have some more attributes. Some of them are only needed in conjunction with GUI use. It is worth to know that each site can have one or more tags. This way one create types of site and conveniently select all sites with a one more tags. The syntax here is as follows

```
site = Site(name='hollow', pos='0.5 0.5 0.0', tags='tag1 tag2 ...')
```

The second part is to generate the coordinates that are used in the process description.

2.7.1 Manual generation

To quickly generate single coordinates you can generate it from a Project like so

```
pt.lattice.generate_coord('hollow.(0,0,0).layer_name')
```

Let's look at the generation string. The general syntax is

```
site_name.offset.layer_name
```

The `site_name` and the `layer_name` must have been defined before. The `offset` is a tuple of three integer numbers $(0, 0, 1)$ and specifies the relative unit cell of this coordinate. Of course this only becomes meaningful as soon as you use more than one coordinate in a process.

Missing values will be filled in from the back using default values, such that

```
site -> site.(0,0,0) -> site.(0,0,0).default_layer
```

2.7.2 Advanced Coordinate Techniques

Generating large process lists with a lot of similar or even degenerate processes is a very boring task. So we should try to use programming logic as much as possible. Here I will outline a couple of idioms you can use here.

Often times it is handier (less typing) to generate a larger set of coordinates at first and then select different subsets from it in a process definition. For this purpose you can use

```
pset = pt.lattice.generate_coord_set(size=[x,y,z], layer_name='layer_name')
```

This collects all sites from the given layer and generates all coordinates in the first unit cell (`offset=(1,1,1)`) and all `x`, `y`, and `z` unit cells in the respective direction.

To select subsets in a readable way I suggest you use list comprehensions, like so

```
[ x for x in pset if not x.offset.any() ]
```

which again selects all sites in the first unit cell. Or to select all site tagged with `foo` you could use

```
[ x for x in pset if 'foo' in x.tags.split() ]
```

or having defined a unit cell size and a site position your can measure real-space distances between coordinate like so

```
np.linalg.norm(x.pos-y.pos)
```

Or of course you can use any combination of the above.

2.7.3 Taking it home

- *sites* belong to a *structure* while *coordinates* belong to a *process*
- coordinates are generated from sites
- coordinate sets can be selected and chopped using list comprehensions and tags

3.1 Command Line Interface (CLI)

Entry point module for the command-line interface. The kmos executable should be on the program path, import this modules main function and run it.

To call kmos command as you would from the shell, use

```
kmos.cli.main('...')
```

Every command can be shortened as long as it is non-ambiguous, e.g.

```
kmos ex <xml-file>
```

instead of

```
kmos export <xml-file>
```

etc.

3.1.1 List of commands

kmos benchmark Run 1 mio. kMC steps on model in current directory and report runtime.

kmos build Build kmc_model.so from *f90 files in the current directory.

Additional Parameters ::

-d/-debug Turn on assertion statements in F90 code

-n/-no-compiler-optimization Do not send optimizing flags to compiler.

kmos edit <xml-file> Open the kmos xml-file in a GUI to edit the model.

kmos export <xml-file> [<export-path>] Take a kmos xml-file and export all generated source code to the export-path. There try to build the kmc_model.so.

Additional Parameters

```
-s/--source-only
    Export source only and don't build binary

-b/--backend (local_smart|lat_int)
    Choose backend. Default is "local_smart".
    lat_int is EXPERIMENTAL and not made
    for production, yet.

-d/--debug
    Turn on assertion statements in F90 code.
    (Only active in compile step)

--acf
    Build the modules base_acf.f90 and proclist_acf.f90. Default is false.
    This both modules contain functions to calculate ACF (autocorrelation_
    ↪function) and MSD (mean squared displacement).

-n/--no-compiler-optimization
    Do not send optimizing flags to compiler.
```

kmos help <command> Print usage information for the given command.

kmos help all Display documentation for all commands.

kmos import <xml-file> Take a kmos xml-file and open an ipython shell with the project_tree imported as pt.

kmos rebuild Export code and rebuild binary module from XML information included in kmc_settings.py in current directory.

Additional Parameters ::

-d/--debug Turn on assertion statements in F90 code

kmos run

Open an interactive shell and create a KMC_Model in it run == shell

kmos settings-export <xml-file> [<export-path>] Take a kmos xml-file and export kmc_settings.py to the export-path.

kmos shell

Open an interactive shell and create a KMC_Model in it run == shell

kmos version Print version number and exit.

kmos view Take a kmc_model.so and kmc_settings.py in the same directory and start to simulate the model visually.

Additional Parameters ::

-v/--steps-per-frame <number> Number of steps per frame

kmos xml Print xml representation of model to stdout

3.2 Data Types

3.2.1 kmos.types

Holds all the data models used in kmos.

class kmos.types.Project

A Project is where (almost) everything comes together. A Project holds all other elements needed to describe one kMC Project ready to be manipulated, exported, or imported.

The overall structure is the following as is also displayed in the editor GUI.

Project:

```

- Meta
- Parameters
- Lattice(s)
- Species
- Processes

```

add_layer (*layers, **kwargs)

Add a layer to the project. A Layer, or keywords that are passed to the Layer constructor are accepted.

Parameters

- **layers** (*list*) – List of layers.
- **cell** (*np.array (3x3)*) – Size of unit-cell.
- **default_layer** (*str.*) – name of default layer.

add_parameter (*parameters, **kwargs)

Add a parameter to the project. A Parameter, or keywords that are passed to the Parameter constructor are accepted.

Parameters

- **name** (*str*) – The name of the parameter.
- **value** (*float*) – Default value of parameter.
- **adjustable** (*bool*) – Create controller in GUI.
- **min** (*float*) – Minimum value for controller.
- **max** (*float*) – Maximum value for controller.
- **scale** (*str*) – Controller scale: ‘log’ or ‘lin’

add_process (*processes, **kwargs)

Add a process to the project. A Process, or keywords that are passed to the Process constructor are accepted.

Parameters

- **name** (*str*) – Name of process.
- **rate_constant** (*str*) – Expression for rate constant.
- **condition_list** (*list.*) – List of conditions (class Condition).
- **action_list** (*list.*) – List of conditions (class Action).
- **enabled** (*bool.*) – Switch this process on or of.
- **chemical_expression** (*str.*) – Chemical expression (i.e: A@site1 + B@site2 -> empty@site1 + AB@site2) to generate process from.
- **tof_count** (*dict.*) – Stoichiometric factor for observable products {'NH3': 1, 'H2O(gas)': 2}. Hint: avoid space in keys.

add_site (**kwargs)

Add a site to the project. The arguments are

add_site(layer_name, site)

Parameters

- **name** (*str*) – Name of layer to add the site to.
- **site** (*Site*) – Site instance to add.

add_species (**species*, ***kwargs*)

Add a species to the project. A Species, or keywords that are passed to the Species constructor are accepted.

Parameters

- **name** (*str*) – Name of species.
- **color** (*str*) – Color of species in editor GUI (#ffffff hex-type specification).
- **representation** (*str*) – ase.atoms.Atoms constructor describing species geometry.
- **tags** (*str*) – Tags of species (space separated string).

get_parameters (*pattern=None*)

Return list of parameters in Project.

Parameters **pattern** (*str*) – Pattern to fnmatch name of parameter against.

get_processes (*pattern=None*)

Return list of processes.

Parameters **pattern** (*str*) – Pattern to fnmatch name of process against.

get_species (*pattern=None*)

Return list of species in Project.

Parameters **pattern** (*str*) – Pattern to fnmatch name of process against.

import_xml_file (*filename*)

Takes a filename, validates the content against kmc_project.dtd and import all fields into the current project tree

parse_and_add_process (*string*)

Generate and add processes using a shorthand notation like, e.g. :: process_name; species1A@coord1 + species2A@coord2 + ... -> species1B@coord1 + species2A@coord2 + ...; rate_constant_expression

Parameters **string** (*str*) – shorthand notation for process

parse_process (*string*)

Generate processes using a shorthand notation like, e.g. :: process_name; species1A@coord1 + species2A@coord2 + ... -> species1B@coord1 + species2A@coord2 + ...; rate_constant_expression

Parameters **string** (*str*) – shorthand notation for process

validate_model ()

Run various consistency and completeness test of the model to make sure we have a minimally complete model.

class kmos.types.**Meta** (**args*, ***kwargs*)

Class holding the meta-information about the kMC project

class kmos.types.**Parameter** (***kwargs*)

A parameter that can be used in a rate constant expression and defined via some init file.

Parameters

- **name** (*str*) – The name of the parameter.
- **adjustable** (*bool*) – Create controller in GUI.
- **min** (*float*) – Minimum value for controller.
- **max** (*float*) – Maximum value for controller.
- **scale** (*str*) – Controller scale: ‘log’ or ‘lin’

class `kmos.types.LayerList` (***kwargs*)

A list of layers

Parameters

- **cell** (*np.array (3x3)*) – Size of unit-cell.
- **default_layer** (*str.*) – name of default layer.

generate_coord (*terms*)

Expecting something of the form `site_name.offset.layer` and return a `Coord` object

generate_coord_set (*size=[1, 1, 1]*, *layer_name='default'*, *site_name=None*)

Generates a set of coordinates around unit cell of any desired size. By default it includes exactly all sites in the unit cell. By setting `size=[2,1,1]` one gets an additional set in the positive and negative x-direction.

class `kmos.types.Layer` (***kwargs*)

Represents one layer in a possibly multi-layer geometry.

Parameters

- **name** (*str*) – Name of layer.
- **sites** (*list*) – Sites associated with this layer (Default: [])

class `kmos.types.Site` (***kwargs*)

Represents one lattice site.

Parameters

- **name** (*str*) – Name of site.
- **pos** (*np.array or str*) – Position within unit cell.
- **tags** (*str*) – Tags for this site (space separated).
- **default_species** (*str*) – Initial population for this site.

class `kmos.types.Species` (***kwargs*)

Class that represent a species such as oxygen, empty, Note: *empty* is treated just like a species.

Parameters

- **name** (*str*) – Name of species.
- **color** (*str*) – Color of species in editor GUI (#ffffff hex-type specification).
- **representation** (*str*) – ase.atoms.Atoms constructor describing species geometry.
- **tags** (*str*) – Tags of species (space separated string).

class `kmos.types.Process` (***kwargs*)

One process in a kMC process list

Parameters

- **name** (*str*) – Name of process.
- **rate_constant** (*str*) – Expression for rate constant.
- **otf_rate** (*str*) – Expression used to calculate rate on the fly using bystander's configuration, otf backend only!.
- **condition_list** (*list.*) – List of conditions (class `Condition`).
- **action_list** (*list.*) – List of conditions (class `Action`).
- **bystander_list** (*list.*) – List of bystanders (class `Bystander`), otf backend only!.
- **enabled** (*bool.*) – Switch this process on or of.

- **chemical_expression** (*str.*) – Chemical expression (i.e: `A@site1 + B@site2` -> `empty@site1 + AB@site2`) to generate process from.
- **tof_count** (*dict.*) – Stoichiometric factor for observable products {‘NH3’: 1, ‘H2Ogas’: 2}. Hint: avoid space in keys.

class `kmos.types.ConditionAction` (***kwargs*)

Represents either a condition or an action. Since both have the same attributes we use the same class here, and just store them in different lists, depending on its role. For better readability one can also use *Condition* or *Action* which are just aliases.

Parameters

- **coord** (*Coord*) – Relative Coord (generated by `LayerList.generate_coord()` or `Lattice.generate_coord_set()`).
- **species** (*str*) – Name of species.

class `kmos.types.Coord` (***kwargs*)

Class that holds exactly one coordinate as used in the description of a process. The distinction between a *Coord* and a *Site* may seem superfluous but it is made to avoid data duplication.

Parameters

- **name** (*str*) – Name of coordinate.
- **offset** (*np.array or list*) – Offset in term of unit-cells.
- **layer** (*str*) – Name of layer.
- **tags** (*str*) – List of tags (space separated string).

pos

`pos` is `np.array((3, 1))` and is calculated from offset and position. Not to be set manually.

3.2.2 kmos.io

Features front-end import/export functions for kMC Projects. Currently import and export is supported to XML and export is supported to Fortran 90 source code.

`kmos.io.export_source` (*project_tree, export_dir=None, code_generator=None, options=None, accelerated=False*)

Export a kmos project into Fortran 90 code that can be readily compiled using `f2py`. The model contained in `project_tree` will be stored under the directory `export_dir`. `export_dir` will be created if it does not exist. The XML representation of the model will be included in the `kmc_settings.py` module.

export_source is the central feature of the *kmos* approach. In order to generate different *backend* solvers, additional candidates of this methods could be implemented.

`kmos.io.export_xml` (*project_tree, filename=None*)

Writes a project to an XML file.

class `kmos.io.ProcListWriter` (*data, dir*)

Write the different parts of Fortran 90 code needed to run a kMC model.

write_proclist (*smart=True, code_generator='local_smart', accelerated=False*)

Write the `proclist.f90` module, i.e. the rules which make up the kMC process list.

write_settings (*code_generator='lat_int', accelerated=False*)

Write the `kmc_settings.py`. This contains all parameters, which can be changed on the fly and without recompilation of the Fortran 90 modules.

3.3 Editor frontend

3.3.1 kmos.gui

A GUI frontend to create and edit kMC models.

class `kmos.gui.Editor`
The editor GUI frontend.

class `kmos.gui.GTKProject` (*parent, menubar*)
A facade of `kmos.types.Project` so that `pygtk` can display in a `TreeView`.

3.3.2 kmos.forms

3.4 Runtime frontend

3.4.1 kmos.run

A front-end module to run a compiled kMC model. The actual model is imported in `kmc_model.so` and all parameters are stored in `kmc_settings.py`.

The model can be used directly like so:

```
from kmos.model import KMC_Model
model = KMC_Model()

model.parameters.T = 500
model.do_steps(100000)
model.view()
```

which, of course can also be part of a python script.

The model can also be run in a different process using the multiprocessing module. This mode is designed for use with a GUI so that the CPU intensive kMC integration can run at full throttle without impeding the front-end. Interaction with the model happens through Queues.

class `kmos.run.ModelRunner`

Setup and initiate many runs in parallel over a regular grid of parameters. A standard type of script is given below.

To allow execution from multiple hosts connected to the same filesystem calculated points are blocked via `<classname>.lock`. To redo a calculation `<classname>.dat` and `<classname>.lock` should be moved out of the way

```
from kmos.run import ModelRunner, PressureParameter, TemperatureParameter

class ScanKinetics(ModelRunner):
    p_O2gas = PressureParameter(1)
    T = TemperatureParameter(600)
    p_COgas = PressureParameter(min=1, max=10, steps=40)
    # ... other parameters to scan

ScanKinetics().run(init_steps=1e7, sample_steps=1e7, cores=4)
```

run (*init_steps=10000000.0, sample_steps=10000000.0, cores=4, samples=1, random_seed=None*)

Launch the `ModelRunner` instance. Creates a regular grid over all `ModelParameters` defined in the `ModelRunner` class.

Parameters `init_steps` – Steps to run model before sampling (i.e. to reach steady-state).

(Default: 1e8) :type init_steps: int :param sample_steps: Number of steps to sample over (Default: 1e8) :type sample_steps: int :param cores: Number of parallel processes to launch. :type cores: int :param samples: Number of samples. Use more samples if precise coverages are needed (Default: 1). :type samples: int

class `kmos.run.ModelParameter` (*min*, *max=None*, *steps=1*, *type=None*, *unit=''*)

A model parameter to be scanned. If instantiated with only one value this parameter will be fixed at this value.

Use a subclass for specific type of grid.

Parameters

- **min** (*float*) – Minimum value for this parameter.
- **max** (*float*) – Maximum value for this parameter (Default: min)
- **steps** (*int*) – Number of steps between minimum and maximum.

class `kmos.run.PressureParameter` (**args*, ***kwargs*)

Create a grid of p in $[p_{\min}, p_{\max}]$ such that $\ln(\{p\})$ is a regular grid.

class `kmos.run.TemperatureParameter` (**args*, ***kwargs*)

Create a grid of p in $[T_{\min}, T_{\max}]$ such that $(\{T\})^{*-1}$ is a regular grid.

class `kmos.run.LinearParameter` (**args*, ***kwargs*)

Create a regular grid between min and max.

class `kmos.run.LogParameter` (**args*, ***kwargs*)

Create a log grid between 10^{\min} and 10^{\max} (like `np.logspace`)

class `kmos.run.KMC_Model` (*image_queue=None*, *parameter_queue=None*, *signal_queue=None*, *size=None*, *system_name='kmc_model'*, *banner=True*, *print_rates=False*, *autosend=True*, *steps_per_frame=50000*, *random_seed=None*, *cache_file=None*, *buffer_parameter=None*, *threshold_parameter=None*, *sampling_steps=None*, *execution_steps=None*, *save_limit=None*)

API Front-end to initialize and run a kMC model using python bindings. Depending on the constructor call the model can be run either via directory calls or in a separate processes access via multiprocessing.Queues. Only one model instance can exist simultaneously per process.

_adjust_database ()

Set the database of processes currently possible according to the current configuration.

_get_configuration ()

Return current configuration of model.

Return type `np.array`

_put (*site*, *new_species*, *reduce=False*)

Works exactly like `put`, but without updating the database of available processes. This is faster for when one does a lot updates at once, however one must call `_adjust_database` afterwards.

Examples

```
model._put([0,0,0,model.lattice.lattice_bridge], model.proclist.co)
# puts a CO molecule at the `bridge` site of the lower left unit cell

model._put([1,0,0,model.lattice.lattice_bridge], model.proclist.co )
# puts a CO molecule at the `bridge` site one to the right

# ... many more

model._adjust_database() # Important !
```

Parameters

- **site** (*list or np.array*) – Site where to put the new species, i.e. [x, y, z, bridge]
- **new_species** (*str*) – Name of new species.
- **reduce** (*bool*) – Of periodic boundary conditions if site falls out site lattice (Default: False)

_set_configuration (*config*)

Set the current lattice configuration.

Expects a 4-dimensional array, with dimensions [X, Y, Z, N] where X, Y, Z are the lattice size and N the number of sites in each unit cell.

Parameters config (*np.array*) – Configuration to set for model. Shape of array has to match with model size.

deallocate ()

Deallocate all arrays that are allocated by the Fortran module. This needs to be called whenever more than one simulation is started from one process.

Note that the current state and history of the system is lost after calling this method.

Note: explicit invocation was chosen over the `__del__` method because there seems to be an easy portable way to control garbage collection.

do_steps (*n=10000, progress=False*)

Propagate the model *n* steps.

Parameters n (*int*) – Number of steps to run (Default: 10000)

double ()

Double the size of the model in each direction and initialize larger model with current configuration in each copy.

dump_config (*filename*)

Use numpy mechanism to store current configuration in a file.

Parameters filename (*str*) – Name of file, to write configuration to.

export_movie (*frames=30, skip=1, prefix='movie', rotation='15z, -70x', suffix='png', verbose=False, **kwargs*)

Export series of snapshots of model instance to an image file in the current directory which allows for easy post-processing of images, e.g. using *ffmpeg*

```
avconv -i movie_%06d.png -r 24 movie.avi
```

or

```
ffmpeg -i movie_%06d.png -f image2 -r 24 movie.avi
```

Allows suffixes are png, pov, and eps. Additional keyword arguments (kwargs) are passed directly to the `ase.io.write` of the ASE library.

When exporting to `*.pov`, one has to manually `povray` each `*.pov` file in the directory which is as simple as typing

```
for pov_file in *.pov
do
    povray ${pov_file}
done
```

using bash.

param frames Number of frames to records (Default: 30).

type frames *int*

param skip Number of kMC steps between frames (Default: 1).

type skip int

param prefix Prefix for filename (Default: movie).

:type

```
##!—— A. Garhammer 2015—— ##!subroutine update_clocks_acf(ran_time) ##!****f*
base/update_clocks_acf ##! FUNCTION ##! Updates walltime, kmc_step, kmc_step_acf,
time_intervalls and kmc_time. ##! ##! ARGUMENTS ##! ##! *
ran_time Random real number  $\in [0, 1]$  ##!***** ##! !real(kind=rsingle), intent(in)
:: ran_time ##!real(kind=rsingle) :: runtime ##! ##! ##! Make sure ran_time is
in the right interval ##!ASSERT(ran_time.ge.0.,"base/update_clocks: ran_time variable has
to be positive.") ##!ASSERT(ran_time.le.1.,"base/update_clocks: ran_time variable has to
be less than 1.") ##! ##! !kmc_time_step = -log(ran_time)/accum_rates(nr_of_proc) ##!
! Make sure the difference is not so small, that it is rounded off ##! AS-
SSERT(kmc_time+kmc_time_step>kmc_time,"base/update_clocks: precision of kmc_time is not suf-
ficient") ##! ##! !call CPU_TIME(runtime) ##! ##! Make sure we are not dividing by zero
```

prefix:
str

param rotation Angle from which movie is recorded (only useful if suffix is png).

String to be interpreted by ASE (Default: '15x,-70x')

type rotation str

param suffix File suffix (type) of exported file (Default: png).

type suffix str

get_atoms (*geometry=True, tag=None, reset_time_overrun=False*)

Return an ASE Atoms object with additional information such as coverage and Turn-over-frequencies attached.

The additional attributes are:

- *info* (extra tags assigned to species)
- *kmc_step*
- *kmc_time*
- *occupation*
- *procstat*
- *integ_rates*
- *tof_data*

tof_data contains previously defined TOFs in reaction per seconds per cell sampled since the last call to *get_atoms()*

info can be used to better visualize similar looking molecule during post-processing

procstat holds the number of times each process was executed since last *get_atoms()* call.

Parameters geometry (*bool*) – Return ASE object of current configuration (Default: True).

get_backend ()

Return name of backend that model was compiled with.

Return type str

get_occupation_header ()

Return the names of the fields returned by *self.get_atoms().occupation*. Useful for the header line of an ASCII output.

get_param_header ()

Return the names of field return by `self.get_atoms().params`. Useful for the header line of an ASCII output.

get_std_sampled_data (*samples*, *sample_size*, *tof_method='integ'*, *output='str'*, *show_progress=False*)

Sample an average model and return TOFs and coverages in a standardized format :

[parameters] [TOFs] [occupations] kmc_time kmc_step

Parameter `tof_method` allows to switch between two different methods for evaluating turn-over-frequencies. The default method `procstat` evaluates the `procstat` counter, i.e. simply the number of executed events in the simulated time interval. `integ` will evaluate the number of times the reaction *could* be evaluated in the simulated time interval based on the local configurations and the rate constant.

Credit for this latter method has to be given to Sebastian Matera for the idea and implementation.

In each case check carefully that the observable is sampled good enough!

Parameters

- **samples** – Number of batches to average coverages over.
- **sample_size** (*int*) – Number of kMC steps in total.
- **tof_method** (*str*) – Method of how to sample TOFs. Possible values are `procrates` or `integ`. While `procrates` only counts the processes actually executed, `integ` evaluates the configuration to estimate the actual rates. The latter can be several orders more efficient for very slow processes. Differences resulting from the two methods can be used as an estimate for the statistical error in samples.

get_tof_header ()

Return the names of the fields returned by `self.get_atoms().tof_data`. Useful for the header line of an ASCII output.

halve ()

Halve the size of the model and initialize each site in the new model with a species randomly drawn from the sites that are reduced onto one. It is necessary that the simulation size is even.

load_config (*filename*)

Use numpy mechanism to load configuration from a file. User must ensure that size of stored configuration is correct.

Parameters `filename` (*str*) – Name of file, to write configuration to.

nr2site (*n*)

Accepts a site index and return the site in human readable coordinates.

Parameters `n` (*int*) – Index of site.

Return type `str`

post_mortem (*steps=None*, *propagate=False*, *err_code=None*)

Accepts an integer and generates a post-mortem report by running that many steps and returning which process would be executed next without executing it.

Parameters

- **steps** (*int*) – Number of steps to run before exit occurs (Default: `None`).
- **propagate** (*bool*) – Run this one more step, where error occurs (Default: `False`).
- **err_code** (*str*) – Error code generated by backend if `project.meta.debug > 0` at compile time.

print_accum_rate_summation (*order='-rate'*, *to_stdout=True*)

Shows rate individual processes contribute to the total rate

The optional argument order can be one of: name, rate, rate_constant, nrofsites. You precede each keyword with a '-', to show in decreasing order. Default: '-rate'. Possible values are rate, rate_constant, name, nrofsites .

print_adjustable_parameters (*match=None, to_stdout=True*)

Print those methods that are adjustable via the GUI.

Parameters *pattern* (*str*) – fname pattern to limit the parameters.

print_coverages (*to_stdout=True*)

Show coverages (per unit cell) for each species and site type for current configurations.

procstat_normalized (*match=None*)

Print an overview view process names along with the number of times it has been executed divided by the current rate constant times the kmc time.

Can help to find those processes which are kinetically hindered.

Parameters *match* (*str*) – fname pattern to filter matching parameter name.

procstat_pprint (*match=None*)

Print an overview view process names along with the number of times it has been executed.

Parameters *match* (*str*) – fname pattern to filter matching parameter name.

put (*site, new_species, reduce=False*)

Puts *new_species* at *site*. The *site* is given by 4-entry sequence like [x, y, z, n], where the first 3 entries define the unit cell from 0 to the number of unit cells in the respective direction. And *n* specifies the site within the unit cell.

The database of available processes will be updated automatically.

Examples

```
model.put([0,0,0,model.lattice.site], model.proclist.co )
# puts a CO molecule at the `bridge` site
# of the lower left unit cell
```

Parameters

- **site** (*list* or *np.array*) – Site where to put the new species, i.e. [x, y, z, bridge]
- **new_species** (*str*) – Name of new species.
- **reduce** (*bool*) – Of periodic boundary conditions if site falls out site lattice (Default: False)

run ()

Runs the model indefinitely. To control the simulations, model must have been initialized with proper Queues.

show (**args, **kwargs*)

Visualize the current configuration of the model using ASE ag.

start ()

Start child process

view ()

Start current model in live view mode.

xml ()

Returns the XML representation that this model was created from.

Return type *str*

class `kmos.run.Model_Rate_Constants`

Holds all rate constants currently associated with the model. To inspect the expression and current settings of it you can just call it as a function with a (glob) pattern that matches the desired processes, e.g.

```
model.rate_constant('*ads*')
```

could print all rate constants for adsorption. Given of course that 'ads' is part of the process name. The just get the rate constant for one specific process you can use

```
model.rate_constant.by_name("<process name>")
```

To set rate constants manually use

```
model.rate_constants.set("<pattern>", <rate-constant (expr.)>)
```

`__call__` (*pattern=None, interactive=False, model=None*)

Return rate constants.

Parameters

- **pattern** (*str*) – fname pattern to filter matching parameter name.
- **model** (*kmos Model*) – runtime instance of kMC to extract rate constants from (optional)

by_name (*proc*)

Return rate constant currently set for *proc*

Parameters **proc** (*str*) – Name of process.

inverse (*interactive=False*)

Return inverse list of rate constants.

class `kmos.run.Model_Parameters` (*print_rates=True*)

Holds all user defined parameters of a model in concise form. All user defined parameters can be accessed and set as attributes, like so

```
model.parameters.<parameter> = X.Y
```

`__call__` (*match=None, interactive=False*)

Return parameters that match 'pattern'

Parameters **match** (*str*) – fname pattern to filter matching parameter name.

3.4.2 kmos.view

Run and view a kMC model. For this to work one needs a `kmc_model(so/pyd)` and a `kmc_settings.py` in the import path.

class `kmos.view.KMC_Viewer` (*model=None, steps_per_frame=50000*)

A graphical front-end to run, manipulate and view a kMC model.

exit (*_widget, _event*)

Exit the viewer application cleanly killing all subprocesses before the main process.

parameter_callback (*name, value*)

Sent (updated) parameters to the model process.

3.4.3 kmos.cli

Entry point module for the command-line interface. The `kmos` executable should be on the program path, import this modules main function and run it.

To call `kmos` command as you would from the shell, use

```
kmos.cli.main('...')
```

Every command can be shortened as long as it is non-ambiguous, e.g.

```
kmos ex <xml-file>
```

instead of

```
kmos export <xml-file>
```

etc.

`kmos.cli.main` (*args=None*)

The CLI main entry point function.

The optional argument *args*, can be used to directly supply command line argument like

\$ `kmos <args>`

otherwise *args* will be taken from STDIN.

3.4.4 kmos.utils

Several utility functions that do not seem to fit somewhere else.

`kmos.utils.build` (*options*)

Build binary with f2py binding from complete set of source file in the current directory.

`kmos.utils.evaluate_kind_values` (*infile, outfile*)

Go through a given file and dynamically replace all selected `int/real_kind` calls with the dynamically evaluated fortran code using only code that the function itself contains.

`kmos.utils.get_ase_constructor` (*atoms*)

Return the ASE constructor string for *atoms*.

`kmos.utils.split_sequence` (*seq, size*)

Take a list and a number *n* and return list divided into *n* sublists of roughly equal size.

`kmos.utils.write_py` (*fileobj, images, **kwargs*)

Write a ASE atoms construction string for *images* into *fileobj*.

3.5 kmos kMC project DTD

The central storage and exchange format is XML. XML was chosen over JSON, pickle or alike because it still seems as the most flexible and universal format with good methods to define the overall structure of the data.

One way to define an XML format is by using a document type description (DTD) and in fact at every import a kmos file is validated against the DTD below.

```
<!ELEMENT kmc (meta?,species_list?,parameter_list?, lattice, process_list?,output_
↪list?)>
  <!ATTLIST kmc
    version CDATA #REQUIRED
  >
  <!ELEMENT meta EMPTY>
  <!ATTLIST meta
    author CDATA #IMPLIED
    debug CDATA #IMPLIED
    email CDATA #IMPLIED
    model_dimension CDATA #IMPLIED
    model_name CDATA #IMPLIED
  >
```

```

<!ELEMENT species_list (species)*>
<!ATTLIST species_list
  default_species CDATA #IMPLIED
>
<!ELEMENT species EMPTY>
<!ATTLIST species
  name CDATA #REQUIRED
  color CDATA #IMPLIED
  representation CDATA #IMPLIED
  tags CDATA #IMPLIED
>
<!ELEMENT parameter_list (parameter)*>
<!ELEMENT parameter EMPTY>
<!ATTLIST parameter
  name CDATA #REQUIRED
  value CDATA #IMPLIED
  adjustable CDATA #IMPLIED
  min CDATA #IMPLIED
  max CDATA #IMPLIED
  scale CDATA #IMPLIED
>
<!ELEMENT lattice (layer)*>
<!ATTLIST lattice
  cell_size CDATA #REQUIRED
  default_layer CDATA #REQUIRED
  substrate_layer CDATA #IMPLIED
  representation CDATA #IMPLIED
>
<!ELEMENT layer (site)*>
<!ATTLIST layer
  name CDATA #REQUIRED
  grid CDATA #IMPLIED
  grid_offset CDATA #IMPLIED
  color CDATA #IMPLIED
>
<!ELEMENT site EMPTY>
<!ATTLIST site
  pos CDATA #REQUIRED
  type CDATA #REQUIRED
  tags CDATA #IMPLIED
  default_species CDATA #IMPLIED
>
<!ELEMENT process_list (process)*>
  <!ELEMENT process (condition|action)*>
    <!ATTLIST process
      name CDATA #REQUIRED
      rate_constant CDATA #REQUIRED
      enabled CDATA #IMPLIED
      tof_count CDATA #IMPLIED
    >
    <!ELEMENT condition EMPTY>
    <!ATTLIST condition
      coord_name CDATA #REQUIRED
      coord_layer CDATA #REQUIRED
      coord_offset CDATA #REQUIRED
      species CDATA #REQUIRED
      implicit CDATA #IMPLIED
    >
    <!ELEMENT action EMPTY>
    <!ATTLIST action
      coord_name CDATA #REQUIRED
      coord_layer CDATA #REQUIRED

```

```
coord_offset CDATA #REQUIRED
species CDATA #REQUIRED
>
<!ELEMENT output_list (output)*>
  <!ELEMENT output EMPTY>
  <!ATTLIST output
    item CDATA #REQUIRED
  >
```

3.6 Backends

In general the backend includes all functions that are implemented in Fortran90, which therefore should not have to be changed by hand often. The backend is divided into three modules, which import each other in the following way

```
base <- lattice <- proclist
```

The key for this division is reusability of the code. The *base* module implement all aspects of the kMC code, which do not depend on the described model. Thus it “never” has to change. The *lattice* module basically repeats all methods of the *base* model in terms of lattice coordinates. Thus the *lattice* module only changes, when the geometry of the model changes, *e.g.* when you add or delete sites. The *proclist* module implements the process list, that is the species or states each site can have and the elementary steps. Typically that changes most often while developing a model.

The rate constants and physical parameters of the system are not implemented in the backend at all, since in the physical sense they are too high-level to justify encoding and compilation at the Fortran level and so they are typical read and parsed from a python script.

The *kmos.run.KMC_Model* class implements a convenient interface for most of these functions, however all public methods (in Fortran called subroutines) and variables can also be accessed directly like so

```
from kmos.run import KMC_Model
model = KMC_Model(print_rates=False, banner=False)
model.base.<TAB>
model.lattice.<TAB>
model.proclist.<TAB>
```

which works best in conjunction with [ipython](#).

3.6.1 local_smart

kmos/base

The base kMC module, which implements the kMC method on a $d = 1$ lattice. Virtually any lattice kMC model can be build on top of this. The methods offered are:

- de/allocation of memory
- book-keeping of the lattice configuration and all available processes
- updating and tracking kMC time, kMC step and wall time
- saving and reloading the current state
- determine the process and site to be executed

base/accum_rates

Stores the accumulated rate constant multiplied with the number of sites available for that process to be used by `determine_procsite`. Let `c` be the rate constants `n` the number of available sites, and `a` the accumulated rates, then a_i is calculated according to $a_i = \sum_{j=1}^i c_j n_j$.

base/add_proc

The main idea of this subroutine is described in `del_proc`. Adding one process to one capability is programmatically simpler since we can just add it to the end of the respective array in `avail_sites`.

- `proc` positive integer number that represents the process to be added.
- `site` positive integer number that represents the site to be manipulated

base/allocate_system

Allocates all book-keeping structures and stores local copies of system name and size(s):

- `system_name` identifier of this simulation, used as name of punch file
- `volume` the total number of sites
- `nr_of_proc` the total number of processes

base/assertion_fail

Function that shall be used by all parts of the program to print a proper message in case some assertion fails.

- `a` a condition that is supposed to hold true
- `r` message that is printed to the poor user in case it fails

base/avail_sites

Main book-keeping array that stores for each process the sites that are available and for each site the address in this very array. The meaning of the fields are:

`avail_sites(proc, field, switch)`

where:

- `proc` – refers to a process in the process list
- the `field` within the process, but the meaning differs as explained under ‘`switch`’
- `switch` – can be either 1 or 2 and switches between (1) the actual numbers of the sites, which are available and filled in from the left but in whatever order they come or (2) the location where the site is stored in (1).

base/can_do

Returns true if ‘`site`’ can do ‘`proc`’ right now

- `proc` integer representing the requested process.
- `site` integer representing the requested site.
- `can` writeable boolean, where the result will be stored.

base/deallocate_system

Deallocate all allocatable arrays: `avail_sites`, `lattice`, `rates`, `accum_rates`, `integ_rates`, `procstat`.

`none`

base/del_proc

`del_proc` delete one process from the main book-keeping array `avail_sites`. These book-keeping operations happen in $O(1)$ time with the help of some more book-keeping overhead. `avail_sites` stores for each process all sites that are available. The array for each process is filled from the left, but sites generally not ordered. With this `determine_procsite` can effectively pick the next site and process. On the other hand a second array (`avail_sites(:,2)`) holds for each process and each site, the location where it is stored in `avail_site(:,1)`. If a site needs to be removed this subroutine first looks up the location via `avail_sites(:,1)` and replaces it with the site that is stored as the last element for this process.

- `proc` positive integer that states the process
- `site` positive integer that encodes the site to be manipulated

base/determine_procsite

Expects two random numbers between 0 and 1 and determines the corresponding process and site from `accum_rates` and `avail_sites`. Technically one random number would be sufficient but to circumvent issues with wrong `interval_search_real` implementation or rounding errors I decided to take two random numbers:

- `ran_proc` Random real number from $\in [0, 1]$ that selects the next process
- `ran_site` Random real number from $\in [0, 1]$ that selects the next site
- `proc` Return integer $\in [1, nr_of_proc]$
- `site` Return integer $\in [1, volume]$

base/get_accum_rate

Return accumulated rate at a given process.

- `proc_nr` integer representing the requested process.
- `return_accum_rate` writeable real, where the requested accumulated rate will be stored.

base/get_avail_site

Return field from the `avail_sites` database

- `proc_nr` integer representing the requested process.
- `field` integer for the site at question
- `switch` 1 or 2 for site or storage location

base/get_integ_rate

Return integrated rate at a given process.

- `proc_nr` integer representing the requested process.

- `return_integ_rate` writeable real, where the requested integrated rate will be stored.

base/get_kmc_step

Return the current `kmc_step`

- `kmc_step` Writeable integer

base/get_kmc_time

Returns current `kmc_time` as rdouble real as defined in `kind_values.f90`.

- `return_kmc_time` writeable real, where the `kmc_time` will be stored.

base/get_kmc_time_step

Returns current `kmc_time_step` (the time increment).

- `return_kmc_step` writeable real, where the `kmc_time_step` will be stored.

base/get_kmc_volume

Return the total number of sites.

- `volume` Writeable integer.

base/get_nrofsites

Return how many sites are available for a certain process. Usually used for debugging

- `proc` integer representing the requested process
- `return_nrofsites` writeable integer, where nr of sites gets stored

base/get_procstat

Return process counter for process `proc` as integer.

- `proc` integer representing the requested process.
- `return_procstat` writeable integer, where the process counter will be stored.

base/get_rate

Return rate of given process.

- `proc_nr` integer representing the requested process.
- `return_rate` writeable real, where the requested rate will be stored.

base/get_species

Return the species that occupies site.

- `site` integer representing the site

base/get_system_name

Return the systems name, that was specified with base/allocate_system

- `system_name` Writeable string of type character(len=200).

base/get_walltime

Return the current walltime.

- `return_walltime` writeable real where the walltime will be stored.

base/increment_procstat

Increment the process counter for process proc by one.

- `proc` integer representing the process to be increment.

base/integ_rates

Stores the time-integrated rates (non-normalized to surface area) Used to determine reaction rates, i.e. average number of reactions per unit surface and time. Let \mathbf{a} the integrated rates, \mathbf{c} be the rate constants, \mathbf{n}_i the number of available sites during kMC-time interval i , $\{\Delta t_i\}$ the corresponding timesteps then $a_i(t)$ at the time $t = \sum_{i=1} \Delta t_i$ is calculated according to $a_i(t) = \sum_{i=1} c_i n_i \Delta t_i$.

base/interval_search_real

This is basically a standard binary search algorithm that expects an array of ascending real numbers and a scalar real and return the key of the corresponding field, with the following modification :

- the value of the returned field is equal of larger of the given value. This is important because the given value is between 0 and the largest value in the array and otherwise the last field is never selected.
- if two or more values in the array are identical, the function return the index of the leftmost of those field. This is important because having field with identical values means that all field except the leftmost one do not contain any sites. Refer to `update_accum_rate` to understand why.
- the value of the returned field may no be zero. Therefore the index the to be equal or larger than the first non-zero field.

However: as everyone knows the binary search is trickier than it appears at first site especially real numbers. So intensive testing is suggested here!

- `arr` real array of type `rsingle` (`kind_values.f90`) in monotonically (not strictly) increasing order
- `value` real positive number from $[0, \text{max_arr_value}]$

base/kmc_step

Number of kMC steps executed.

base/kmc_time

Simulated kMC time in this run in seconds.

base/kmc_time_step

The time increment of the current kMC step.

base/lattice

Stores the actual physical lattice in a 1d array, where the value on each slot represents the species on that site.

Species constants can be conveniently defined in `lattice_...` and later used directly in the process list.

base/nr_of_proc

Total number of available processes.

base/nr_of_sites

Stores the number of sites available for each process.

base/procstat

Stores the total number of times each process has been executed during one simulation.

base/rates

Stores the rate constants for each process in s^{-1} .

base/reload_system

Restore state of simulation from *.reload file as saved by `save_system()`. This function also allocates the system's memory so calling `allocate_system` again, will cause a runtime failure.

- `system_name` string of 200 characters which will make the `reload_system` look for a file called `./<system_name>.reload`
- `reloaded` logical return variable, that is `.true.` reload of system could be completed successfully, and `.false.` otherwise.

base/replace_species

Replaces the species at a given site with `new_species`, given that `old_species` is correct, i.e. identical to the site that is already there.

- `site` integer representing the site
- `old_species` integer representing the species to be removed
- `new_species` integer representing the species to be placed

base/reset_site

This function is a higher-level function to reset a site as if it never existed. To achieve this the species is set to null_species and all available processes are stripped from the site via del_proc.

- `site` integer representing the requested site.
- `species` integer representing the species that ought to be at the site, for consistency checks

base/save_system

save_system stores the entire system information in a simple ASCII file named `<system_name>.reload`. All fields except `avail_sites` are stored in the simple scheme:

variable value

In the case of array variables, multiple values are separated by one or more spaces, and the record is terminated with a newline. The variable `avail_sites` is treated slightly differently, since printed on a single line it is almost impossible to interpret from the ASCII files. Instead each process starts a new line, and the first number on the line stands for the process number and the remaining fields, hold the values.

none

base/set_kmc_time

Sets current `kmc_time` as `rdouble` real as defined in `kind_values.f90`.

- `new` readable real, that the kmc time will be set to

base/set_rate_const

Allows to set the rate constant of the process with the number `proc_nr`.

- `proc_n` The process number as defined in the corresponding `proclist_module`.
- `rate` the rate in s^{-1}

base/set_system_name

Set the systems name. Useful in conjunction with `base.save_system` to save `*.reload` files under a different name than the default one.

- `system_name` Readable string of type `character(len=200)`.

base/start_time

CPU time spent in simulation at least reload.

base/system_name

Unique identifier of this simulation to be used for restart files. This name should not contain any characters that you don't want to have in a filename either, i.e. only `[A-Za-z0-9_-]`.

base/update_accum_rate

Updates the vector of accum_rates.

none

base/update_clocks

Updates walltime, kmc_step and kmc_time.

- `ran_time` Random real number $\in [0, 1]$

base/update_integ_rate

Updates the vector of integ_rates.

none

base/volume

Total number of sites.

base/walltime

Total CPU time spent on this simulation.

kmos/lattice

Implements the mappings between the real space lattice and the 1-D lattice, which kmos/base operates on. Furthermore replicates all geometry specific functions of kmos/base in terms of lattice coordinates. Using this module each site can be addressed with 4-tuple (i, j, k, n) where i, j, k define the unit cell and n the site within the unit cell.

lattice/allocate_system

Allocates system, fills mapping cache, and checks whether mapping is consistent

none

lattice/calculate_lattice2nr

Maps all lattice coordinates onto a continuous set of integer $\in [1, volume]$

- `site` integer array of size (4) a lattice coordinate

lattice/calculate_nr2lattice

Maps a continuous set of integers $\in [1, volume]$ to a 4-tuple representing a lattice coordinate

- `nr` integer representing the site index

lattice/deallocate_system

Deallocates system including mapping cache.

none

lattice/default_layer

The layer in which the model is initially in by default (only relevant for multi-lattice models).

lattice/lattice2nr

Caching array holding the mapping from index to lattice coordinate: $(x, y, z, n) \rightarrow i$.

lattice/model_dimension

Store the number of dimensions of this model: 1, 2, or 3

lattice/nr2lattice

Caching array holding the mapping from index to lattice coordinate: $i \rightarrow (x, y, z, n)$.

lattice/nr_of_layers

Constant storing the number of layers (for multi-lattice models > 1)

lattice/site_positions

The positions of (adsorption) site in the unit cell in fractional coordinates.

lattice/spuck

spuck = Sites Per Unit Cell Konstant The number of sites per unit cell, i.e. for coordinate notation (x, y, n) this is the maximum value of n .

lattice/system_size

Stores the current size of the allocated system lattice (x, y, z) in an integer array. In low-dimensional system, corresponding entries will be set to 1. Note that this should be thought of as a read-only variable. Changing its value at model runtime will not the indented effect of actually changing the simulated lattice. The definitive location for custom lattice size is *simulation_size* in *kmc_settings.py*.

If the system size shall be changed programmatically, it needs to happen before the *KMC_Model* is instantiated and Fortran array are allocated accordingly, like to

```
#!/usr/bin/env python
import kmc_settings import kmos.run
kmc_settings.simulation_size = 9, 9, 4
with kmos.run.KMC_Model() as model: print(model.lattice.system_size)))'
```

lattice/unit_cell_size

The dimensions of the unit cell (e.g. in Angstrom) of the unit cell.

kmos/proclist

Implements the kMC process list.

proclist/do_kmc_step

Performs exactly one kMC step. * first update clock * then configuration sampling step * last execute process

none

proclist/do_kmc_steps

Performs *n* kMC step. If one has to run many steps without evaluation `do_kmc_steps` might perform a little better. * first update clock * then configuration sampling step * last execute process

n : Number of steps to run

proclist/get_kmc_step

Determines next step without executing it.

none

proclist/get_occupation

Evaluate current lattice configuration and returns the normalized occupation as matrix. Different species run along the first axis and different sites run along the second.

none

proclist/init

Allocates the system and initializes all sites in the given layer.

- `input_system_size` number of unit cell per axis.
- `system_name` identifier for reload file.
- `layer` initial layer.
- `no_banner` [optional] if True no copyright is issued.

proclist/initialize_state

Initialize all sites and book-keeping array for the given layer.

- `layer` integer representing layer

proclist/run_proc_nr

Runs process `proc` on site `nr_site`.

- `proc` integer representing the process number
- `nr_site` integer representing the site

libkmc/kind_values

This module offers `kind_values` for commonly used intrinsic types in a platform independent way.

3.6.2 lat_int

kmos/base

The base kMC module, which implements the kMC method on a $d = 1$ lattice. Virtually any lattice kMC model can be build on top of this. The methods offered are:

- de/allocation of memory
- book-keeping of the lattice configuration and all available processes
- updating and tracking kMC time, kMC step and wall time
- saving and reloading the current state
- determine the process and site to be executed

base/accum_rates

Stores the accumulated rate constant multiplied with the number of sites available for that process to be used by `determine_procsite`. Let `c` be the rate constants `n` the number of available sites, and `a` the accumulated rates, then a_i is calculated according to $a_i = \sum_{j=1}^i c_j n_j$.

base/add_proc

The main idea of this subroutine is described in `del_proc`. Adding one process to one capability is programmatically simpler since we can just add it to the end of the respective array in `avail_sites`.

- `proc` positive integer number that represents the process to be added.
- `site` positive integer number that represents the site to be manipulated

base/allocate_system

Allocates all book-keeping structures and stores local copies of system name and size(s):

- `system_name` identifier of this simulation, used as name of punch file
- `volume` the total number of sites
- `nr_of_proc` the total number of processes

base/assertion_fail

Function that shall be used by all parts of the program to print a proper message in case some assertion fails.

- `a` a condition that is supposed to hold true
- `r` message that is printed to the poor user in case it fails

base/avail_sites

Main book-keeping array that stores for each process the sites that are available and for each site the address in this very array. The meaning of the fields are:

```
avail_sites(proc, field, switch)
```

where:

- `proc` – refers to a process in the process list
- the `field` within the process, but the meaning differs as explained under ‘switch’
- `switch` – can be either 1 or 2 and switches between (1) the actual numbers of the sites, which are available and filled in from the left but in whatever order they come or (2) the location where the site is stored in (1).

base/can_do

Returns true if ‘site’ can do ‘proc’ right now

- `proc` integer representing the requested process.
- `site` integer representing the requested site.
- `can` writeable boolean, where the result will be stored.

base/deallocate_system

Deallocate all allocatable arrays: `avail_sites`, `lattice`, `rates`, `accum_rates`, `procstat`.

none

base/del_proc

`del_proc` delete one process from the main book-keeping array `avail_sites`. These book-keeping operations happen in $O(1)$ time with the help of some more book-keeping overhead. `avail_sites` stores for each process all sites that are available. The array for each process is filled from the left, but sites generally not ordered. With this `determine_procsite` can effectively pick the next site and process. On the other hand a second array (`avail_sites(:,2)`) holds for each process and each site, the location where it is stored in `avail_site(:,1)`. If a site needs to be removed this subroutine first looks up the location via `avail_sites(:,1)` and replaces it with the site that is stored as the last element for this process.

- `proc` positive integer that states the process
- `site` positive integer that encodes the site to be manipulated

base/determine_procsite

Expects two random numbers between 0 and 1 and determines the corresponding process and site from `accum_rates` and `avail_sites`. Technically one random number would be sufficient but to circumvent issues with wrong `interval_search_real` implementation or rounding errors I decided to take two random numbers:

- `ran_proc` Random real number from $\in [0, 1]$ that selects the next process
- `ran_site` Random real number from $\in [0, 1]$ that selects the next site
- `proc` Return integer $\in [1, nr_of_proc]$
- `site` Return integer $\in [1, volume]$

base/get_accum_rate

Return accumulated rate at a given process.

- `proc_nr` integer representing the requested process.
- `return_accum_rate` writeable real, where the requested accumulated rate will be stored.

base/get_avail_site

Return field from the `avail_sites` database

- `proc_nr` integer representing the requested process.
- `field` integer for the site at question
- `switch` 1 or 2 for site or storage location

base/get_integ_rate

Return integrated rate at a given process.

- `proc_nr` integer representing the requested process.
- `return_integ_rate` writeable real, where the requested integrated rate will be stored.

base/get_kmc_step

Return the current `kmc_step`

- `kmc_step` Writeable integer

base/get_kmc_time

Returns current `kmc_time` as `rdouble` real as defined in `kind_values.f90`.

- `return_kmc_time` writeable real, where the `kmc_time` will be stored.

base/get_kmc_time_step

Returns current `kmc_time_step` (the time increment).

- `return_kmc_step` writeable integer, where the `kmc_time_step` will be stored.

base/get_kmc_volume

Return the total number of sites.

- `volume` Writeable integer.

base/get_nrofsites

Return how many sites are available for a certain process. Usually used for debugging

- `proc` integer representing the requested process
- `return_nrofsites` writeable integer, where nr of sites gets stored

base/get_procstat

Return process counter for process `proc` as integer.

- `proc` integer representing the requested process.
- `return_procstat` writeable integer, where the process counter will be stored.

base/get_rate

Return rate of given process.

- `proc_nr` integer representing the requested process.
- `return_rate` writeable real, where the requested rate will be stored.

base/get_species

Return the species that occupies site.

- `site` integer representing the site

base/get_system_name

Return the systems name, that was specified with `base/allocate_system`

- `system_name` Writeable string of type `character(len=200)`.

base/get_walltime

Return the current walltime.

- `return_walltime` writeable real where the walltime will be stored.

base/increment_procstat

Increment the process counter for process `proc` by one.

- `proc` integer representing the process to be increment.

base/integ_rates

Stores the time-integrated rates (non-normalized to surface area) Used to determine reaction rates, i.e. average number of reactions per unit surface and time. Let \mathbf{a} be the integrated rates, \mathbf{c} be the rate constants, \mathbf{n}_i the number of available sites during kMC-time interval i , $\{\Delta t_i\}$ the corresponding timesteps then $a_i(t)$ at the time $t = \sum_{i=1} \Delta t_i$ is calculated according to $a_i(t) = \sum_{i=1} c_i n_i \Delta t_i$.

base/interval_search_real

This is basically a standard binary search algorithm that expects an array of ascending real numbers and a scalar real and return the key of the corresponding field, with the following modification :

- the value of the returned field is equal or larger of the given value. This is important because the given value is between 0 and the largest value in the array and otherwise the last field is never selected.
- if two or more values in the array are identical, the function return the index of the leftmost of those field. This is important because having field with identical values means that all field except the leftmost one do not contain any sites. Refer to `update_accum_rate` to understand why.
- the value of the returned field may no be zero. Therefore the index the to be equal or larger than the first non-zero field.

However: as everyone knows the binary search is trickier than it appears at first site especially real numbers. So intensive testing is suggested here!

- `arr` real array of type `rsingle` (`kind_values.f90`) in monotonically (not strictly) increasing order
- `value` real positive number from $[0, \text{max_arr_value}]$

base/kmc_step

Number of kMC steps executed.

base/kmc_time

Simulated kMC time in this run in seconds.

base/kmc_time_step

The time increment of the current kMC step.

base/lattice

Stores the actual physical lattice in a 1d array, where the value on each slot represents the species on that site.

Species constants can be conveniently defined in `lattice_...` and later used directly in the process list.

base/nr_of_proc

Total number of available processes.

base/nr_of_sites

Stores the number of sites available for each process.

base/procstat

Stores the total number of times each process has been executed during one simulation.

base/rates

Stores the rate constants for each process in s^{-1} .

base/reload_system

Restore state of simulation from *.reload file as saved by save_system(). This function also allocates the system's memory so calling allocate_system again, will cause a runtime failure.

- `system_name` string of 200 characters which will make the reload_system look for a file called `./<system_name>.reload`
- `reloaded` logical return variable, that is `.true.` reload of system could be completed successfully, and `.false.` otherwise.

base/replace_species

Replaces the species at a given site with `new_species`, given that `old_species` is correct, i.e. identical to the site that is already there.

- `site` integer representing the site
- `old_species` integer representing the species to be removed
- `new_species` integer representing the species to be placed

base/reset_site

This function is a higher-level function to reset a site as if it never existed. To achieve this the species is set to `null_species` and all available processes are stripped from the site via `del_proc`.

- `site` integer representing the requested site.
- `species` integer representing the species that ought to be at the site, for consistency checks

base/save_system

`save_system` stores the entire system information in a simple ASCII file named `<system_name>.reload`. All fields except `avail_sites` are stored in the simple scheme:

variable value

In the case of array variables, multiple values are separated by one or more spaces, and the record is terminated with a newline. The variable `avail_sites` is treated slightly differently, since printed on a single line it is almost impossible to interpret from the ASCII files. Instead each process starts a new line, and the first number on the line stands for the process number and the remaining fields, hold the values.

none

base/set_kmc_time

Sets current kmc_time as rdouble real as defined in kind_values.f90.

- new readable real, that the kmc time will be set to

base/set_rate_const

Allows to set the rate constant of the process with the number proc_nr.

- proc_n The process number as defined in the corresponding proclist_module.
- rate the rate in s^{-1}

base/set_system_name

Set the systems name. Useful in conjunction with base.save_system to save *.reload files under a different name than the default one.

- system_name Readable string of type character(len=200).

base/start_time

CPU time spent in simulation at least reload.

base/system_name

Unique identifier of this simulation to be used for restart files. This name should not contain any characters that you don't want to have in a filename either, i.e. only [A-Za-z0-9_-].

base/update_accum_rate

Updates the vector of accum_rates.

none

base/update_clocks

Updates walltime, kmc_step and kmc_time.

- ran_time Random real number $\in [0, 1]$

base/update_integ_rate

Updates the vector of integ_rates.

none

base/volume

Total number of sites.

base/walltime

Total CPU time spent on this simulation.

kmos/lattice

Implements the mappings between the real space lattice and the 1-D lattice, which kmos/base operates on. Furthermore replicates all geometry specific functions of kmos/base in terms of lattice coordinates. Using this module each site can be addressed with 4-tuple (i, j, k, n) where i, j, k define the unit cell and n the site within the unit cell.

lattice/allocate_system

Allocates system, fills mapping cache, and checks whether mapping is consistent

none

lattice/calculate_lattice2nr

Maps all lattice coordinates onto a continuous set of integer $\in [1, volume]$

- `site` integer array of size (4) a lattice coordinate

lattice/calculate_nr2lattice

Maps a continuous set of of integers $\in [1, volume]$ to a 4-tuple representing a lattice coordinate

- `nr` integer representing the site index

lattice/deallocate_system

Deallocates system including mapping cache.

none

lattice/default_layer

The layer in which the model is initially in by default (only relevant for multi-lattice models).

lattice/lattice2nr

Caching array holding the mapping from index to lattice coordinate: $(x, y, z, n) \rightarrow i$.

lattice/model_dimension

Store the number of dimensions of this model: 1, 2, or 3

lattice/nr2lattice

Caching array holding the mapping from index to lattice coordinate: $i \rightarrow (x, y, z, n)$.

lattice/nr_of_layers

Constant storing the number of layers (for multi-lattice models > 1)

lattice/site_positions

The positions of (adsorption) site in the unit cell in fractional coordinates.

lattice/spuck

spuck = Sites Per Unit Cell Konstant The number of sites per unit cell, i.e. for coordinate notation (x, y, n) this is the maximum value of *n*.

lattice/system_size

Stores the current size of the allocated system lattice (x, y, z) in an integer array. In low-dimensional system, corresponding entries will be set to 1. Note that this should be thought of as a read-only variable. Changing its value at model runtime will not the indented effect of actually changing the simulated lattice. The definitive location for custom lattice size is *simulation_size* in *kmc_settings.py*.

If the system size shall be changed programmatically, it needs to happen before the *KMC_Model* is instantiated and Fortran array are allocated accordingly, like to

```
#!/usr/bin/env python
import kmc_settings import kmos.run
kmc_settings.simulation_size = 9, 9, 4
with kmos.run.KMC_Model() as model: print(model.lattice.system_size)))‘
```

lattice/unit_cell_size

The dimensions of the unit cell (e.g. in Angstrom) of the unit cell.

kmos/proclist

Implements the kMC process list.

proclist/do_kmc_step

Performs exactly one kMC step. * first update clock * then configuration sampling step * last execute process

none

proclist/do_kmc_steps

Performs *n* kMC step. If one has to run many steps without evaluation *do_kmc_steps* might perform a little better. * first update clock * then configuration sampling step * last execute process

n : Number of steps to run

proclist/get_kmc_step

Determines next step without executing it.

none

proclist/get_occupation

Evaluate current lattice configuration and returns the normalized occupation as matrix. Different species run along the first axis and different sites run along the second.

none

proclist/init

Allocates the system and initializes all sites in the given layer.

- `input_system_size` number of unit cell per axis.
- `system_name` identifier for reload file.
- `layer` initial layer.
- `no_banner` [optional] if True no copyright is issued.

proclist/initialize_state

Initialize all sites and book-keeping array for the given layer.

- `layer` integer representing layer

libkmc/kind_values

This module offers `kind_values` for commonly used intrinsic types in a platform independent way.

3.6.3 otf

kmos/base

The base kMC module, which implements the kMC method on a $d = 1$ lattice. Virtually any lattice kMC model can be build on top of this. The methods offered are:

- de/allocation of memory
- book-keeping of the lattice configuration and all available processes
- updating and tracking kMC time, kMC step and wall time
- saving and reloading the current state
- determine the process and site to be executed

base/accum_rates

Stores the accumulated rate constant up to a given process number taking into account all sites in which it is possible. ###

base/accum_rates_proc

Used to store the accumulated rate associated to each process ###

base/add_proc

The main idea of this subroutine is described in `del_proc`. Adding one process to one capability is programmatically simpler since we can just add it to the end of the respective array in `avail_sites`.

- `proc` positive integer number that represents the process to be added.
- `site` positive integer number that represents the site to be manipulated

base/allocate_system

Allocates all book-keeping structures and stores local copies of system name and size(s):

- `system_name` identifier of this simulation, used as name of punch file
- `volume` the total number of sites
- `nr_of_proc` the total number of processes

base/assertion_fail

Function that shall be used by all parts of the program to print a proper message in case some assertion fails.

- `a` a condition that is supposed to hold true
- `r` message that is printed to the poor user in case it fails

base/avail_sites

Main book-keeping array that stores for each process the sites that are available and for each site the address in this very array. The meaning of the fields are:

`avail_sites(proc, field, switch)`

where:

- `proc` – refers to a process in the process list
- the `field` within the process, but the meaning differs as explained under ‘`switch`’
- `switch` – can be either 1 or 2 and switches between (1) the actual numbers of the sites, which are available and filled in from the left but in whatever order they come or (2) the location where the site is stored in (1).

base/can_do

Returns true if ‘`site`’ can do ‘`proc`’ right now

- `proc` integer representing the requested process.
- `site` integer representing the requested site.
- `can` writeable boolean, where the result will be stored.

base/deallocate_system

Deallocate all allocatable arrays: `avail_sites`, `lattice`, `rates`, `accum_rates`, `procstat`.

`none`

base/del_proc

`del_proc` delete one process from the main book-keeping array `avail_sites`. These book-keeping operations happen in $O(1)$ time with the help of some more book-keeping overhead. `avail_sites` stores for each process all sites that are available. The array for each process is filled from the left, but sites generally not ordered. With this `determine_procsite` can effectively pick the next site and process. On the other hand a second array (`avail_sites(:,2)`) holds for each process and each site, the location where it is stored in `avail_site(:,1)`. If a site needs to be removed this subroutine first looks up the location via `avail_sites(:,1)` and replaces it with the site that is stored as the last element for this process.

- `proc` positive integer that states the process
- `site` positive integer that encodes the site to be manipulated

base/determine_procsite

Expects two random numbers between 0 and 1 and determines the corresponding process and site from `accum_rates` and `avail_sites`. Technically one random number would be sufficient but to circumvent issues with wrong `interval_search_real` implementation or rounding errors I decided to take two random numbers:

- `ran_proc` Random real number from $\in [0, 1]$ that selects the next process
- `ran_site` Random real number from $\in [0, 1]$ that selects the next site
- `proc` Return integer $\in [1, nr_of_proc]$
- `site` Return integer $\in [1, volume]$

base/get_accum_rate

Return accumulated rate at a given process.

- `proc_nr` integer representing the requested process.
- `return_accum_rate` writeable real, where the requested accumulated rate will be stored.

base/get_avail_site

Return field from the `avail_sites` database

- `proc_nr` integer representing the requested process.
- `field` integer for the site at question
- `switch` 1 or 2 for site or storage location

base/get_integ_rate

Return integrated rate at a given process.

- `proc_nr` integer representing the requested process.

- `return_integ_rate` writeable real, where the requested integrated rate will be stored.

base/get_kmc_step

Return the current `kmc_step`

- `kmc_step` Writeable integer

base/get_kmc_time

Returns current `kmc_time` as `rdouble` real as defined in `kind_values.f90`.

- `return_kmc_time` writeable real, where the `kmc_time` will be stored.

base/get_kmc_time_step

Returns current `kmc_time_step` (the time increment).

- `return_kmc_step` writeable integer, where the `kmc_time_step` will be stored.

base/get_kmc_volume

Return the total number of sites.

- `volume` Writeable integer.

base/get_nrofsites

Return how many sites are available for a certain process. Usually used for debugging

- `proc` integer representing the requested process
- `return_nrofsites` writeable integer, where nr of sites gets stored

base/get_procstat

Return process counter for process `proc` as integer.

- `proc` integer representing the requested process.
- `return_procstat` writeable integer, where the process counter will be stored.

base/get_rate

Return rate of given process.

- `proc_nr` integer representing the requested process.
- `return_rate` writeable real, where the requested rate will be stored.

base/get_species

Return the species that occupies site.

- `site` integer representing the site

base/get_system_name

Return the systems name, that was specified with base/allocate_system

- `system_name` Writeable string of type character(len=200).

base/get_walltime

Return the current walltime.

- `return_walltime` writeable real where the walltime will be stored.

base/increment_procstat

Increment the process counter for process proc by one.

- `proc` integer representing the process to be increment.

base/integ_rates

Stores the time-integrated rates (non-normalized to surface area) Used to determine reaction rates, i.e. average number of reactions per unit surface and time. Let \mathbf{a} the integrated rates, \mathbf{c} be the rate constants, \mathbf{n}_i the number of available sites during kMC-time interval i , $\{\Delta t_i\}$ the corresponding timesteps then $a_i(t)$ at the time $t = \sum_{i=1} \Delta t_i$ is calculated according to $a_i(t) = \sum_{i=1} c_i n_i \Delta t_i$.

base/interval_search_real

This is basically a standard binary search algorithm that expects an array of ascending real numbers and a scalar real and return the key of the corresponding field, with the following modification :

- the value of the returned field is equal or larger than given value. This is important because the given value is between 0 and the largest value in the array and otherwise the last field is never selected.
- if two or more values in the array are identical, the function return the index of the leftmost of those field. This is important because having field with identical values means that all field except the leftmost one do not contain any sites. Refer to `update_accum_rate` to understand why.
- the value of the returned field may not be zero. Therefore the index the to be equal or larger than the first non-zero field.

However: as everyone knows the binary search is trickier than it appears at first sight especially real numbers. So intensive testing is suggested here!

- `arr` real array of type `rsingle` (`kind_values.f90`) in monotonically (not strictly) increasing order
- `value` real positive number from $[0, \text{max_arr_value}]$

base/kmc_step

Number of kMC steps executed.

base/kmc_time

Simulated kMC time in this run in seconds.

base/kmc_time_step

The time increment of the current kMC step.

base/lattice

Stores the actual physical lattice in a 1d array, where the value on each slot represents the species on that site.

Species constants can be conveniently defined in `lattice_...` and later used directly in the process list.

base/nr_of_proc

Total number of available processes.

base/nr_of_sites

Stores the number of sites available for each process.

base/procstat

Stores the total number of times each process has been executed during one simulation.

base/rates

Stores the rate constants for each currently possible process ordered as `avail_sites(:,1)`.

base/rates

Stores the rate constants for each process in s^{-1} .

base/reaccumulate_rates_matrix

Performs a process wide reaccumulation of the values in the `rates_matrix`. To be used when some of the user parameters are updated. Expected to alleviate some of the problems arising from floating point errors

base/reload_system

Restore state of simulation from *.reload file as saved by `save_system()`. This function also allocates the system's memory so calling `allocate_system` again, will cause a runtime failure.

- `system_name` string of 200 characters which will make the `reload_system` look for a file called `./<system_name>.reload`
- `reloaded` logical return variable, that is `.true.` reload of system could be completed successfully, and `.false.` otherwise.

base/replace_species

Replaces the species at a given site with `new_species`, given that `old_species` is correct, i.e. identical to the site that is already there.

- `site` integer representing the site
- `old_species` integer representing the species to be removed
- `new_species` integer representing the species to be placed

base/reset_site

This function is a higher-level function to reset a site as if it never existed. To achieve this the species is set to `null_species` and all available processes are stripped from the site via `del_proc`.

- `site` integer representing the requested site.
- `species` integer representing the species that ought to be at the site, for consistency checks

base/save_system

`save_system` stores the entire system information in a simple ASCII file named `<system_name>.reload`. All fields except `avail_sites` are stored in the simple scheme:

variable value

In the case of array variables, multiple values are separated by one or more spaces, and the record is terminated with a newline. The variable `avail_sites` is treated slightly differently, since printed on a single line it is almost impossible to interpret from the ASCII files. Instead each process starts a new line, and the first number on the line stands for the process number and the remaining fields, hold the values.

none

base/set_kmc_time

Sets current `kmc_time` as `rdouble` real as defined in `kind_values.f90`.

- `new` readable real, that the `kmc` time will be set to

base/set_rate_const

Allows to set the rate constant of the process with the number `proc_nr`.

- `proc_n` The process number as defined in the corresponding `proclist_` module.
- `rate` the rate in s^{-1}

base/set_system_name

Set the systems name. Useful in conjunction with `base.save_system` to save `*.reload` files under a different name than the default one.

- `system_name` Readable string of type `character(len=200)`.

base/start_time

CPU time spent in simulation at least reload.

base/system_name

Unique identifier of this simulation to be used for restart files. This name should not contain any characters that you don't want to have in a filename either, i.e. only [A-Za-z0-9_-].

base/update_accum_rate

Updates the vector of accum_rates.

none

base/update_clocks

Updates walltime, kmc_step and kmc_time.

- `ran_time` Random real number $\in [0, 1]$

base/update_integ_rate

Updates the vector of integ_rates.

none

base/update_rates_matrix

Updates the rates_matrix. To be used when the state of a bystander has been modified

!

- `proc` positive integer number that represents the process whose rate is changed.
- `site` positive integer number that represents the site for the process
- `rate` positive real number that represents the updated rate

base/volume

Total number of sites.

base/walltime

Total CPU time spent on this simulation.

kmos/lattice

Implements the mappings between the real space lattice and the 1-D lattice, which kmos/base operates on. Furthermore replicates all geometry specific functions of kmos/base in terms of lattice coordinates. Using this module each site can be addressed with 4-tuple (i, j, k, n) where i, j, k define the unit cell and n the site within the unit cell.

lattice/allocate_system

Allocates system, fills mapping cache, and checks whether mapping is consistent

none

lattice/calculate_lattice2nr

Maps all lattice coordinates onto a continuous set of integer $\in [1, volume]$

- `site` integer array of size (4) a lattice coordinate

lattice/calculate_nr2lattice

Maps a continuous set of of integers $\in [1, volume]$ to a 4-tuple representing a lattice coordinate

- `nr` integer representing the site index

lattice/deallocate_system

Deallocates system including mapping cache.

none

lattice/default_layer

The layer in which the model is initially in by default (only relevant for multi-lattice models).

lattice/lattice2nr

Caching array holding the mapping from index to lattice coordinate: $(x, y, z, n) \rightarrow i$.

lattice/model_dimension

Store the number of dimensions of this model: 1, 2, or 3

lattice/nr2lattice

Caching array holding the mapping from index to lattice coordinate: $i \rightarrow (x, y, z, n)$.

lattice/nr_of_layers

Constant storing the number of layers (for multi-lattice models > 1)

lattice/site_positions

The positions of (adsorption) site in the unit cell in fractional coordinates.

lattice/spuck

spuck = Sites Per Unit Cell Konstant The number of sites per unit cell, i.e. for coordinate notation (x, y, n) this is the maximum value of *n*.

lattice/system_size

Stores the current size of the allocated system lattice (x, y, z) in an integer array. In low-dimensional system, corresponding entries will be set to 1. Note that this should be thought of as a read-only variable. Changing its value at model runtime will not have the intended effect of actually changing the simulated lattice. The definitive location for custom lattice size is *simulation_size* in *kmc_settings.py*.

If the system size shall be changed programmatically, it needs to happen before the *KMC_Model* is instantiated and Fortran array are allocated accordingly, like to

```
#!/usr/bin/env python
import kmc_settings import kmos.run
kmc_settings.simulation_size = 9, 9, 4
with kmos.run.KMC_Model() as model: print(model.lattice.system_size))'
```

lattice/unit_cell_size

The dimensions of the unit cell (e.g. in Angstrom) of the unit cell.

kmos/proclist

Implements the kMC process list.

proclist/do_kmc_step

Performs exactly one kMC step. * first update clock * then configuration sampling step * last execute process

none

proclist/do_kmc_steps

Performs *n* kMC step. If one has to run many steps without evaluation *do_kmc_steps* might perform a little better. * first update clock * then configuration sampling step * last execute process

n : Number of steps to run

proclist/get_kmc_step

Determines next step without executing it.

none

proclist/get_occupation

Evaluate current lattice configuration and returns the normalized occupation as matrix. Different species run along the first axis and different sites run along the second.

none

proclist/init

Allocates the system and initializes all sites in the given layer.

- `input_system_size` number of unit cell per axis.
- `system_name` identifier for reload file.
- `layer` initial layer.
- `no_banner` [optional] if True no copyright is issued.

proclist/initialize_state

Initialize all sites and book-keeping array for the given layer.

- `layer` integer representing layer

proclist/run_proc_nr

Runs process `proc` on site `nr_site`.

- `proc` integer representing the process number
- `nr_site` integer representing the site

libkmc/kind_values

This module offers `kind_values` for commonly used intrinsic types in a platform independent way.

Trouble Shooting

I found a bug or have a feature request. How can I get in touch ? Please post issues [here](#) or via email `mjhoffmann .at. gmail .dot. com` or via twitter `@maxjhoffmann`

My rate constant expression doesn't work. How can I debug it? When initializing the model, the backend uses `kmos.evaluate_rate_expression`. So you can try

```
from kmos import evaluate_rate_expression
evaluate_rate_expression('<your-string-here>', parameters={})
```

where `parameters` is a dictionary defining the variable that are defined in the context of the expression evaluation, like so

```
parameters = {'T': {'value': 500},
              'p_NClgas': {'value': 1},
              }
```

Test only parts of your expression to localize the error. Typical mistakes are syntax errors (e.g. unclosed parentheses) and forgotten conversion factors (e.g. eV) which can easily lead to overflow if written in the exponent.

How can I print the chemical potential value, that kmos is using internally? You can then print the explicit value for specific conditions in `kmos shell`, for example like so

```
from kmos import evaluate_rate_expression
print(
    evaluate_rate_expression('mu_COgas',
        {'T':{'value':600},
         'p_COgas': {'value':1}
        }
    )))
```

where 'CO' should be replaced by whatever gas species you are inspecting. And the resulting number is given in eV. `kmos` linearly interpolates the gas phase chemical potential from the NIST JANAF thermochemical tables if you have downloaded them manually. If you don't have them installed, an error message should get raised which explains how to do so.

When I use `kmos shell` the model doesn't have the species and sites I have defined. Note that Fortran is case-insensitive. Therefore `f2py` turns all variable and functions names into lower case by convention. Try to lower-case your species or site name.

When I run kmos the GUI way and close it, it seems to hang and I need to use the window manager to kill it.

This is a bug waiting to be fixed. To avoid it close the window showing the atoms object by clicking on its close button or Alt-F4 or whichever shortcut your WM uses.

Running a model it sometimes prints *Warning: numerical precision too low, to resolve time-steps* This means that the kMC step of the current process was so small compared to the current kMC time that for the processor $t + \Delta t = t$. This should under normal circumstances only occur if you changed external conditions during a kMC run.

Otherwise it could mean that your rate constants vary over 12 or more orders of magnitude. If this is the case one needs to wonder whether non-coarse grained kMC is actually the right approach for the system. On the hand because the selection of the next process will no longer be reliable and second because reasonable sampling of all involved process may no longer happen.

When running a model without GUI evaluation steps seem very slow. If you have a *kmos.run.KMC_Model* instance and call *model.get_atoms()* the generation of the real-space geometry takes the longest time. If you only have to evaluate coverages or turn-over frequencies you are better off using *model.get_atoms(geometry=False)*, which returns an object with all numbers but without the actual geometry.

What units is kmos using ? By default length are measured in angstrom, energies in eV, pressure in bar, constants are taken from CODATA 2010. Note that the rate expressions though contain explicit conversion factors like *bar*, *eV* etc. If in doubt check the resulting rate constants by hand.

How can I change the occupation of a model at runtime? This is explained in detail at *manipulate_model_runtime* though the import bit is that you call

```
model._adjust_database()
```

after changing the occupation and before doing the next kMC step.

How can I quickly obtain *k_tot* ?

That is :: `model.base.get_accum_rate(model.proclist.nr_of_proc)`

How can I check the system size ?

You can check :: `model.lattice.system_size`

to get the number of unit cell in the x, y, and z direction. The number of sites per unit cell is stored in

```
model.lattice.spuck
```

a.k.a Sites Per Unit Cell Konstant :-). Or you check

```
model.base.get_volume()
```

to get the total number of sites, i.e. :: `model.base.get_volume() == model.lattice.system_size.prod()*model.lattice.spuck`
`=> True`

More to follow.

Todo

Explain *post-mortem* procedure

Frequently Asked Questions

What other kMC codes are there? Kinetic Monte Carlo codes that I am currently aware of, that are in some form released on the intertubes are with no claim of completeness :

- [akmc](#) (G. Henkelman)
- [Carlos](#) (J. Lukkien)
- [chimp](#) (D. Dooling)
- [KMCLib](#) (M. Leetma)
- [Graph Theoretical KMC Code](#) (D. Vlachos)
- [Monty](#) (SXM Boerrigter)
- [MoCKa](#) (L. Kunz)
- [NASCAM](#) (S. Lucas)
- [Spparks](#) (S. Plimpton)
- [Zacros](#) (M. Stamatakis)

Though The Google might find you some more. Please drop me a line if you find any information inaccurate.

What does kmos stand for anyways? Good question, initially kmos was supposed to stand for *kinetic modeling on steroids* because it feels really fast to model with kmos. But that confused people too much since we are not modelling reactions on steroids but on surfaces :-). Some other popular variants are

- kMC Modeling Of Surfaces
- kMC modeling offering source
- kMC models on screen

I am open for suggestions.

This document was generated Nov 29, 2017.

k

`kmos.cli`, 47
`kmos.gui`, 41
`kmos.io`, 40
`kmos.run`, 41
`kmos.types`, 36
`kmos.utils`, 48
`kmos.view`, 47

Symbols

__call__() (kmos.run.Model_Parameters method), 47
 __call__() (kmos.run.Model_Rate_Constants method), 47
 _adjust_database() (kmos.run.KMC_Model method), 42
 _get_configuration() (kmos.run.KMC_Model method), 42
 _put() (kmos.run.KMC_Model method), 42
 _set_configuration() (kmos.run.KMC_Model method), 43

A

add_layer() (kmos.types.Project method), 37
 add_parameter() (kmos.types.Project method), 37
 add_process() (kmos.types.Project method), 37
 add_site() (kmos.types.Project method), 37
 add_species() (kmos.types.Project method), 37

B

build() (in module kmos.utils), 48
 by_name() (kmos.run.Model_Rate_Constants method), 47

C

ConditionAction (class in kmos.types), 40
 Coord (class in kmos.types), 40

D

deallocate() (kmos.run.KMC_Model method), 43
 do_steps() (kmos.run.KMC_Model method), 43
 double() (kmos.run.KMC_Model method), 43
 dump_config() (kmos.run.KMC_Model method), 43

E

Editor (class in kmos.gui), 41
 evaluate_kind_values() (in module kmos.utils), 48
 exit() (kmos.view.KMC_Viewer method), 47
 export_movie() (kmos.run.KMC_Model method), 43
 export_source() (in module kmos.io), 40
 export_xml() (in module kmos.io), 40

G

generate_coord() (kmos.types.LayerList method), 39

generate_coord_set() (kmos.types.LayerList method), 39

get_ase_constructor() (in module kmos.utils), 48
 get_atoms() (kmos.run.KMC_Model method), 44
 get_backend() (kmos.run.KMC_Model method), 44
 get_occupation_header() (kmos.run.KMC_Model method), 44
 get_param_header() (kmos.run.KMC_Model method), 44

get_parameters() (kmos.types.Project method), 38
 get_processes() (kmos.types.Project method), 38
 get_speciess() (kmos.types.Project method), 38
 get_std_sampled_data() (kmos.run.KMC_Model method), 45
 get_tof_header() (kmos.run.KMC_Model method), 45
 GTKProject (class in kmos.gui), 41

H

halve() (kmos.run.KMC_Model method), 45

I

import_xml_file() (kmos.types.Project method), 38
 inverse() (kmos.run.Model_Rate_Constants method), 47

K

KMC_Model (class in kmos.run), 42
 KMC_Viewer (class in kmos.view), 47
 kmos (module), 3
 kmos.cli (module), 47
 kmos.gui (module), 41
 kmos.io (module), 40
 kmos.run (module), 41
 kmos.types (module), 36
 kmos.utils (module), 48
 kmos.view (module), 47

L

Layer (class in kmos.types), 39
 LayerList (class in kmos.types), 38
 LinearParameter (class in kmos.run), 42
 load_config() (kmos.run.KMC_Model method), 45
 LogParameter (class in kmos.run), 42

M

main() (in module kmos.cli), 48
Meta (class in kmos.types), 38
Model_Parameters (class in kmos.run), 47
Model_Rate_Constants (class in kmos.run), 46
ModelParameter (class in kmos.run), 42
ModelRunner (class in kmos.run), 41

N

nr2site() (kmos.run.KMC_Model method), 45

P

Parameter (class in kmos.types), 38
parameter_callback() (kmos.view.KMC_Viewer method), 47
parse_and_add_process() (kmos.types.Project method), 38
parse_process() (kmos.types.Project method), 38
pos (kmos.types.Coord attribute), 40
post_mortem() (kmos.run.KMC_Model method), 45
PressureParameter (class in kmos.run), 42
print_accum_rate_summation() (kmos.run.KMC_Model method), 45
print_adjustable_parameters() (kmos.run.KMC_Model method), 46
print_coverages() (kmos.run.KMC_Model method), 46
Process (class in kmos.types), 39
ProcListWriter (class in kmos.io), 40
procstat_normalized() (kmos.run.KMC_Model method), 46
procstat_pprint() (kmos.run.KMC_Model method), 46
Project (class in kmos.types), 36
put() (kmos.run.KMC_Model method), 46

R

run() (kmos.run.KMC_Model method), 46
run() (kmos.run.ModelRunner method), 41

S

show() (kmos.run.KMC_Model method), 46
Site (class in kmos.types), 39
Species (class in kmos.types), 39
split_sequence() (in module kmos.utils), 48
start() (kmos.run.KMC_Model method), 46

T

TemperatureParameter (class in kmos.run), 42

V

validate_model() (kmos.types.Project method), 38
view() (kmos.run.KMC_Model method), 46

W

write_proclist() (kmos.io.ProcListWriter method), 40
write_py() (in module kmos.utils), 48
write_settings() (kmos.io.ProcListWriter method), 40

X

xml() (kmos.run.KMC_Model method), 46