

---

# **LIME Documentation**

***Release***

**Christian Brinch**

August 21, 2015



|          |                                  |          |
|----------|----------------------------------|----------|
| <b>1</b> | <b>LIME user manual</b>          | <b>3</b> |
| 1.1      | Introduction . . . . .           | 3        |
| 1.2      | Command line options . . . . .   | 5        |
| 1.3      | Setting up models . . . . .      | 6        |
| 1.4      | Model functions . . . . .        | 10       |
| 1.5      | Output from LIME . . . . .       | 17       |
| 1.6      | Post-processing . . . . .        | 18       |
| 1.7      | Ideas for LIME 2.0 . . . . .     | 19       |
| 1.8      | Appendix: Bibliography . . . . . | 19       |



Contents:



---

## LIME user manual

---

### 1.1 Introduction

#### 1.1.1 Disclaimer

We, the authors and maintainers of LIME, do not guarantee that results given by LIME are correct, nor can we be held responsible for erroneous results. We do not claim that LIME is perfect or free of bugs and therefore the user should always take utmost care when drawing scientific conclusions based on results obtained with LIME. It is very important that the user performs tests and sanity checks whenever working with the LIME code to make sure that the results are reasonable and reliable. In particular, care needs to be taken when extending the runtime parameters into regimes for which the code was not designed.

#### 1.1.2 The LIME code

LIME (Line Modeling Engine) is an excitation and radiation transfer code that can be used to predict line and continuum radiation from an astronomical source model. The code uses unstructured 3D Delaunay grids for photon transport and accelerated Lambda Iteration for population calculations.

LIME was developed for the purpose of predicting the emission signature of low-mass young stellar objects, including molecular envelopes and protoplanetary disks. In principle the method should work for similar environments such as (giant) molecular clouds, atmospheres around evolved stars, high mass stars, molecular outflows, etc. As opposed to most other line radiation transfer codes which are constrained by cylindrical or spherical symmetry, LIME, being a 3D code, does not impose any such geometrical constraints. The main limitation therefore to what can be done with LIME is the availability of input models.

LIME is distributed under a Gnu General Public License.

Any publication that contains results obtained with the LIME code should cite the publication Brinch & Hogerheijde, A&A, 523, A25, 2010.

#### 1.1.3 Development history

The initial LIME code was written by Christian Brinch between 2006 and 2010, with version 1.0 appearing in early 2010. LIME derives from the radiation transfer code RATRAN developed by Michiel R. Hogerheijde and Floris van der Tak (Hogerheijde & van der Tak, 2000), although after several rewrites, the shared codebase is very small. The photon transport method is a direct implementation of the SimpleX algorithm (Ritzerveld & Icke, 2006).

Subsequent to the creation of the package by Christian Brinch, contributors to LIME have included:

- Tuomas Lunttila

- Sébastien Maret
- Marco Padovani
- Anika Schmiedeke
- Ian Stewart
- Mathieu Westphal

### 1.1.4 Obtaining LIME

The LIME code can be obtained from gitHub at <https://github.com/lime-rt/lime>. The available files include the source code, this documentation, and an example model. The documentation can be read on line at <https://readthedocs.org/projects/lime/>.

### 1.1.5 Requirements

LIME runs on any platform with an ANSI C compiler. Most modern operating systems are equipped with the GNU gcc compiler, but if it is not already present, it can be obtained from the GNU website (<http://www.gnu.org>). Furthermore, LIME needs a number of libraries to be present, including ncurses, GNU scientific Library (GSL), cfitsio, and qhull. Please refer to the README file within the LimePackage for details on how to obtain and install these libraries on various systems. Although it is not strictly needed for LIME to run, it is useful to have some kind of software that can process FITS files (IDL, CASA, MIRIAD, etc.) in order to be able to extract science results from the model images.

There are no specific hardware requirements for LIME to run. A fast computer is recommended (>2 GHz) with a reasonable amount of memory (>1 GB), but less will do as well. LIME can be run in multi-threaded (parallel) mode, if several CPUs are available. It is also possible to run several instances of LIME simultaneously on a multi-processor machine with enough memory.

### 1.1.6 Setting up LIME

LIME is compiled at run time, so there is no need to make any kind of pre-installation of the code. The only requirement for the code to run is that the path to *lime* script is in the PATH environment variable.

---

**Note:** Starting with LIME 1.5, sourcing the *sourceme.bash* or *sourceme.bash* (depending on your SHELL type) is not needed anymore.

---

### 1.1.7 Running LIME

Once the PATH variable is set, LIME can be run from the command line

```
bash$ lime model.c
```

where *model.c* is the file containing the model (this file can have any name). This will cause the code to be compiled and the terminal window should change and display the progress of the calculations. After completion, the user is prompted to press a key which will bring the terminal window back. It is possible to run LIME in silent mode, that is, without any output in the terminal window. This is done by setting the silent flag to 1 (the default setting is 0) in the file LimePackage/src/lime.h. LIME also accepts several *command line options*.



### 1.1.8 The inner workings of LIME

The first thing that happens after compilation is that LIME allocates memory for the grid and the molecular data based on the parameter settings in the model file. All user defined settings are checked for sanity and in case there are inconsistencies, LIME will abort with an error message. It then goes on to generate the grid (unless a predefined grid is provided) by picking and evaluating random points until enough points have been chosen to form the grid. The grid is then iteratively smoothed to avoid oddly-shaped Delaunay triangles. Because the grid needs to be re-triangulated at each iteration, the smoothing process may take a while. After smoothing, a number of grid properties (e.g. velocity splines) are pre-calculated for later use, and the grid is written to file.

When the grid is ready, LIME decides whether to calculate populations or not, depending on the user's choice of output images and LTE options (see chapter 2). If one or more non-LTE line images are asked for, LIME will proceed to calculate the level populations. This too is an iterative process where the radiation field and the populations are recalculated repeatedly. The radiation field is obtained by propagating photons through the grid, a fix number for each grid point, and using the resulting radiation field, the code enters a minor iteration loop where a set of linear equations, determining the statistical equilibrium, are iterated upon in order to converge upon a set of populations. This is done for each grid point in turn. Once all the grid points has gotten new populations, the process is repeated.

When the solution has converged, the code will ray-trace the model to obtain an image. Ray-tracing is done for each user- defined image in turn. At the end of the ray-tracing, FITS files will be written to the disk at the code will clean up the memory and terminate.

## 1.2 Command line options

---

**Note:** Starting with LIME 1.5, command line options can be used to change LIME default behavior without editing the source code.

---

LIME accepts several command line options:

- v** Display version information
- h** Display help message
- f** Use fast exponential computation. When this option is set, LIME uses a lookup-table replacement for the exponential function, which however (due to cunning use of the properties of the function) returns a value with full floating-point precision, indeed with better precision than that for much of the range. Use of this option reduces the run time by 25%.
- n** Turn off *ncurses* messages. This is useful when running LIME in a non-interactive way.
- p** *nthreads* Run in parallel mode with *nthreads*. The default a single thread, i.e. serial execution.

---

**Note:** The number of threads may also be set with the *par->nThreads* parameter.

---

## 1.3 Setting up models

### 1.3.1 The model file

All basic setup of a model is done in a single file which we refer to as `model.c` (although it may be given any name). `Model.c` is, as the name suggests, C source code which is compiled together with LIME at runtime, and therefore it must conform to the ansi C standard. Setting up a model however, requires only little knowledge of the C programming language. For an in- depth introduction to C the user is referred to “The C Programming Language 2nd ed.” by Kernighan and Ritchie, and otherwise, numerous tutorials and introductions can be found on the Internet. The file `lime_cs.pdf`, contained in the `LimePackage` directory, is a quick reference for setting up models for LIME. Please note that all physical numbers in `model.c` should be given in SI-units.

In most common cases, everything about a model should be described within `model.c`. However, `model.c` can be set up as a wrapper that will call other files containing parts of the model or even call external codes or subroutines. Examples of such usage are given below in the section Advanced setup.

`model.c` should always begin with the following inclusion

```
#include "lime.h"
```

to make `model.c` aware of the global LIME variable structures. Other header files may be included in `model.c` if needed, with the possible need of modifying the Makefile accordingly. Following the preprocessor commands, the main model function should appear

```
void input(inputPars *, image *);
```

This function should contain the parameter and image settings.

### 1.3.2 Parameters

A structure named “`par`” is defined in `lime.h`. This structure contains all basic settings such as number of grid points, model radius, input and output filenames, etc. Some of these parameters always need to be set by the user, while others are optional with preset default values. There is an exception to this rule, namely when restarting LIME with previously calculated populations. In that case, none of the non-optional parameters are required.

```
(double) par->radius (required)
```

This value sets the outer radius of the computational domain. It should be set large enough to cover the entire spatial extend of the model. In particular, if a cylindrical input model is used (e.g., the input file for the RATRAN code) one should not use the radius of the cylinder but rather the distance from the center to the corner of the (r,z)-plane.

```
(double) par->minScale (required)
```

`minScale` is the smallest scales sampled by the code. Structures smaller than `minScale` will not be sampled properly. If one uses spherical sampling (see below) this number can also be thought upon as the inner edge of the grid. This number should not be set smaller than needed, because an undesirable large number of grid point will end up near the center of the model.

```
(integer) par->pIntensity (required)
```

This number is the number of model grid points. The more grid points that are used, the longer the code will take to run. Too few points however, will cause the model to be under-sampled with the risk of getting wrong results. Useful numbers are between a few thousands up to about one hundred thousand.

```
(integer) par->sinkPoints (required)
```

The sinkPoints are grid points that are distributed randomly at par->radius forming the surface of the model. As a photon from within the model reaches a sink point it is said to escape and is not traced any longer. The number of sink points is a user defined quantity since the exact number may affect the resulting image as well as the running time of the code. One should choose a number that gives a surface density large enough not to cause artifacts in the image and low enough not to slow down the gridding too much. Since this is model dependent, a global best value cannot be given, but a useful range is between a few thousands and about ten thousand.

```
(integer) par->sampling (optional)
```

The sampling parameter takes value 0, 1 or 2. sampling=0 is used for uniform sampling in Log(radius) which is useful for models with a central condensation (i.e., envelopes, disks), whereas sampling=1 is uniform sampling in x, y, and z. The latter is useful for models with no central condensation (molecular clouds, galaxies, slab geometries).

The value sampling=2 was added because the routine for 0 was found not to generate grid points with exact spherical rotational symmetry. The 2 setting implements this now properly; sampling=0 has, however, been retained for purposes of backward compatibility. In practice there is little obvious difference between the outputs from 0 versus 2.

The default value is now sampling=2.

```
(double) par->tcmb (optional)
```

This parameter is the temperature of the cosmic microwave background. This parameter defaults to 2.725K which is the value at zero redshift (i.e., the solar neighborhood). One should make sure to set this parameter properly when calculating models at a redshift larger than zero: TCMB = 2.725(1+z) K. It should be noted that even though LIME can now take the change in CMB temperature with increasing z into account, it does not (yet) take cosmological effects into account when ray-tracing (such as stretching of the frequencies when using Jansky as unit). This is currently under development.

```
(string) par->moldatfile[i] (optional)
```

Path to the i'th molecular data file. Molecular data files contains the energy states, Einstein coefficients, and collisional rates which are needed by LIME to solve the excitation. These files need to conform to the standard of the LAMDA database (<http://www.strw.leidenuniv.nl/~moldata>). Data files can be downloaded from the LAMDA database but from LIME version 1.23, LIME can also download these files automatically. If a data file name is give that cannot be found locally, LIME will try and download the file instead. When downloading data files, the filename can be give both with and without the surname .dat (i.e., “co” or “co.dat”). moldatfile is an array so multiple data files can be used for a single LIME run. There is no default value.

```
(string) par->dust (optional)
```

Path to a dust opacity table. This table should be a two column ascii file with wavelength in the first column and opacity in the second column. Currently LIME uses the same tables as RATRAN from Ossenkopf and Henning (1994), and so the wavelength should be given in microns (1e-6 meters) and the opacity in cm<sup>2</sup>/g. This is the only place in LIME where SI units are not used. The moldatfile and dust parameters are optional in the sense that at least one of them (or both) should be set. There is no default value. A future version of LIME will allow spatial variance of the dust opacities, so that opacities can be given as function of x, y, and z.

```
(string) par->outputfile (optional)
```

This is the file name of the output file that contains the level populations. If this parameter is not set, LIME will not output the populations. There is no default value.

```
(string) par->binoutputfile (optional)
```

This is the file name of the output file that contains the grid, populations, and molecular data in binary format. This file is used to restart LIME with previously calculated populations. Once the populations have been calculated and the binoutputfile has been written, LIME can re-ray-trace for a different set of image parameters without re-calculating the populations. There is no default value.

```
(string) par->restart (optional)
```

This is the file name of a binoutputfile that will be used to restart LIME. If this parameter is set, all other parameter statements (except `par->antialias`; see below) will be ignored and can safely be left out of the model file. There is no default value.

```
(string) par->gridfile (optional)
```

This is the file name of the output file that contains the grid. If this parameter is not set, LIME will not output the grid. The grid file is written out as a VTK file. This is a formatted ascii file that can be read with a number of 3D visualizing tools (Visualization Tool Kit, Paraview, and others). There is no default value.

```
(string) par->pregrid (optional)
```

A file containing an ascii table with predefined grid point positions. If this option is used, LIME will not generate its own grid, but rather use the grid defined in this file. The file needs to contain all physical properties of the grid points, i.e., density, temperature, abundance, velocity etc. There is no default value.

```
(integer) par->lte_only (optional)
```

If set, LIME performs an LTE calculation. Useful for quick checks. The default `lte_only=0`, i.e., full non-LTE calculation.

```
(integer) par->blend (optional)
```

If set, LIME takes line blending into account, however, only if there are any overlapping lines among the transitions found in the moldatfile(s). LIME will print a message on screen if it finds overlapping lines. Switching line blending on will slow the code down considerably, in particular if there is more than one molecular data file. The default is `blend=0` (no line blending).

```
(integer) par->antialias (optional)
```

If set, LIME will anti-alias the output image. `anti-alias` can take the value of any positive integer, with the value 1 (default) being no anti-aliasing. Greater values correspond to stronger anti-aliasing. LIME uses stochastic super-sampling anti-aliasing. This is very effective in minimizing artifacts in the image, but it also slows down the ray-tracer by a factor equal to the value of `antialias`. This parameter is the only one that will not be ignored in case `par->restart` is set.

```
(integer) par->polarization (optional)
```

If set, LIME will calculate the polarized continuum emission. This parameter only has an effect if LIME is set up to do a continuum calculation only. The resulting image cube will have three channels containing the Stokes I, Q, and U. In order for the polarization to work, a magnetic field needs to be defined (see below). When polarization is switched on, LIME is identical to the DustPol code (Padovani et al., 2012).

```
(integer) par->nThreads (optional)
```

If set, LIME will perform the most time-consuming sections of its calculations in parallel, using the specified number of threads. Serial operation is the default.

### 1.3.3 Images

LIME can output a number of images per run. The information about each image is contained in a structure array called `img`. The images defined in the image array can be either line or continuum images or both. All definitions of an image may be changed between images (i.e., distance, resolution, inclination, etc.) so that a number of images with varying source distance or image resolution can be made in one go. In the following, `i` should be replaced by the image number (0, 1, 2, ...)

```
(integer) img[i]->pxls (required)
```

This is the number of pixels per spatial dimensions of the FITS file. The total amount of pixels in the image is thus the square of this number.

```
(double) img[i]->imgres (required)
```

The image resolution or size of each pixel. This number is given in arc seconds. The image field of view is therefore  $\text{pxls} \times \text{imgres}$ .

```
(double) img[i]->theta (required)
```

Theta is the viewing angle (the angle between the model z axis and the ray-tracers line of sight). This number is given in radians, not degrees, so that a face-on view (of models where this term is applicable) is 0 and edge-on view is  $\pi/2$ .

```
(double) img[i]->distance (required)
```

The source distance in meters. LIME knows the conversion between parsec, AU, and meters, so the distance can be given as  $100 \times \text{pc}$ , for example. If the source is located at a cosmological distance, this parameter is the luminosity distance.

```
(integer) img[i]->unit (required)
```

The unit of the image. This variable can take values between 0 and 4. 0 for Kelvin, 1 for Jansky per pixel, 2 for SI units, and 3 for Solar luminosity per pixel. The value 4 is a special option that will create an optical depth image cube (dimensionless).

```
(string) img[i]->filename (required)
```

This variable is the name of the FITS file. It has no default value.

```
(double) img[i]->phi (optional)
```

Phi is an optional geometric parameter. Like theta, it should be given in radians between 0 and  $2\pi$ . Phi is the rotation angle of the model (x,y)-plane around the z-axis. If the model is view face-on (so that the line of sight coincides with the z-axis), phi corresponds to the position angle on the sky. The default value is 0.

```
(double) img[i]->source_vel (optional)
```

The source velocity is an optional parameter that gives the spectra a velocity offset. This parameter is useful when comparing the model to an astronomical source with a known relative velocity.

```
(integer) img[i]->nchan (semi optional)
```

nchan is the number of velocity channels in a spectral image cube. See the note below for additional information.

```
(double) img[i]->velres (semi optional)
```

The velocity resolution of the spectral dimension of the FITS file (the width of a velocity channel). This number is given in m/s. See the note below for additional information.

```
(integer) img[i]->trans (semi optional)
```

The transition number when ray-tracing line images. This number refers to the transition number in the molecular data files. Contrary to the numbers in the data files, trans is zero-index, meaning that the first transition is labeled 0, the second transition 1, and so on. For linear rotor molecules without fine structure transition in their data files (CO, CS, HCN, etc.) the trans parameter is identified by the lower level of the transition. For example, for CO J=1-0 the trans label would be zero and for CO J=6-5 the trans label would be 5. For molecules with a complex level configuration (e.g., H<sub>2</sub>O), the user needs to refer to the datafile to find the correct label for a given transition. See the note below for additional information.

```
(double) img[i]->freq (semi optional)
```

Center frequency of the spectral axis in Hz. This parameter can be used for both line and continuum images. See the note below for additional information.

```
(double) img[i]->bandwidth (semi optional)
```

With of the spectral axis in Hz. See the note below for additional information.

1.3.4 Note on semi-optional image parameters


The above parameters listed as semi optional determine what kind of image is produced (line or continuum). Only certain combinations are permitted, however some of them have to be set. LIME decides to make a continuum image if the parameter nchan is left unset. This will result in a single channel continuum image. In nchan is unset, the only other parameter which is allowed to be set is freq, which, however, has to be set. In addition, the parameter par->dust needs to be set as well, otherwise, LIME will produce an error. In order to produce a line image cube, either the parameter nchan, velres, and trans or nchan, freq, and bandwidth should be set. Any other combination will produce an error. For line images, at least one moldatfile should be provided and optionally a dust opacity table as well.

1.4 Model functions

The second part of the model.c file contains the actual model description. This is provided as seven sub-routines: density, molecular abundance, temperature, systematic velocities, random velocities, magnetic field, and gas-to-dust ratio. The user only needs to provide the functions that are relevant to a particular model, e.g., for continuum images only, the user need not include the abundance function or any of the velocity functions. The magnetic field function needs only be included for continuum polarization images.


1.4.1 Density

The density subroutine contains a user-defined description of the 3D density profile of the collision partner(s).



```
void
density(double x, double y, double z, double *density){
    density[0] = f(x,y,z);
    density[1] = f(x,y,z);
    ...
    density[n] = f(x,y,z);
}
```

LIME can deal with an unlimited number



of collision  
partners (n).

However,

LIME will  
produce an  
error if more  
density pro-  
files are given  
in the density  
subroutine

than there are  
collision part-  
ners listed in  
the molecular  
data file. In  
most cases, a  
single density  
profile will  
suffice. The  
density is  
a number  
density, that  
is, the number  
of collision  
partners per  
unit volume  
(in cubic me-  
ters, not cubic  
centimeters).

Please note  
that the cur-  
rent version  
of LIME  
always takes

the abundance relative to the first collision partner. This is potentially a problem if the first collision partner is not the total H2 density and the user will have to correct for this in the abundances (see below).

### 1.4.2 Molecular abundance

The abundance subroutine contains descriptions of the molecular abundance profiles of the input model. The number of abundance profiles should match exactly the number of molecular data files defined in par->moldatfile.

```
void
abundance(double x, double y, double z, double *abundance){
    abundance[0] = f(x,y,z);
    abundance[1] = f(x,y,z);
    ...
    abundance[n] = f(x,y,z);
}
```

The abundance is the fractional abundance with respect to the primary collision partner (density[0]) so that the molecular density of the first species is given by abundance[0] x density[0]. The abundances are dimensionless.

### 1.4.3 Temperature

The temperature subroutine contains the descriptions of the gas, and optionally, the dust temperature.

```
void
temperature(double x, double y, double z, double *temperature){
    temperature[0] = f(x,y,z);
    temperature[1] = f(x,y,z);
}
```

The entry 0 in the temperature array is the kinetic gas temperature. This value is required for LIME to run. The entry 1 is the optional dust temperature. Both are in Kelvin. If there is no explicit dust temperature given in the temperature subroutine, LIME will assume that the dust temperature equals the gas temperature.

### 1.4.4 Random velocities

This subroutine contains a scalar field which describes the velocity dispersion of the random motions of the gas. This number is the Doppler b-parameter which is the 1/e half-width of the line profile. The doppler subroutines differs from the other model subroutines in the sense that the return type is a scalar, and not an array. The doppler b-parameter should be given in m/s.

```
void
doppler(double x, double y, double z, double *doppler){
    *doppler = f(x,y,z);
}
```

Because the return type is a scalar, the asterisk in front of the variable name needs to be present. `doppler[0]` does not work.

### 1.4.5 Velocity field

The velocity field subroutine contains the systematic velocity field of the gas. The return type of this subroutine is a three component vector, with components for the x, y, and z axis.

```
void
velocity(double x, double y, double z, double *velocity){
    velocity[0] = f(x,y,z);
    velocity[1] = f(x,y,z);
    velocity[2] = f(x,y,z);
}
```

In the current version of LIME, splines are calculated based on the information in the velocity field function and therefore this function is only called once. Hence, it need not be as optimized as in previous versions of LIME. It is now feasible to use look-up tables for the velocity field as well. LIME will use a forth-order polynomial to approximate the line-of-sight velocity field component. In case the par-pregrid option is set, LIME will use linear interpolation between grid points.

### 1.4.6 Magnetic field

The magnetic field subroutine contains a description of the magnetic field. The return type of this subroutine is a three component vector, with components for the x, y, and z axis. The magnetic field only has an effect for continuum polarization calculations, that is, if `par->polarization` is set.



```
void
magfield(double x, double y, double z, double *B){
    B[0] = f(x,y,z);
    B[1] = f(x,y,z);
    B[2] = f(x,y,z);
}
```

### 1.4.7 Gas-to-dust ratio

Finally the gas-to-dust ratio is an optional function which the user can choose to include in the model.c file. If this function is left out, LIME defaults to a dust-to-gas ratio of 100 everywhere. This number only has an effect if the continuum is included in the calculations.

```
void
gasIdust(double x, double y, double z, double *gtd){
    *gtd = f(x,y,z);
}
```

### 1.4.8 Other settings

A number of additional settings can be found in the file LimePackage/src/lime.h. These settings should in general not be changed by the user, unless there is an explicit need to do so. A few of them however, could be useful to some users. The keyword silent which is by default set to zero can be set to one. This will cause LIME to run completely silent with no output to the screen at all. This can be useful for running LIME in batch mode in the background.

Another number that might be of interest is NITERATIONS, by default set to 16. This is the number of major iteration loops LIME will go through before ray-tracing. If the user is happy with the signal-to-noise achieved after fewer iterations, this number can be lowered accordingly. Obviously, a higher number will cause LIME to go through more iterations, which may be needed for models with slow convergence.

### 1.4.9 Advanced setup

Standard use of LIME requires the user to formulate the model in the model functions described above as either an analytical expression or a look-up table of values. As input models increase in complexity however, analytical descriptions may no longer be possible and with model dimensionality higher than one, look-up tables become difficult to manage within the model.c functions. In the following we will explain how to use complex numerical models and pre-gridded models as input for LIME.

### 1.4.10 Using numerical input models

Numerical input model can roughly be divided into two groups: those where the model properties are described as cell averages and those where the model properties are described at cell nodes (see figure). In either case, LIME will send a coordinate to the model functions and expect a value back. It is the up to the user to write an interface that will look up the appropriate return value.

In the simplest case where the numerical model is described as cell averaged values, the user needs to loop through the cells and find the cell in which the LIME point falls and return the value of that particular cell. In the case where the model is described on cell nodes, the user must loop through the nodes to find the node which lies closest to the LIME point and return that node value. This approach obviously limits the LIME model smoothness to the input model resolution since all LIME points which falls with an input model grid cell (or within a certain distance from a grid node) gets the same value. One way to get around this is to interpolate in the input grid, which in principle can be done in either case, although this may be highly non-trivial if the model is described on unstructured grid nodes or

is of a dimensionality greater than one. An example of linear interpolation in a one dimensional table can be found in the example model.c file below.

In the special case where the input model is described on unstructured grid nodes (e.g., Smoothed Particle Hydrodynamics simulations) the input grid can be used directly in LIME. This requires the user to set the `par->pregrid` parameter.

If the user is more comfortable writing code in the FORTRAN language, it is possible to use the model subroutines as wrappers to call FORTRAN functions which then carries out any necessary calculations and return the values to model.c. This can be done the following way:

```
void
density(double x, double y, double z, double *density){
    fortransub_(&x, &y, &z, &density[0]);
}
```

```
SUBROUTINE fortransub(x,y,z,temp)
DOUBLE x,y,z,temp
temp=f(x,y,z)
RETURN
END
```

In order for this to work the file containing the FORTRAN function needs to be compiled by a FORTRAN compiler and the resulting object file needs to be linked with LIME. This only works if the linking is also done with the FORTRAN compiler, so some modification to the Makefile is needed. Notice that the underscore after the name of the FORTRAN subroutine in the C function call has to be present. Please note that the example above is untested and may need modification in order to work.

If the input model file consist of a table of values, for instance as when using the output of another code as input for LIME, the idea is look up the input grid point (or cell) which is closest to the LIME grid point in question (or for cell based tables, the cell in which the LIME point falls). The way to deal with this is to make a column formatted ascii file with the input model:

```
x_1 y_1 z_1  density_1  temperature_1  any_other_stuff_1  ...
x_2 y_2 z_2  density_2  temperature_2  any_other_stuff_2  ...
...
x_n y_n z_n  density_n  temperature_n  any_other_stuff_n  ...
```

The idea is to find the  $i$ 'th entry in that list where  $\text{minimum}((x_i-x)^2+(y_i-y)^2+(z_i-z)^2)$  is true, or in other words which entry in the list lies closest to a given LIME point  $(x,y,z)$ . One way to solve this would be as follows (example in pseudocode)

```
density(x,y,z){
    mindist=very_large_number
    open("model_input_file",read)
    while not end-of-file{
        read_one_line(x_i,y_i,z_i,density_i,...)
        calculate distance from (x,y,z) to (x_i,y_i,z_i) == dist
        if dist < mindist then {
            mindist = dist
            bestdensity = density_i
        }
    }
    close(file)
    return bestdensity
}
```

and similarly for the temperature and other properties. This is potentially a slow process, opening and closing a file for every grid point. To speed up the process, it is useful to make the model columns available as arrays in model.c.

This can be done by formatting the columns using proper C-syntax as arrays and putting them in a “header” file that can be included in model.c

```
int size=numer_of_lines_in_model_file;
double model_x[size]={x1,x2,...,xn};
double model_y[size]={y1,y2,...,yn};
double model_z[size]={z1,z2,...,zn};
double model_density[size]={density1,density2,...,densityn};
...
```

The pseudocode example from above now reads:

```
density(x,y,z){
  mindist=very_large_number
  for i from 0 to size by 1
    calculate distance from (x,y,z) to (model_x[i],model_y[i],model_z[i]) == dist
    if dist < mindist then {
      mindist = dist
      bestdensity = model_densiy[i]
    }
  }
  return bestdensity
}
```

### 1.4.11 RATRAN models as input for LIME

It is possible to use existing 1D or 2D model files from the RATRAN code in LIME. This is done with `ratranInput()` subroutine. The .mdl file has to comply with the RATRAN standard and the header (everything above the @ sign) of the file needs to be intact. The functions in model.c look like this

```
void
density(double x, double y, double z, double *density){
  density[0]=ratranInput("model.mdl", "nh", x,y,z)*1e6;
}
```

and

```
void
teperature(double x, double y, double z, double *temperature){
  temperature[0]=ratranInput("model.mdl", "te", x,y,z);
}
```

for the density and temperature respectively. Notice that the density is multiplied by 1e6 to convert the cgs units from RATRAN into LIMEs SI units. The calls to the subroutine for the doppler velocity, systemic velocity, dust temperature, and abundance are similar, using the appropriate keywords to identify the column in the RATRAN .mdl file. Since RATRAN uses molecular density and not abundance, the abundance function should read

```
void
abundance(double x, double y, double z, double *abundance){
  abundance[0]=ratranInput("model.mdl","nh",x,y,z)/ratranInput("model.mdl","nm", x,y,z);
}
```

Obviously it is possible to mix RATRAN input, that is, using different .mdl files for the different functions. All parameters in model.c still need to be set, ie., `par->radius`, even though this information is contained in the RATRAN header. If the RATRAN grid is not logarithmically spaced, it may be advantageous to set `par->sampling=1`.

### 1.4.12 Example model file

Here follows the model.c file that can be found in the example directory in the LimePackage. This model describes a simple spherical envelope of HCO<sup>+</sup> gas. The temperature is also one dimensional, but provided as a table of value. The additional code in the temperature subroutine interpolates the values of the table. A constant molecular abundance and Doppler b- parameter is used. The velocity field is described by a free-fall on radial trajectories toward a central mass of one Solar mass. This example will produce a single image of the HCO<sup>+</sup> J=4-3 line in the approximate distance of the Taurus star forming region, using Kelvins as the unit.

```
#include "lime.h"

void
input(inputPars *par, image *img){
    par->radius      = 2000*AU;
    par->minScale     = 0.5*AU;
    par->pIntensity   = 4000;
    par->sinkPoints    = 3000;
    par->dust          = "jena_thin_e6.tab";
    par->moldatfile[0] = "hco+@xpol.dat";
    par->outputfile    = "populations.pop";
    par->binoutputfile = "restart.pop";
    par->gridfile      = "grid.vtk";

    img[0].nchan      = 60;
    img[0].velres      = 500.;
    img[0].trans       = 3;
    img[0].pxls        = 100
    img[0].imgres       = 0.1;
    img[0].theta        = 0.0;
    img[0].distance     = 140*PC;
    img[0].source_vel  = 0;
    img[0].unit         = 0;
    img[0].filename     = "image0.fits";
}

void
density(double x, double y, double z, double *density){
    double r;
    r=sqrt(x*x+y*y+z*z);
    density[0] = 1.5e6*pow(r/(300*AU),-1.5)*1e6;
}

void
temperature(double x, double y, double z, double *temperature){
    int i,k,x0=0;
    double r;
    double temp[2][10] = {
        {2.0e13, 5.0e13, 8.0e13, 1.1e14, 1.4e14, 1.7e14, 2.0e14, 2.3e14, 2.6e14, 2.9e14},
        {44.777, 31.037, 25.718, 22.642, 20.560, 19.023, 17.826, 16.857, 16.050, 15.364}
    };
    r=sqrt(x*x+y*y+z*z);
    if(r > temp[0][0] && r<temp[0][9]){
        for(i=0;i<9;i++){
            if(r>temp[0][i] && r<temp[0][i+1]) x0=i;
        }
    }
    if(r<temp[0][0])
        temperature[0]=temp[1][0];
```

```

else if (r>temp[0][9])
    temperature[0]=temp[1][9];
else
    temperature[0]=temp[1][x0]+(r-temp[0][x0])*(temp[1][x0+1]-temp[1][x0])/(temp[0][x0+1]-temp[0][x0]);
}

void
abundance(double x, double y, double z, double *abundance){
    abundance[0] = 1.e-9;
}

void
doppler(double x, double y, double z, double *doppler){
    *doppler = 200.;
}

void
velocity(double x, double y, double z, double *vel){
    double R, phi,r,theta;
    R=sqrt(x*x+y*y+z*z);
    theta=atan2(sqrt(x*x+y*y),z);
    phi=atan2(y,x);
    r=-sqrt(2*6.67e-11*1.989e30/R);
    vel[0]=r*sin(theta)*cos(phi);
    vel[1]=r*sin(theta)*sin(phi);
    vel[2]=r*cos(theta);
}

```

## 1.5 Output from LIME

Besides the FITS images, which are the main output, LIME produces other output that can be used not only for diagnostics but also science results. This chapter describes the various output files and how to work with them.

### 1.5.1 The grid

Once the Delaunay grid has been created by LIME, a VTK file with the grid and grid properties are written (if the parameter `par->gridfile` is set, see chapter 2). The VTK (Visualization Tool Kit) format is a formatted ascii file that are used to handle geometrical objects, in our case an unstructured grid. VTK files can be read by several visualization software packages. In particular we advocate the use of paraview (<http://www.paraview.org>) which is an open source program available for several platforms.

The grid file contains the (x,y,z)-coordinate of each grid point, as well as a reference to the neighbors of each grid point. From this information the Delaunay triangulation can be reconstructed. The file also holds three scalar fields and a vector field for the H2 density, temperature, molecular density and the velocity field. Other properties could be written out as well, but that will require the user to edit the `write_VTK_unstructured_Points()` function in `grid.c`.

Inspecting the grid using paraview can be a useful way to make sure that the model indeed behaves as expected. It makes for impressive visualizations that can be included in presentations. However, paraview does a poor job when it comes to publication quality plots.

## 1.5.2 Populations

The level populations are written out in a separate file if LIME is set up to calculate the level populations, that is, if at least one molecular data file is defined in `model.c` (and if the parameter `par->outputfile` is set). Currently, LIME can only write out populations from the first molecule (`par->moldatfile[0]`). The populations output file contains the x, y, and z coordinates for each grid point as well as the H<sub>2</sub> density, temperature, and molecular density besides the level populations. Contrary to the grid file, it does not, however, contain information about the neighbors of the grid points and therefore, the Delaunay triangulation cannot be reconstructed from this file (unless the points are re-triangulated with `qhull` or a similar tool). The information in the population file allows the user to plot projections and slices of the model properties including the populations. This is the best way to directly compare the LIME model and the result of the excitation calculation with the results obtained by other codes. One particularly interesting property to plot is the excitation temperature

$$\frac{n_u}{n_l} = \frac{g_u}{g_l} \exp\left(-\frac{\Delta E}{k_B T_{ex}}\right)$$

which is obtained from the level populations. *u* and *l* refers to the upper and lower level and *g* are the statistical weights. Calculating the excitation temperature is the best way to check for masering in the model since the excitation temperature turns negative in the case of population inversion. If, and only if, the gas is in local thermodynamic equilibrium (LTE) the excitation temperature equals the kinetic temperature, so plotting the ratio of kinetic gas temperature to the excitation temperature gives a measure of the deviation from LTE.

## 1.5.3 Images

Image cubes are the main output from LIME. LIME produces model images in the FITS file format only.

## 1.6 Post-processing

In order to make direct comparisons between LIME models and observations, some kind of post-processing of the images will be needed in almost all cases. In this chapter we will give some hints and tricks to how this can be done using readily available software packages.

### 1.6.1 Convolution

In order to compare LIME results to single dish observations, the image cube needs to be convolved with a beam profile that corresponds to the instrument beam at the frequency in question. Before convolving an image it is important to make sure that the image is larger than the beam size and that the beam is resolved by the pixels (pixel size  $\ll$  beam size). The reason that the image needs to be bigger than the beam is to avoid artificial edge effects at the corners of the image. This is not very important if only the spectrum toward the center of the image is of interest, but if the image is being used as a model of a single dish map, edge effects become important. In general, it is recommended that the image is made large enough that the emission has dropped sufficiently close to zero at the edges of the image.

If the beam size is small, it may be an issue that the beam is not sufficiently resolved by pixels. This is important to make sure that structures that are picked up by the telescope beam is sufficiently sampled by the ray-tracer in LIME. In general it is a good idea to calculate the image in a considerably higher resolution than what is needed, because artifacts in the image that are due to the randomness of the grid are then smoothed out. In order to compare a convolved model spectrum to a single observed spectrum toward the source center, the spectrum at the center pixel should be used without additional averaging of pixels.

When comparing model images to interferometric observations, there is no need to convolve the image with a beam profile. In this case, model and data is compared in frequency space in which case the model image needs to be Fourier transformed or in image space in which case the model should be sampled with the (u,v)-spacing from the dataset and

inverted and cleaned using the same process as the observed data has gone through. When Fourier transforming the model image, one should be careful to avoid aliasing effects that are caused by the regularity of the pixel grid. Such effects are model dependent and difficult to prevent entirely. On the other hand, comparing the model to interferometric data in image space is dangerous as well, because of the non-uniqueness of the de-convolved image.

Both convolution and Fourier transforming can be done using the MIRIAD tasks `convolve` and `fft` after converting the FITS file into MIRIAD format using the MIRIAD task `fits`. Both convolution and Fourier transformation can be done in IDL or Python.

## 1.6.2 Plotting the model

The LIME data cubes can be visualized in numerous ways, both in one and two dimensions. One dimensional plots include the spectrum of a single pixel and the brightness profile along either spatial direction at a specific frequency or summed over a range of frequencies. The two dimensional (contour) plots are images when done in the plane spanned by the two spatial axis, and position-velocity (PV) diagrams when done in the frequency and any one of the spatial axis.

When plotting images, it is often useful to sum over a range of frequencies. This results in, what is known as, moment maps. These can be made to any order, but zero and first moments are most often used. The  $n$ th moment is defined as

$$\mu_n(x, y) = \int_{-\infty}^{\infty} (v - v_{\text{source}})^n I(x, y, z) dv$$

Sometimes the first moment (and also higher order moments) is normalized by the zero moment.

## 1.7 Ideas for LIME 2.0

In the following we list a number of new features which are being considered for the next major release of LIME. Users should feel free to contact the maintainers with suggestions, improvements, new functionalities or bugs needing to be fixed.

- Line polarization
- Visibility output
- Tau images
- User-defined, function based grid sample weights
- Basecol/Vamdc support
- etc...

## 1.8 Appendix: Bibliography

- Brinch & Hogerheijde, A&A, 523, A25, 2010; see also <http://www.nbi.dk/~brinch/lime.php>
- Hogerheijde & van der Tak, A&A, 362, 697, 2000
- Ritzerveld & Icke, PhysRevE, 74, 26704, 2006
- Ossenkopf & Henning, A&A, 291, 943, 1994
- Kernighan & Ritchie, “The C Programming Language 2nd ed.”, Prentice Hall, 1988, ISBN-13: 978-0131103627
- Padovani et al., A&A, 543, A16, 2012





## Symbols

- V  
command line option, [5](#)
- f  
command line option, [5](#)
- h  
command line option, [5](#)
- n  
command line option, [5](#)
- p nthreads  
command line option, [5](#)

## C

- command line option
  - V, [5](#)
  - f, [5](#)
  - h, [5](#)
  - n, [5](#)
  - p nthreads, [5](#)