
aiovault Documentation

Release 0.1.0

Terry Cain

Nov 16, 2017

Contents

1	aiovault	3
2	Installation	5
2.1	Stable release	5
2.2	From sources	5
3	Basic Usage	7
4	Contributing	9
4.1	Types of Contributions	9
4.2	Get Started!	10
4.3	Pull Request Guidelines	11
4.4	Tips	11
5	Credits	13
5.1	Development Lead	13
5.2	Contributors	13
6	History	15
6.1	1.1.1 (2017-11-16)	15
6.2	1.1.0 (2017-11-16)	15
6.3	1.0.0 (2017-07-29)	15
6.4	0.2.0 (2017-07-20)	15
6.5	0.1.3 (2017-07-17)	16
6.6	0.1.2 (2017-07-17)	16
6.7	0.1.1 (2017-07-17)	16
7	Indices and tables	17

Contents:

CHAPTER 1

aiovault

TODO

2.1 Stable release

To install aiovault, run this command in your terminal:

```
$ pip install aiovault
```

This is the preferred method to install aiovault, as it will always install the most recent stable release.

If you don't have `pip` installed, this [Python installation guide](#) can guide you through the process.

2.2 From sources

The sources for aiovault can be downloaded from the [Github repo](#).

You can either clone the public repository:

```
$ git clone git://github.com/terrycain/aiovault
```

Or download the [tarball](#):

```
$ curl -OL https://github.com/terrycain/aiovault/tarball/master
```

Once you have a copy of the source, you can install it with:

```
$ python setup.py install
```


CHAPTER 3

Basic Usage

To get started with using vault you first need to import AIOVault and initialise a client. The client object can also be used as a context manager so it all can be used with the *with* statement.

```
import aiovault

with aiovault.VaultClient(token='6c84fb90-12c4-11e1-840d-7b25c5ee775a') as client:
    is_authed = await client.is_authenticated()
    print(is_authed) # True

    await client.secrets.generic.create('some_secret', key1='value1', key2='value2')
    secret = await client.secrets.generic.read('some_secret')

    print(secret['key1']) # value1
    print(secret['key2']) # value2
```


Contributions are welcome, and they are greatly appreciated! Every little bit helps, and credit will always be given. You can contribute in many ways:

4.1 Types of Contributions

4.1.1 Report Bugs

Report bugs at <https://github.com/terrycain/aiovault/issues>.

If you are reporting a bug, please include:

- Your operating system name and version.
- Any details about your local setup that might be helpful in troubleshooting.
- Detailed steps to reproduce the bug.

4.1.2 Fix Bugs

Look through the GitHub issues for bugs. Anything tagged with “bug” and “help wanted” is open to whoever wants to implement it.

4.1.3 Implement Features

Look through the GitHub issues for features. Anything tagged with “enhancement” and “help wanted” is open to whoever wants to implement it.

4.1.4 Write Documentation

aiovault could always use more documentation, whether as part of the official aiovault docs, in docstrings, or even on the web in blog posts, articles, and such.

4.1.5 Submit Feedback

The best way to send feedback is to file an issue at <https://github.com/terrycain/aiovault/issues>.

If you are proposing a feature:

- Explain in detail how it would work.
- Keep the scope as narrow as possible, to make it easier to implement.
- Remember that this is a volunteer-driven project, and that contributions are welcome :)

4.2 Get Started!

Ready to contribute? Here's how to set up *aiovault* for local development.

1. Fork the *aiovault* repo on GitHub.
2. Clone your fork locally:

```
$ git clone git@github.com:your_name_here/aiovault.git
```

3. Install your local copy into a virtualenv. Assuming you have virtualenvwrapper installed, this is how you set up your fork for local development:

```
$ mkvirtualenv aiovault
$ cd aiovault/
$ python setup.py develop
```

4. Create a branch for local development:

```
$ git checkout -b name-of-your-bugfix-or-feature
```

Now you can make your changes locally.

5. When you're done making changes, check that your changes pass flake8 and the tests, including testing other Python versions with tox:

```
$ flake8 aiovault tests
$ python setup.py test or py.test
$ tox
```

To get flake8 and tox, just pip install them into your virtualenv.

6. Commit your changes and push your branch to GitHub:

```
$ git add .
$ git commit -m "Your detailed description of your changes."
$ git push origin name-of-your-bugfix-or-feature
```

7. Submit a pull request through the GitHub website.

4.3 Pull Request Guidelines

Before you submit a pull request, check that it meets these guidelines:

1. The pull request should include tests.
2. If the pull request adds functionality, the docs should be updated. Put your new functionality into a function with a docstring, and add the feature to the list in README.rst.
3. The pull request should work for Python 2.6, 2.7, 3.3, 3.4 and 3.5, and for PyPy. Check https://travis-ci.org/terrycain/aiovault/pull_requests and make sure that the tests pass for all supported Python versions.

4.4 Tips

To run a subset of tests:

```
$ py.test tests.test_aiovault
```


5.1 Development Lead

- Terry Cain <terry@terrys-home.co.uk>

5.2 Contributors

None yet. Why not be the first?

6.1 1.1.1 (2017-11-16)

- Updated readme

6.2 1.1.0 (2017-11-16)

- Fixed verify=False bug

6.3 1.0.0 (2017-07-29)

- First stable release

6.4 0.2.0 (2017-07-20)

- Switched to use the dev version of Python 2.6
- Fixed link target in README
- Fixed typo in README code example
- Added AppRole authentication backend
- Added Transit secret backend
- Created test harness for running Vault in non dev mode
- Added Seal/Unseal, initialization and health methods

6.5 0.1.3 (2017-07-17)

- Fixed rendering of README on PyPI

6.6 0.1.2 (2017-07-17)

- Mostly repository maintenance.
- Updated requirements_dev.txt and setup.py
- Fixed issue where tox was not passing environment variables
- Limited coverage scope to the library not test suite

6.7 0.1.1 (2017-07-17)

- First release on PyPI.

CHAPTER 7

Indices and tables

- `genindex`
- `modindex`
- `search`