supervisorclusterctl Documentation

Release 0.1.1

Robert Winkler

Contents

1	installation	3
	.1 Control Machine Requirements	3
	.2 Managed Node Requirements	3
	3 Installing supervisorclusterctl	4
2	Jser Guide	5
	2.1 Running supervisorclusterctl	5
3	Contributing	7
	3.1 Types of Contributions	7
	3.2 Get Started!	8
	Pull Request Guidelines	
4	Authors	9
	Development Lead	9
	Contributors	9
5	Changes	11
	Changes 5.1 0.1.2	11
	5.2 0.1.1	
	53 010	11

supervisorclustered is a cmd line tool that allows to control a cluster of processes by utilizing Supervisor and Ansible.

The tool uses Ansible and Supervisor's supervisorctl to control remote Supervisor daemons (supervisord). The primary goal of supervisorclustered is to simplify the use of Ansible and Supervisor's supervisored by focusing on the most commonly used supervisored actions. The tool only works with Python 2.6 or 2.7, since Ansible does not work with Python 3 yet.

Contents 1

2 Contents

Installation

Topics

- Installation
 - Control Machine Requirements
 - Managed Node Requirements
 - Installing supervisorclusterctl
 - * Installing via pip
 - * Installing from source
 - * Create RPM package
 - * Installing from tarball or zipball

1.1 Control Machine Requirements

supervisorclusterctl requires Ansible to be installed on the control machine. You only need to install Ansible on one machine and it can control an entire fleet of remote nodes from that central point.

Currently Ansible can be run from any machine with Python 2.6 installed (Windows isn't supported for the control machine). This includes Red Hat, Debian, CentOS, OS X, any of the BSDs, and so on.

Ansible can be installed via "pip", the Python package manager. If 'pip' isn't already available in your version of Python, you can get pip by:

```
$ sudo easy_install pip
```

Then install Ansible with:

```
$ sudo pip install ansible
```

Note: Some Linux distributions offer a version of Ansible that is installable through the system package manager. Use the package management tools of your distribution to check availability.

1.2 Managed Node Requirements

supervisorclustered requires Supervisor to be installed on the remote nodes.

Supervisor can be installed via "pip":

```
$ sudo pip install supervisor
```

Note: Some Linux distributions offer a version of Supervisor that is installable through the system package manager. Use the package management tools of your distribution to check availability.

1.3 Installing supervisorclusterctl

1.3.1 Installing via pip

supervisorclusterctl can be installed via "pip":

```
$ sudo pip install supervisorclusterctl
```

1.3.2 Installing from source

supervisorclusterctl is trivially easy to install from source. No daemons or database setup are required.

To install from source:

```
$ git clone https://github.com/RobWin/supervisorclusterctl.git
$ cd ./supervisorclusterctl
$ sudo python setup.py install
```

1.3.3 Create RPM package

You can create a RPM package which can be used by many of popular Linux distributions, including Red Hat, SuSE:

```
$ sudo python setup.py bdist_rpm
```

1.3.4 Installing from tarball or zipball

A zipball or tarball of the source are available on the Project page.

User Guide

Topics

- User Guide
 - Running supervisorclusterctl

2.1 Running supervisorclusterctl

Now that you've installed supervisorclusterctl, it's time to get started with some basics.

Run help to see all available command-line commands, arguments and options

```
$ supervisorclusterctl -h
     usage: supervisorclusterctl [-h] [-v] [-s] [-V]
                                 host-pattern
                                 {status, reread, reload, update, start, stop, restart, remove}
     supervisorclusterctl is a cmd line tool that allows to control a cluster of
     processes by utilizing Supervisor and Ansible.
     positional arguments:
       host-pattern
                             A host-pattern usually refers to a group of hosts. For
                             more details, see Ansible documentation about
                             Patterns.
       {status, reread, reload, update, start, stop, restart, remove}
                             One of the available supervisorctl actions.
                             Get status info of all processes.
         status
         reread
                             Reread the configuration files of supervisord
         reload
                             Restart remote supervisord
                             Reload the configuration files of supervisord and
         update
                             add/remove processes as necessary
         start
                             Start a process by name
                             Stop a process by name
         stop
         restart
                             Restart a process by name
         remove
                             Remove a process by name
     optional arguments:
       -h, --help
                             show this help message and exit
       -v, --verbose
                             run in verbose mode (-vvv for more, -vvvv to enable
```

```
connection debugging)
-s, --sudo run supervisorctl actions with sudo (nopasswd))
-V, --version show program's version number and exit
```

Run subcommand help to see all available arguments and options of the subcommand

```
$ supervisorclusterctl production restart -h
    usage: supervisorclusterctl host-pattern start [-h] process-name

positional arguments:
    process-name Name of the process

optional arguments:
    -h, --help show this help message and exit
```

Now edit /etc/ansible/hosts and put one or more remote systems in it, for which you have your SSH key in authorized_keys:

```
[production]
192.168.0.11
192.168.0.12
[development]
192.168.0.10
```

This is an inventory file, which is explained in greater detail in Ansible's documentation

Run the supervisorclusterctl <host-pattern> status command to get the status of all Supervisor managed processes on all of your configured production nodes:

Now you are able to restart the managed_service process on all of your configured production nodes:

```
$ supervisorclusterctl production restart managed_service
    192.168.0.11 | success | rc=0 >>
    managed_service: stopped
    managed_service: started

192.168.0.12 | success | rc=0 >>
    managed_service: stopped
    managed_service: started
```

Contributing

Contributions are welcome, and they are greatly appreciated! Every little bit helps, and credit will always be given. You can contribute in many ways:

3.1 Types of Contributions

3.1.1 Report Bugs

Report bugs at https://github.com/RobWin/supervisorclusterctl/issues.

If you are reporting a bug, please include:

- Your operating system name and python version.
- Any details about your local setup that might be helpful in troubleshooting.
- Detailed steps to reproduce the bug.

3.1.2 Fix Bugs

Look through the GitHub issues for bugs. Anything tagged with "bug" is open to whoever wants to implement it.

3.1.3 Implement Features

Look through the GitHub issues for features. Anything tagged with "feature" is open to whoever wants to implement it.

3.1.4 Write Documentation

supervisorclustered could always use more documentation, whether as part of the official supervisorclustered docs, in docstrings, or even on the web in blog posts, articles, and such.

3.1.5 Submit Feedback

The best way to send feedback is to file an issue at https://github.com/RobWin/supervisorclusterctl/issues.

If you are proposing a feature:

- Explain in detail how it would work.
- Keep the scope as narrow as possible, to make it easier to implement.
- Remember that this is a volunteer-driven project, and that contributions are welcome:)

3.2 Get Started!

Ready to contribute? Here's how to set up *supervisorclusterctl* for local development.

- 1. Fork the *supervisorclusterctl* repo on GitHub.
- 2. Clone your fork locally:

```
$ git clone git@github.com:your_name_here/supervisorclusterctl.git
```

3. Install your local copy into a virtualenv. Assuming you have virtualenvwrapper installed, this is how you set up your fork for local development:

```
$ mkvirtualenv supervisorclusterctl
$ cd supervisorclusterctl/
$ python setup.py develop
```

4. Create a branch for local development:

```
$ git checkout -b name-of-your-bugfix-or-feature
```

Now you can make your changes locally.

5. When you're done making changes, check that your changes are working:

```
$ python setup.py test
```

6. Commit your changes and push your branch to GitHub:

```
$ git add .
$ git commit -m "Your detailed description of your changes."
$ git push origin name-of-your-bugfix-or-feature
```

7. Submit a pull request through the GitHub website.

3.3 Pull Request Guidelines

Before you submit a pull request, check that it meets these guidelines:

- 1. The pull request should include tests.
- 2. If the pull request adds functionality, the docs should be updated.
- 3. The pull request should work for Python 2.6 and 2.7. Check https://travis-ci.org/RobWin/supervisorclusterctl/pull_requests and make sure that the tests pass for all supported Python versions.

CHAPTER 4	4
-----------	---

Authors

4.1 Development Lead

• Robert Winkler <rbr/>brtwnklr@gmail.com>

4.2 Contributors

None yet. Why not be the first?

10 Chapter 4. Authors

Changes

5.1 0.1.2

• Fixed issue #1: reload not working

5.2 0.1.1

- supervisorclusterctl returns the return code of the ansible call now
- Added new unit tests and fixed the setup.py

5.3 0.1.0

• Initial release.