
AdafruitDRV2605 Library Documentation

Release 1.0

Tony DiCola

Aug 25, 2018

Contents

| | | |
|----------|----------------------------|-----------|
| 1 | Dependencies | 3 |
| 2 | Usage Example | 5 |
| 3 | Contributing | 7 |
| 4 | Building locally | 9 |
| 5 | Table of Contents | 11 |
| 5.1 | Simple test | 11 |
| 5.2 | adafruit_drv2605 | 12 |
| 6 | Indices and tables | 15 |
| | Python Module Index | 17 |

CircuitPython module for the DRV2605 haptic feedback motor driver.

CHAPTER 1

Dependencies

This driver depends on:

- [Adafruit CircuitPython](#)
- [Bus Device](#)

Please ensure all dependencies are available on the CircuitPython filesystem. This is easily achieved by downloading the [Adafruit library and driver bundle](#).

CHAPTER 2

Usage Example

See `examples/drv2605_simpletest.py` for a demo of the usage.

CHAPTER 3

Contributing

Contributions are welcome! Please read our [Code of Conduct](#) before contributing to help this project stay welcoming.

CHAPTER 4

Building locally

To build this library locally you'll need to install the `circuitpython-build-tools` package.

```
python3 -m venv .env
source .env/bin/activate
pip install circuitpython-build-tools
```

Once installed, make sure you are in the virtual environment:

```
source .env/bin/activate
```

Then run the build:

```
circuitpython-build-bundles --filename_prefix adafruit-circuitpython-drv2605 --
↳library_location .
```


5.1 Simple test

Ensure your device works with this simple test.

Listing 1: examples/drv2605_simpletest.py

```
1 # Simple demo of the DRV2605 haptic feedback motor driver.
2 # Will play all 117 effects in order for about a half second each.
3 # Author: Tony DiCola
4 import time
5
6 import board
7 import busio
8
9 import adafruit_drv2605
10
11
12 # Initialize I2C bus and DRV2605 module.
13 i2c = busio.I2C(board.SCL, board.SDA)
14 drv = adafruit_drv2605.DRV2605(i2c)
15
16 # Main loop runs forever trying each effect (1-117).
17 # See table 11.2 in the datasheet for a list of all the effect names and IDs.
18 # http://www.ti.com/lit/ds/symlink/drv2605.pdf
19 effect = 1
20 while True:
21     print('Playing effect #{0}'.format(effect))
22     drv.set_waveform(effect) # Select the effect on slot 0.
23     # Optionally you can assign effects to up to 7 different slots to combine
24     # them in interesting ways. Use the slot keyword and specify a slot 0 to 6
25     # (0 is the default).
26     #drv.set_waveform(effect, slot=1)
27     drv.play() # Play the effect.
```

(continues on next page)

(continued from previous page)

```

28     time.sleep(0.5)
29     # Increment effect ID and wrap back around to 1.
30     effect += 1
31     if effect > 117:
32         effect = 1

```

5.2 adafruit_drv2605

CircuitPython module for the DRV2605 haptic feedback motor driver. See `examples/simpletest.py` for a demo of the usage.

- Author(s): Tony DiCola

class `adafruit_drv2605.DRV2605` (*i2c, address=90*)
 TI DRV2605 haptic feedback motor driver module.

library

The library selected for waveform playback. Should be a value of:

- `LIBRARY_EMPTY`: Empty
- `LIBRARY_TS2200A`: TS2200 library A (the default)
- `LIBRARY_TS2200B`: TS2200 library B
- `LIBRARY_TS2200C`: TS2200 library C
- `LIBRARY_TS2200D`: TS2200 library D
- `LIBRARY_TS2200E`: TS2200 library E
- `LIBRARY_LRA`: LRA library

See the datasheet for the meaning and description of effects in each library.

mode

The mode of the chip. Should be a value of:

- `MODE_INTTRIG`: Internal triggering, vibrates as soon as you call `play()`. Default mode.
- `MODE_EXTTRIGEDGE`: External triggering, edge mode.
- `MODE_EXTTRIGLVL`: External triggering, level mode.
- `MODE_PWMANALOG`: PWM/analog input mode.
- `MODE_AUDIOVIBE`: Audio-to-vibration mode.
- `MODE_REALTIME`: Real-time playback mode.
- `MODE_DIAGNOS`: Diagnostics mode.
- `MODE_AUTOCAL`: Auto-calibration mode.

See the datasheet for the meaning of modes beyond `MODE_INTTRIG`.

`play()`

Play back the select effect(s) on the motor.

`set_waveform` (*effect_id, slot=0*)

Select an effect waveform for the specified slot (default is slot 0, but up to 7 effects can be combined with

slot values 0 to 6). See the datasheet for a complete table of effect ID values and the associated waveform / effect.

stop ()

Stop vibrating the motor.

use_ERM ()

Use an eccentric rotating mass motor (the default).

use_LRM ()

Use a linear resonance actuator motor.

CHAPTER 6

Indices and tables

- `genindex`
- `modindex`
- `search`

Python Module Index

a

[adafruit_drv2605](#), 12

A

adafruit_drv2605 (module), [12](#)

D

DRV2605 (class in adafruit_drv2605), [12](#)

L

library (adafruit_drv2605.DRV2605 attribute), [12](#)

M

mode (adafruit_drv2605.DRV2605 attribute), [12](#)

P

play() (adafruit_drv2605.DRV2605 method), [12](#)

S

set_waveform() (adafruit_drv2605.DRV2605 method),
[12](#)

stop() (adafruit_drv2605.DRV2605 method), [13](#)

U

use_ERM() (adafruit_drv2605.DRV2605 method), [13](#)

use_LRM() (adafruit_drv2605.DRV2605 method), [13](#)