

---

# **minispec Documentation**

***Release 0.1.1***

**The minispec development team**

**Feb 28, 2019**



---

## Contents

---

<b>1</b>	<b>Getting started</b>	<b>3</b>
<b>2</b>	<b>Troubleshooting</b>	<b>5</b>
<b>3</b>	<b>API documentation</b>	<b>7</b>
<b>4</b>	<b>Advanced topics</b>	<b>9</b>
<b>5</b>	<b>Reference</b>	<b>11</b>



minispec is a minimal module for computing audio spectrograms.



## 1.1 Installation instructions

### 1.1.1 pypi

The simplest way to install *minispec* is through the Python Package Index (PyPI). This will ensure that all required dependencies are fulfilled. This can be achieved by executing the following command:

```
pip install minispec
```

or:

```
sudo pip install minispec
```

to install system-wide, or:

```
pip install -u minispec
```

to install just for your own user.

### 1.1.2 Source

If you've downloaded the archive manually from the [releases](#) page, you can install using the `setuptools` script:

```
tar xzf minispec-VERSION.tar.gz
cd minispec-VERSION/
python setup.py install
```

If you intend to develop *minispec* or make changes to the source code, you can install with `pip install -e` to link to your actively developed source tree:

```
tar xzf minispec-VERSION.tar.gz
cd minispec-VERSION/
pip install -e .
```

Alternately, the latest development version can be installed via pip:

```
pip install git+https://github.com/minispec/minispecbrew install ffmpeg` or get a ↪
↪binary version from their website https://www.ffmpeg.org.
```



## CHAPTER 2

---

### Troubleshooting

---

If you have questions about how to use minispec, please consult the [discussion forum](#). For bug reports and other, more technical issues, consult the [github issues](#).



## CHAPTER 3

---

API documentation

---



## CHAPTER 4

---

Advanced topics

---



## 5.1 Changelog

### 5.1.1 v0.1.1

2019-02-28

Merge minispec with librosa v0.6.3

### 5.1.2 v0.1.0

2018-11-29

Initial release.

## 5.2 Glossary

**time series** Typically an audio signal, denoted by  $y$ , and represented as a one-dimensional *numpy.ndarray* of floating-point values.  $y[t]$  corresponds to amplitude of the waveform at sample  $t$ .

**sampling rate** The (positive integer) number of samples per second of a time series. This is denoted by an integer variable `sr`.

**frame** A short slice of a *time series* used for analysis purposes. This usually corresponds to a single column of a spectrogram matrix.

**window** A vector or function used to weight samples within a frame when computing a spectrogram.

**frame length** The (positive integer) number of samples in an analysis window (or *frame*). This is denoted by an integer variable `n_fft`.

**hop length** The number of samples between successive frames, e.g., the columns of a spectrogram. This is denoted as a positive integer `hop_length`.

**window length** The length (width) of the window function (e.g., Hann window). Note that this can be smaller than the *frame length* used in a short-time Fourier transform. Typically denoted as a positive integer variable `win_length`.

**spectrogram** A matrix `S` where the rows index frequency bins, and the columns index frames (time). Spectrograms can be either real-valued or complex-valued. By convention, real-valued spectrograms are denoted as *numpy.ndarrays* `S`, while complex-valued STFT matrices are denoted as `D`.

**onset (strength) envelope** An onset envelope `onset_env[t]` measures the strength of note onsets at frame `t`. Typically stored as a one-dimensional *numpy.ndarray* of floating-point values `onset_envelope`.

**chroma** Also known as pitch class profile (PCP). Chroma representations measure the amount of relative energy in each pitch class (e.g., the 12 notes in the chromatic scale) at a given frame/time.

- `genindex`



## C

chroma, [12](#)

## F

frame, [11](#)

frame length, [11](#)

## H

hop length, [11](#)

## O

onset (strength) envelope, [12](#)

## S

sampling rate, [11](#)

spectrogram, [12](#)

## T

time series, [11](#)

## W

window, [11](#)

window length, [12](#)